

LY33-9101-0
File No. S370/4300-40

Program Product

**VSE/Advanced Functions
Handbook**

Program Number 5746-XE8

Release 2

IBM

Preface

This manual, although a -0 suffix edition, is actually a major revision of the publication DOS/VSE Handbook, SY33-5871-7. The manual is provided as a VSE/Advanced Function, Release 2, serviceability aid and is a summary of other VSE/Advanced Functions Release 2 documentation.

Note: For reasons of brevity, the product name "VSE/Advanced Functions" is referred to in this publication as VSE/AF.

The volume contains following information:

- Chapter I: General Information
- II: VSE/AF General Information
- III: VSE/AF IOCS (General, SAM, DAM, ISAM)
- IV: VSE/AF Supervisor Control Blocks and Areas
- V: VSE/AF Service Aids

If there is any discrepancy between the information contained in this manual and the optional programming material for the product (e.g. Diagnosis Reference publications), the latter is assumed to be correct.

Separate handbooks are available for related program products as follows:

- VSE/POWER handbook: LY33-9094
- VSE/PCPS handbook: LY33-9095
- VSE/ICCF handbook: LY33-9096

A handbook-sized binder, FE Part Number 453 559, may be purchased from IBM. Customers may order it by their IBM marketing representative. IBM personnel should order it as an FE part from Mechanicsburg.

First Edition (June 1980)

This edition applies to Release 2 of VSE/Advanced Functions, Program Number 5746-XE8, with the required DOS/VSE SCP, Program Number 5745-030, and to all subsequent versions and releases until otherwise indicated in new editions or Technical Newsletters. Changes are continually made to the information herein; before using this publication in connection with the operation of IBM systems, consult the latest *IBM System/370 and 4300 Processor Bibliography*, GC20-0001, for the editions that are applicable and current.

It is possible that this material may contain reference to, or information about, IBM products (machines and programs), programming, or services that are not announced in your country. Such references or information must not be constructed to mean that IBM intends to announce such IBM products, programming, or services in your country.

Publications are not stocked at the addresses given below; requests for copies of IBM publications should be made to your IBM representative or to the IBM branch office serving your locality.

A form for reader's comments is provided at the back of this publication. If the form has been removed, comments may be addressed either to WT-DP/CE Technical Operations, Schoenaicher Strasse 220, D-7030 Boeblingen, Germany.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation whatever. You may, of course, continue to use the information you supply.

TABLE OF CONTENTS

Chapter I General Information

Machine Instructions	01
Extended MNEMONIC Instruction Codes	04
Assembler Instructions	05
Condition Codes	06
Code Translation Table	08
Machine Instructions Formats	12
Control Register Allocation	13
Assignment of Control Register Field	13
Permanent Main Storage Assignment	14
Program Status Word (PSW)	16
Channel Address Word (CAW)	17
Channel Command Word (CCW)	17
Channel Status Word (CSW)	17
Limited Channel Logout	18
Machine Check Interruption Code	18
Codes for Program Interruptions	19
Codes for External Interruptions	19
Codes for Input/Output Interruptions	19
Codes for Supervisor Call Interruptions	19
Channel Commands	19
Hexadecimal and Decimal Conversion	23
Sense Information Summary	24

Chapter II DOS/VSE General Information

IPL Control Statements	01
Job Control and Attention Routine Commands	06
Linkage Editor Control Statements	23
Librarian	25
ESERV	35
LSERV,LVTOC	37
Supervisor Macros	38
Device Type Codes	42
Format of ESD CARD	44
TXT CARD	44
RLD CARD	45
END CARD	45
REP CARD	45

Chapter III DOS/VSE IOCS (General/SAM/DAM/ISAM)

Standard Volume Label, Tape	01
Standard Volume Label, Tape ASCII	02
Standard Magnetic Tape File Label	03
Standard Volume Label, DASD	07
Standard DASD File Label, Format 1	09
Standard DASD File Label, Format 2	13
Standard DASD File Label, Format 3	17
Standard DASD File Label, Format 4	18
Standard Diskette Volume Label 1	21
Standard Diskette HDR 1 Label	22
DATA Management and System Control Macros	23
LIOCS Module Name Versus Options	35
DTFCD (Reader)	41
DTFCD (Punch)	44
DTFCD (Comb. Reader/Punch)	46
DTFPR	47
DTFCN	49
DTFDR	50
DTFOR	51
DTFMR	53
DTFMT (DATA Files)	56
DTFMT (Workfiles)	64
DTFSD (Data Files)	65
DTFSD (Workfiles)	70
DTFDA	72
DTFDA Extension	77

TABLE OF CONTENTS (. . . Cont'd)

Chapter III (Cont'd)

DTFIS (LOAD)	79
DTFIS (Add)	83
DTFIS (Retrve, Random)	89
DTFIS (Retrve, Seqntl)	93
DTFIS (Addrtr)	96
DTFDU	103
DTFPH (Magnetic Tape)	105
DTFPH (Sequential Disk)	106
DTFPH (DAM Files)	108
DTFPH (Diskette)	109
DTFDI	111
DTFCP (Disk=Yes)	113
DTFCP (Disk=No)	116
DTFCP (Disk=Parameter omitted)	118
DTF-Table Types	119
RPS DTF/Module Relationship	120
RPS DTF-Extension	121

Chapter IV DOS/VSE Supervisor Control and Areas

Supervisor Storage Allocation	01
Supervisor Calls	03
Command Control Block (CCB)	07
Input/Output Request Block (IORB)	10
Storage Management Control Block (SMCB)	12
System Control Program Communication Region (SYSCOM)	13
Partition Communication Region (COMREG)	17
Logical Transient Owner Identifier (LTID)	25
Logical Transient Key (LTK)	25
I/O Requestors Partition or System Task ID (REQID)	25
RAS Linkage Area	26
Define the Lock (DTL)	27
Locktab Entry	27
Owner Element	27
Partition Control Blocks Interrelationship	28
Partition Control Block (PCB)	29
Program Information Block (PIB)	30
Program Information Block Extension (PIB 2 TAB)	31
Save Areas	32
I/O Table Interrelationship	33
Logical Unit Block (LUB)	34
Storage Protection Key, Partition Identification Key (PIK)	35
Task Identifier (TID)	35
Relationship of Fetch/Load Control Blocks	36
Job Information Block (JIB)	37
Channel Queue Table (CHANQ)	38
Channel Control Table (CHNTAB)	39
Track Hold Table (THTAB)	40
Console Buffering Table	40
Line Mode Table	41
Relationship of Control and Workblocks for Channel Program Fixing	42
Fixlist Header Block (FHB) Layout	43
Fix Request Block (FRB)	44
Fix list Block (FLB) Layout	44
Locate List Block, Layout	45
Line Pointer Blocks, Layout	45
Density Data	46
Event Control Block (ECB)	47
Resource Control Block (RCB)	47
Cross Partition ECB (XECB) Table	47
Disk Information Block (DIB) Table	48
MICR DTF Addresses and Pointers (PDTABB, PDTABA)	50
Error Recovery Procedure Information Block (ERPIB)	51
Error Recovery Block and Error Queue Entry (ERBLOC)	52
Cancel Codes and Messages	53

TABLE OF CONTENTS (. . . Cont'd)

Chapter IV Cont'd

Physical Unit Block (PUB)	55
Physical Unit Block Ownership Table	56
PUB2 Entry Addressing	57
PUB2 Table	58
Recorder File Table (RF TABLE)	62
Task Information Block (TIB)	64
Task Control Block (TCB)	65
Partition Selection String (PSS)	66
Partition Identifier String (PIDSTR)	66
PCB Address Table (PCBATAB)	66
Task Selection String (TSS)	66
Internal Resource Table (RETAB)	66
Task Identifier String (TIDSTR)	67
TIB Address Table (TIBATAB)	67
Task Selection Control Block Interrelationship	68
Task Status Flags and Resource Gates	69
Job Accounting Interface Common Table	71
Job Accounting Interface Partition Table	72
ASCII ABCDIC Translation Tables	73
Segment and Page Table	78
Page Data Set Table (DPDTAB)	79
Task Timer Table (TTTAB)	80
Interval Timer Request Entry in TCB	80
Page Out Queue Entry (PGQUO)	80
Page Frame Table Entry (PFTE)	81
PAGETAB	82
Translation Control Block (CCWTCB)	83
Copy Blocks	84
Replica Block, Didal Block and Entry	87
Converting Virtual to Real Address	88
Page Data Set Format	89
Replica Header Blocks, Layout	90
Layout of Shared Virtual Area (SVA)	91
Layout of Directory Entry	92
Routine Identifiers (RID)	93
VTAM Address Vector Table (ISTAVT)	94
Entry in the Asynchronous Process Scheduler Option Table	94
Anchor Table (ANCHTAB)	95
CRT Constant Table (CRTTAB)	96

Chapter V DOS/VSE Service Aids

OLTEP	01
EREP	04
SDAID	11
Tracing of 4331 Communication Adapter Events	17
Hard and Soft Wait Codes	18
Error Bytes and Informations in Low Real Storage	20
PDZAP	21
DOSVSDMP and Standalone Dump	23
DOSVSDMP Hard Wait Codes	26
MSHP	27

CHAPTER I
GENERAL INFORMATION

CHAPTER II
VSE/AF2 GENERAL INFORMATION

CHAPTER III
VSE/AF2 IOCS (GENERAL/SAM/DAM/ISAM)

CHAPTER IV
VSE/AF2 SUPERVISOR CONTROL BLOCKS AND AREAS

CHAPTER V
VSE/AF2 SERVICE AIDS

CHAPTER I
GENERAL INFORMATION



MACHINE INSTRUCTIONS

General Instructions:

<u>Name</u>	<u>Mnemonic</u>	<u>Op Code</u>	<u>Format</u>	<u>Operands</u>
Add (c)	AR	1A	RR	R1,R2
Add (c)	A	5A	RX	R1,D2(X2,B2)
Add Halfword (c)	AH	4A	RX	R1,D2(X2,B2)
Add Logical (c)	ALR	1E	RR	R1,R2
Add Logical (c)	AL	5E	RX	R1,D2(X2,B2)
AND (c)	NR	14	RR	R1,R2
AND (c)	N	54	RX	R1,D2(X2,B2)
AND (c)	NI	94	SI	D1(B1),I2
AND (c)	Nc	D4	SS	D1(L,B1),D2(B2)
Branch and Link	BALR	05	RR	R1,R2
Branch and Link	BAL	45	RX	R1,D2(X2,B2)
Branch on Condition	BCR	07	RR	M1,R2
Branch on Condition	BC	47	RX	M1,D2(X2,B1)
Branch on Count	BCTR	06	RR	R1,R2
Branch on Count	BCT	46	RX	R1,D2(X2,B2)
Branch on Index High	BXH	86	RS	R1,R3,D2(B2)
Branch on Index Low or Equal	BXLE	87	RS	R1,R3,D2(B2)
Compare (c)	CR	19	RR	R1,R2
Compare (c)	C	59	RX	R1,D2(X2,B2)
Compare and Swap	CS	BA	RS	R1,R3,D2(B2)
Compare Double and Swap	CDS	BB	RS	R1,R3,D2(B2)
Compare Halfword (c)	CH	49	RX	R1,D2(X2,B2)
Compare Logical (c)	CLR	15	RR	R1,R2
Compare Logical (c)	CL	55	RX	R1,D2(X2,B2)
Compare Logical (c)	CLC	D5	SS	D1(L,B1),D2(B2)
Compare Logical (c)	CLI	95	SI	D1(B1),I2
Compare Logical Characters under Mask (c)	CLM	BD	RS	R1,M3,D2(B2)
Compare Logical Long (c)	CLCL	0F	RR	R1,R2
Convert to Binary	CVB	4F	RX	R1,D2(X2,B2)
Convert to Decimal	CVD	4E	RX	R1,D2(X2,B2)
Divide	DR	1D	RR	R1,R2
Divide	D	5D	RX	R1,D2(X2,B2)
Exclusive OR (c)	XR	17	RR	R1,R2
Exclusive OR (c)	X	57	RX	R1,D2(X2,B2)
Exclusive OR (c)	XI	97	SI	D1(B1),I2
Exclusive OR (c)	XC	D7	SS	D1(L,B1),D2(B2)
Execute	EX	44	RX	R1,D2(X2,B2)
Insert Character	IC	43	RX	R1,D2(X2,B2)
Insert Characters under Mask (c)	ICM	BF	RS	R1,M3,D2(B2)
Load	LR	18	RR	R1,R2
Load	L	58	RX	R1,D2(X2,B2)
Load Address	LA	41	RX	R1,D2(X2,B2)
Load and Test (c)	LTR	12	RR	R1,R2
Load Complement (c)	LCR	13	RR	R1,R2
Load Halfword	LH	48	RX	R1,D2(X2,B2)
Load Multiple	LM	98	RS	R1,R3,D2(B2)
Load Negative (c)	LNR	11	RR	R1,R2
Load Positive (c)	LPR	10	RR	R1,R2
Monitor Call (m)	MC	AF	SI	D1(B1),I2
Move	MVI	92	SI	D1(B1),I2
Move	MVC	D2	SS	D1(L,B1),D2(B2)
Move Inverse	MVCIN	E8	SS	D1(L,B1),D2(B2)
Move Long (c)	MVCL	0E	RR	R1,R2
Move Numerics	MVN	D1	SS	D1(L,B1),D2(B2)
Move with Offset	MVO	F1	SS	D1(L1,B1),D2(L2,B2)
Move Zones	MVZ	D3	SS	D1(L,B1),D2(B2)
Multiply	MR	1C	RR	R1,R2
Multiply	M	5C	RX	R1,D2(X2,B2)
Multiply Halfword	MH	4C	RX	R1,D2(X2,B2)
OR (c)	OR	16	RR	R1,R2
OR (c)	O	56	RX	R1,D2(X2,B2)
OR (c)	OI	96	SI	D1(B1),I2
OR (c)	OC	D6	SS	D1(L,B1),D2(B2)
Pack	PACK	F2	SS	D1(L1,B1),D2(L2,B2)
Set Program Mask (n)	SPM	04	RR	R1
Shift Left Double (c)	SLDA	8F	RS	R1,D2(B2)

MACHINE INSTRUCTIONS (. . . Cont'd)

General Instructions:

Name	Mnemonic	Op Code	Format	Operands
Shift Left Double Logical	SLDL	8D	RS	R1,D2(B2)
Shift Left Single (c)	SLA	8B	RS	R1,D2(B2)
Shift Left Single Logical	SLL	89	RS	R1,D2(B2)
Shift Right Double (c)	SRDA	8E	RS	R1,D2(B2)
Shift Right Double Logical	SRDL	8C	RS	R1,D2(B2)
Shift Right Single (c)	SRA	8A	RS	R1,D2(B2)
Shift Right Single Logical	SRL	88	RS	R1,D2(B2)
Store	ST	50	RX	R1,D2(X2,B2)
Store Character	STC	42	RX	R1,D2(X2,B2)
Store Characters under Mask	STCM	BE	RS	R1,M3,D2(B2)
Store Clock (c)	STCK	B205	S	D2(B2)
Store Halfword	STH	40	RX	R1,D2(X2,B2)
Store Multiple	STM	90	RS	R1,R3,D2(B2)
Subtract (c)	SR	1B	RR	R1,R2
Subtract (c)	S	5B	RX	R1,D2(X2,B2)
Subtract Halfword (c)	SH	4B	RX	R1,D2(X2,B2)
Subtract Logical (c)	SLR	1F	RR	R1,R2
Subtract Logical (c)	SL	5F	RX	R1,D2(X2,B2)
Supervisor Call	SVC	0A	RR	I
Test and Set (c)	TS	93	S	D2(B2)
Test under Mask (c)	TM	91	SI	D1(B1),I2
Translate	TR	DC	SS	D1(L,B1),D2(B2)
Translate and Test (c)	TRT	DD	SS	D1(L,B1),D2(B2)
Unpack	UNPK	F3	SS	D1(L1,B1),D2(L2,B2)

Decimal Instructions:

Add Decimal (c)	AP	FA	SS	D1(L1,B1),D2(L2,B2)
Compare Decimal (c)	CP	F9	SS	D1(L1,B1),D2(L2,B2)
Divide Decimal	DP	FD	SS	D1(L1,B1),D2(L2,B2)
Edit (c)	ED	DE	SS	D1(L,B1),D2(B2)
Edit and Mark (c)	EDMK	DF	SS	D1(L,B1),D2(B2)
Multiply Decimal	MP	FC	SS	D1(L1,B1),D2(L2,B2)
Shift and Round Decimal (c)	SRP	F0	SS	D1(L1,B1),D2(B2),I3
Subtract Decimal (c)	SP	FB	SS	D1(L1,B1),D2(L2,B2)
Zero and Add Decimal (c)	ZAP	F8	SS	D1(L1,B1),D2(L2,B2)

Control Instructions:

Clear Page	CLRP	B215	S	D2(B2)
Connect Page	CTP	80	RS	R1,D2(B2)
Deconfigure Page	DEP	B21B	S	D2(B2)
Diagnose (p)		83	SI or RS	
Disconnect Page	DCTP	B21C	S	D2(B2)
Insert Page Bits	IPB	84	RS	R1,D2(B2)
Insert Storage Key (p)	ISK	09	RR	R1,R2
Insert PSW Key	IPK	B20B	S	
Load Control (p)	LCTL	87	RS	R1,R3,D2(B2)
Load Frame Index	LFI	88	RS	R1,D2(B2)
Load PSW (n,p)	LPSW	82	S	D2(B2)
Make Addressable	MAD	B21D	S	D2(B2)
Make Unaddressable	MUN	B21E	S	D2(B2)
Reset Reference Bit (c,p)	RRB	B213	S	D2(B2)
Retrieve Status and Page	RSP	D8	SS	D1(B1),D2(B2)
Set Clock (c,p)	SCK	B204	S	D2(B2)
Set Clock Comparator (p)	SCKC	B206	S	D2(B2)
Set CPU Timer (p)	SPT	B208	S	D2(B2)
Set Page Bits	SPB	85	RS	R1,D2(B2)
Set Storage Key (p)	SSK	08	RR	R1,R2
Set PSW Key from Address	SPKA	B20A	S	D2(B2)
Set System Mask (p)	SSM	80	S	D2(B2)
Store Capacity Counts	STCAP	B21F	S	D2(B2)
Store Clock Comparator (p)	STCKC	B207	S	D2(B2)
Store Control (p)	STCTL	86	RS	R1,R3,D2(B2)
Store CPU ID (p)	STIDP	B202	S	D2(B2)
Store CPU Timer (p)	STPT	B209	S	D2(B2)
Store then AND System Mask (p)	STNSM	AC	SI	D1(B1),I2
Store then OR System Mask (p)	STOSM	AD	SI	D1(B1),I2

MACHINE INSTRUCTIONS (. . . Cont'd)

I/O Instructions:

<u>Name</u>	<u>Mne- monic</u>	<u>Op Code</u>	<u>Format</u>	<u>Operands</u>
Clear I/O	CIRIO	9D01	S	D2(B2)
Halt I/O (c,p)	HIO	9E00	S	D2(B2)
Halt Device (c,p)	HDV	9E01	S	D2(B2)
Start I/O (c,p)	SIO	9C00	S	D2(B2)
Start I/O Fast Release (c,p)	SIOF	9C01	S	D2(B2)
Store Channel ID (c,p)	STIDC	B203	S	D2(B2)
Test Channel (c,p)	TCH	9F00	S	D2(B2)
Test I/O (c,p)	TIO	9D00	S	D2(B2)

Floating Point Instructions:

Add Normalized, Extended (c,x)	AXR	36	RR	R1,R2
Add Normalized, Long (c)	ADR	2A	RR	R1,R2
Add Normalized, Long (c)	AD	6A	RX	R1,D2(X2,B2)
Add Normalized, Short (c)	AER	3A	RR	R1,R2
Add Normalized, Short (c)	AE	7A	RX	R1,D2(X2,B2)
Add Unnormalized, Long (c)	AWR	2E	RR	R1,R2
Add Unnormalized, Long (c)	AW	6E	RX	R1,D2(X2,B2)
Add Unnormalized, Short (c)	AUR	3E	RR	R1,R2
Add Unnormalized, Short (c)	AU	7E	RX	R1,D2(X2,B2)
Compare, Long (c)	CDR	29	RR	R1,R2
Compare, Long (c)	CD	69	RX	R1,D2(X2,B2)
Compare, Short (c)	CER	39	RR	R1,R2
Compare, Short (c)	CE	79	RX	R1,D2(X2,B2)
Divide, Long	DDR	2D	RR	R1,R2
Divide, Long	DD	6D	RX	R1,D2(X2,B2)
Divide, Short	DER	3D	RR	R1,R2
Divide, Short	DE	7D	RX	R1,D2(X2,B2)
Halve, Long	HDR	24	RR	R1,R2
Halve, Short	HER	34	RR	R1,R2
Load and Test, Long (c)	LTDR	22	RR	R1,R2
Load and Test, Short (c)	LTER	32	RR	R1,R2
Load Complement, Long (c)	LCDR	23	RR	R1,R2
Load Complement, Short (c)	LCER	33	RR	R1,R2
Load, Long	LDR	28	RR	R1,R2
Load, Long	LD	68	RX	R1,D2(X2,B2)
Load Negative, Long (c)	LNDR	21	RR	R1,R2
Load Negative, Short (c)	LNDR	31	RR	R1,R2
Load Positive, Long (c)	LPDR	20	RR	R1,R2
Load Positive, Short (c)	LPER	30	RR	R1,R2
Load Rounded, Extended to Long (x)	LRDR	25	RR	R1,R2
Load Rounded, Long to Short (x)	LRER	35	RR	R1,R2
Load, Short	LER	38	RR	R1,R2
Load, Short	LE	78	RX	R1,D2(X2,B2)
Multiply, Extended (x)	MXR	26	RR	R1,R2
Multiply, Long	MDR	2C	RR	R1,R2
Multiply, Long	MD	6C	RX	R1,D2(X2,B2)
Multiply, Long/Extended (x)	MXDR	27	RR	R1,R2
Multiply, Long/Extended (x)	MXD	67	RX	R1,D2(X2,B2)
Multiply, Short	MER	3C	RR	R1,R2
Multiply, Short	ME	7C	RX	R1,D2(X2,B2)
Store, Long	STD	60	RX	R1,D2(X2,B2)
Store, Short	STE	70	RX	R1,D2(X2,B2)
Subtract Normalized, Ext'd (c,x)	SXR	37	RR	R1,R2
Subtract Normalized, Long (c)	SDR	2B	RR	R1,R2
Subtract Normalized, Long (c)	SD	6B	RX	R1,D2(X2,B2)
Subtract Normalized, Short (c)	SER	3B	RR	R1,R2
Subtract Normalized, Short (c)	SE	7B	RX	R1,D2(X2,B2)
Subtract Unnormalized, Long (c)	SWR	2F	RR	R1,R2
Subtract Unnormalized, Long (c)	SW	6F	RX	R1,D2(X2,B2)
Subtract Unnormalized, Short (c)	SUR	3F	RR	R1,R2
Subtract Unnormalized, Short (c)	SU	7F	RX	R1,D2(X2,B2)

(a) Direct Control Feature
(c) Condition Code is set
(m) Monitoring Feature

(n) New Condition Code is loaded
(p) Privileged Instruction
(x) Extended precision floating point feature

EXTENDED MNEMONIC INSTRUCTION CODES

GENERAL

Extended Code	Machine Instruction	Meaning
B D2(X2,B2)	BC 15, D2(X2,B2)	Branch Unconditionally
BR R2	BCR 15, R2	Branch Unconditionally
NOP D2(X2,B2)	BC 0, D2(X2,B2)	No Operation
NOPR R2	BCR 0, R2	No Operation (RR)

AFTER COMPARE INSTRUCTIONS (A:B)

BH D2(X2,B2)	BC 2, D2(X2,B2)	Branch on A High
BL D2(X2,B2)	BC 4, D2(X2,B2)	Branch on A Low
BE D2(X2,B2)	BC 8, D2(X2,B2)	Branch on A equal B
BNH D2(X2,B2)	BC 13, D2(X2,B2)	Branch on A not High
BNL D2(X2,B2)	BC 11, D2(X2,B2)	Branch on A not Low
BNE D2(X2,B2)	BC 7, D2(X2,B2)	Branch on A not Equal B


AFTER ARITHMATIC INSTRUCTIONS

BO D2(X2,B2)	BC 1, D2(X2,B2)	Branch on Overflow
BP D2(X2,B2)	BC 2, D2(X2,B2)	Branch on Plus
BM D2(X2,B2)	BC 4, D2(X2,B2)	Branch on Minus
BZ D2(X2,B2)	BC 8, D2(X2,B2)	Branch on Zero
BNP D2(X2,B2)	BC 13, D2(X2,B2)	Branch on not Plus
BNM D2(X2,B2)	BC 11, D2(X2,B2)	Branch on not Minus
BNZ D2(X2,B2)	BC 7, D2(X2,B2)	Branch on not Zero

AFTER TEST UNDER MASK INSTRUCTIONS

BO D2(X2,B2)	BC 1, D2(X2,B2)	Branch if Ones
BM D2(X2,B2)	BC 4, D2(X2,B2)	Branch if Mixed
BZ D2(X2,B2)	BC 8, D2(X2,B2)	Branch if Zero's
BNO D2(X2,B2)	BC 14, D2(X2,B2)	Branch if not Ones

CNOP ALIGNMENT



EDIT AND EDMK PATTERN CHARACTERS (In Hex)

20 – Digit selector	40 – Blank	5C – Aterisk
21 – Start of significance	4B – Period	6B – Comma
22 – Field separator	5B – Dollar sign	C3D9 – CR

ASSEMBLER INSTRUCTIONS

<u>Function</u>	<u>Mnemonic</u>	<u>Meaning</u>
Data Definition	DC	Define Constant
	DS	Define Storage
	CCW	Define Channel Command Word
Program Sectioning and Linking	START	Start Assembly
	CSECT	Identify Control Section
	DSECT	Identify Dummy Section
	COM	Identify blank common Control Section
	ENTRY	Identify Entry Point Symbol
	EXTRN	Identify External Symbol
Base Register Assignment	USING	Use Base Address Register
	DROP	Drop Base Address Register
Control of listings	TITLE	Identify Assembly Output
	EJECT	Start new Page
	SPACE	Space Listing
	PRINT	Print Optional Data
Program Control	ICTL	Input Format Control
	ISEQ	Input Sequence Checking
	PUNCH	Punch a Card
	REPRO	Reproduce following Card
	ORG	Set Location Counter
	EQU	Equate Symbol
	LTORG	Begin Literal Pool
	CNOP	Conditional No-Operation
	COPY	Copy predefined Source Coding
	END	End Assembly
	Macro Definition	MACRO
MNOTE		Request for Error Message
MEXIT		Macro Definition Exit
MEND		Macro Definition Trailer
Conditional Assembly	ACTR	Conditional Assembly Loop Counter
	AGO	Unconditional Branch
	AIF	Conditional Branch
	ANOP	Assembly No-Operation
	GBLA	Define global SETA Symbol
	GBLB	Define global SETB Symbol
	GBLC	Define global SETC Symbol
	LCLA	Define local SETA Symbol
	LCLB	Define local SETB Symbol
	LCLC	Define local SETC Symbol
	SETA	Set Arithmetic Variable Symbol
	SETB	Set Arithmetic
	SETC	Set Character Variable Symbol

SUMMARY OF CONSTANTS

Type	Implied Length Bytes	Alignment	Format	Truncation Padding
C	—	Byte	Characters	Right
X	—	Byte	Hexadecimal Digits	Left
B	—	Byte	Binary Digits	Left
F	4	Word	Fixed-point Binary	Left
H	2	Halfword	Fixed-point Binary	Left
E	4	Word	Short Floating-point	Right
D	8	Doubleword	Long Floating-point	Right
L	16	Doubleword	Extended Floating-point	Right
P	—	Byte	Packed Decimal	Left
Z	—	Byte	Zoned Decimal	Left
A	4	Word	Value of Address	Left
Y	2	Halfword	Value of Address	Left
S	2	Halfword	Address in Base-Displacement form	—
V	4	Word	Externally defined Address Value	Left

CONDITION CODES

Condition Code Setting Mask Bit Position	0 8	1 4	2 2	3 1
<u>Floating Point Arithmetic</u>				
Add Normalized S/L/E	zero	<zero	>zero	—
Add Unnormalized S/L	zero	<zero	>zero	—
Compare S/L (A:B)	equal	A low	A high	—
Load and Test S/L	zero	<zero	>zero	—
Load Complement S/L	zero	<zero	>zero	—
Load Negative S/L	zero	<zero	—	—
Load Positive S/L	zero	—	>zero	—
Subtract Normalized S/L/E	zero	<zero	>zero	—
Subtract Unnormalized S/L	zero	<zero	>zero	—
<u>Fixed Point and Decimal Arithmetic</u>				
Add H/F/Dec.	zero	<zero	>zero	overflow
Add Logical	zero, no carry	not zero, no carry	zero, carry	not zero, carry
Compare H/F/Dec. (A:B)	equal	A low	A high	—
Compare and Swap/Double	equal	not equal	—	—
Compare Logical	equal	A low	A high	—
Compare Logical Characters under Mask	equal	A low	A high	—
Load and Test	zero	<zero	>zero	—
Load Complement	zero	<zero	>zero	overflow
Load Negative	zero	<zero	—	—
Load Positive	zero	—	>zero	overflow
Shift and Round Decimal	zero	<zero	>zero	overflow
Shift Left Single/Double	zero	<zero	>zero	overflow
Shift Right Single/Double	zero	<zero	>zero	—
Subtract H/F/Dec.	zero	<zero	>zero	overflow
Subtract Logical	—	not zero, no carry	zero, carry	not zero, carry
Zero and Add	zero	<zero	>zero	overflow
<u>Logical Operations</u>				
AND	zero	not zero	—	—
Compare Logical (A:B)	equal	A low	A high	—
Edit	zero	<zero	>zero	—
Edit and Mask	zero	<zero	>zero	—
Exclusive OR	zero	not zero	—	—
Insert Characters under Mask	all zero	1 st bit one	1 st bit zero	—
Move Long (A:B)	equal	A low	A high	overlap
OR	zero	not zero	—	—
Test under Mask	all zeros	mixed	—	all ones
Translate and Test	zero	incomplete	complete	—
<u>Input/Output Operations</u>				
Clear I/O	no oper in interruption	CSW stored	chan busy	not oper
Halt Device	pending/busy	CSW stored	channel working	not oper
Halt I/O	interruption pending	CSW stored	burst op stopped	not oper
Start I/O, SIOF	started	CSW stored	busy	not oper
Store Channel ID	ID stored	CSW stored	busy	not oper
Test I/O	available	CSW stored	busy	not oper
Test Channel	available	interruption pending	burst mode	not oper

CONDITION CODES (. . . Cont'd)

Condition Code Setting	0	1	2	3
Mask Bit Position	8	4	2	1
<u>Miscellaneous Operations</u>				
Set Clock	set	secure	—	not oper
Store Clock	set	not set	error	not oper
Test and set	left zero	left one	—	—
Reset Reference Bit	Ref bit zero, change bit zero	Ref bit zero, change bit one	Ref bit one, change bit zero	Ref bit one, change bit one
Make Addressable	successful	already addressable	—	—
Make Unaddressable	successful	already connected	—	—
Retrieve Status and Page Set Page Bits	valid Ref bit 0, C bit 0	— R bit 0, C bit 1	— R bit 1, C bit 0	invalid R bit 1, C bit 1
Load Frame Index	addressable	connected	disconnected	address is invalid
Connect Page	successful	already disconnected	not successful	—
Disconnect Page	successful	already disconnected	—	—

CODE TRANSLATION TABLE

Dec	Hex.	Instruction (RR)	Graphics and Controls		7-Track Tape BCDIC (2)	Card Code	Binary
			BCDIC	EBCDIC(1)			
0	00			NUL	NUL	12-0-1-8-9	0000 0000
1	01			SOH	SOH	12-1-9	0000 0001
2	02			STX	STX	12-2-9	0000 0010
3	03			ETX	ETX	12-3-9	0000 0011
4	04	SPM		PF	EOT	12-4-9	0000 0100
5	05	BALR		HT	ENO	12-5-9	0000 0101
6	06	BCTR		LC	ACK	12-6-9	0000 0110
7	07	BCR		DEL	BEL	12-7-9	0000 0111
8	08	SSK			BS	12-8-9	0000 1000
9	09	ISK			HT	12-1-8-9	0000 1001
10	0A	SVC	SMM		LF	12-2-8-9	0000 1010
11	0B		VT		VT	12-3-8-9	0000 1011
12	0C		FF		FF	12-4-8-9	0000 1100
13	0D		CR		CR	12-5-8-9	0000 1101
14	0E	MVCL	SO		SO	12-6-8-9	0000 1110
15	0F	CLCL	SI		SI	12-7-8-9	0000 1111
16	10	LPR	DLE		DLE	12-11-1-8-9	0001 0000
17	11	LNR	DC1		DC1	11-1-9	0001 0001
18	12	LTR	DC2		DC2	11-2-9	0001 0010
19	13	LCR	TM		DC3	11-3-9	0001 0011
20	14	NR	RES		DC4	11-4-9	0001 0100
21	15	CLR	NL		NAK	11-5-9	0001 0101
22	16	OR	BS		SYN	11-6-9	0001 0110
23	17	XR	IL		ETB	11-7-9	0001 0111
24	18	LR	CAN		CAN	11-8-9	0001 1000
25	19	CR	EM		EM	11-1-8-9	0001 1001
26	1A	AR	CC		SUB	11-2-8-9	0001 1010
27	1B	SR	CU1		ESC	11-3-8-9	0001 1011
28	1C	MR	IFS		FS	11-4-8-9	0001 1100
29	1D	DR	IGS		GS	11-5-8-9	0001 1101
30	1E	ALR	IRS		RS	11-6-8-9	0001 1110
31	1F	SLR	IUS		US	11-7-8-9	0001 1111
32	20	LPDR	DS		SP	11-0-1-8-9	0010 0000
33	21	LNDR	SOS		!	0-1-9	0010 0001
34	22	LTDR	FS		"	0-2-9	0010 0010
35	23	LCDR			#	0-3-9	0010 0011
36	24	HDR	BYP		\$	0-4-9	0010 0100
37	25	LRDR	LF		%	0-5-9	0010 0101
38	26	MXR	ETB		&	0-6-9	0010 0110
39	27	MXDR	ESC		'	0-7-9	0010 0111
40	28	LDR			(0-8-9	0010 1000
41	29	CDR)	0-1-8-9	0010 1001
42	2A	ADR	SM		*	0-2-8-9	0010 1010
43	2B	SDR	CU2		+	0-3-8-9	0010 1011
44	2C	MDR			,	0-4-8-9	0010 1100
45	2D	DDR	ENQ		-	0-5-8-9	0010 1101
46	2E	AWR	ACK		.	0-6-8-9	0010 1110
47	2F	SWR	BEL		/	0-7-8-9	0010 1111
48	30	LPER			0	12-11-0-1-8-9	0011 0000
49	31	LNER			1	1-9	0011 0001
50	32	LTER	SYN		2	2-9	0011 0010
51	33	LCER			3	3-9	0011 0011
52	34	HER	PN		4	4-9	0011 0100
53	35	LRER	RS		5	5-9	0011 0101
54	36	AXR	UC		6	6-9	0011 0110
55	37	SXR	EOT		7	7-9	0011 0111
56	38	LER			8	8-9	0011 1000
57	39	CER			9	1-8-9	0011 1001
58	3A	AER			:	2-8-9	0011 1010
59	3B	SER	CU3		;	3-8-9	0011 1011
60	3C	MER	DC4		<	4-8-9	0011 1100
61	3D	DER	NAK		=	5-8-9	0011 1101
62	3E	AUR			>	6-8-9	0011 1110
63	3F	SUR	SUB		?	7-8-9	0011 1111

1 EBCDIC graphics shown are standard bit pattern assignment. For specific print train/chain:
See printer manual.

2 Add C (Check bit) for odd or even parity as needed, except as noted.

3 For even parity use CA

Dec	Hex	Instruction (RX)	Graphics and Controls			7-Track Tape BCDIC (2)	Card Code	Binary
			BCDIC	EBCDIC (1)	ASCII			
64	40	STH			@	(3)	no punches	0100 0000
65	41	LA			A		12-0-1-9	0100 0001
66	42	STC			B		12-0-2-9	0100 0010
67	43	IC			C		12-0-3-9	0100 0011
68	44	EX			D		12-0-4-9	0100 0100
69	45	BAL			E		12-0-5-9	0100 0101
70	46	BCT			F		12-0-6-9	0100 0110
71	47	BC			G		12-0-7-9	0100 0111
72	48	LH			H		12-0-8-9	0100 1000
73	49	CH			I		12-1-8	0100 1001
74	4A	AH			J		12-2-8	0100 1010
75	4B	SH			K	B A 8 2 1	12-3-8	0100 1011
76	4C	MH	•	∨	L	B A 8 4	12-4-8	0100 1100
77	4D			(M	B A 8 4 1	12-5-8	0100 1101
78	4E	CVD	#	+	N	B A 8 4 2	12-6-8	0100 1110
79	4F	CVB	&	!	O	B A 8 4 2 1	12-7-8	0100 1111
80	50	ST	& +	&	P	B A	12	0101 0000
81	51				Q		12-11-1-9	0101 0001
82	52				R		12-11-2-9	0101 0010
83	53				S		12-11-3-9	0101 0011
84	54	N			T		12-11-4-9	0101 0100
85	55	CL			U		12-11-5-9	0101 0101
86	56	O			V		12-11-6-9	0101 0110
87	57	X			W		12-11-7-9	0101 0111
88	58	L			X		12-11-8-9	0101 1000
89	59	C			Y		11-1-8	0101 1001
90	5A	A		!	Z		11-2-8	0101 1010
91	5B	S	\$	\$	[B 8 2 1	11-3-8	0101 1011
92	5C	M	•	•	\	B 8 4	11-4-8	0101 1100
93	5D	D)]	B 8 4 1	11-5-8	0101 1101
94	5E	AL	∨	∨	^	B 8 4 2	11-6-8	0101 1110
95	5F	SL	△	∨	~	B 8 4 2 1	11-7-8	0101 1111
96	60	STD	/	/	·	B	11	0110 0000
97	61		/	/	a	A	10-1	0110 0001
98	62				b		11-0-2-9	0110 0010
99	63				c		11-0-3-9	0110 0011
100	64				d		11-0-4-9	0110 0100
101	65				e		11-0-5-9	0110 0101
102	66				f		11-0-6-9	0110 0110
103	67	MXD			g		11-0-7-9	0110 0111
104	68	LD			h		11-0-8-9	0110 1000
105	69	CD			i		0-1-8	0110 1001
106	6A	AD		∴	j		12-11	0110 1010
107	6B	SD	·	·	k	A 8 2 1	0-3-8	0110 1011
108	6C	MD	%	%	l	A 8 4	0-4-8	0110 1100
109	6D	DD	Y	∨	m	A 8 4 1	0-5-8	0110 1101
110	6E	AW	#	∨	n	A 8 4 2	0-6-8	0110 1110
111	6F	SW	#	∨	o	A 8 4 2 1	0-7-8	0110 1111
112	70	STE			p		12-11-0	0111 0000
113	71				q		12-11-0-1-9	0111 0001
114	72				r		12-11-0-2-9	0111 0010
115	73				s		12-11-0-3-9	0111 0011
116	74				t		12-11-0-4-9	0111 0100
117	75				u		12-11-0-5-9	0111 0101
118	76				v		12-11-0-6-9	0111 0110
119	77				w		12-11-0-7-9	0111 0111
120	78	LE			x		12-11-0-8-9	0111 1000
121	79	CE			y		1-8	0111 1001
122	7A	AE		∴	z	A	2-8	0111 1010
123	7B	SE	@# =	∴	{	8 2 1	3-8	0111 1011
124	7C	ME	@' =	@ =		8 4	4-8	0111 1100
125	7D	DE	∴	∴	}	8 4 1	5-8	0111 1101
126	7E	AU	∴	∴	~	8 4 2	6-8	0111 1110
127	7F	SU	∴	∴	DEL	8 4 2 1	7-8	0111 1111

1 EBCDIC graphics shown are standard bit pattern assignments. For specific print train/chain: See printer manual.

2 Add C (check bit) for odd or even parity as needed, except as noted.

CODE TRANSLATION TABLE (. . . Cont'd)

Dec	Hex	Instruction (RS, SI, S)	Graphics and Controls			7-Track Tape BCDIC (2)	Card Code	Binary
			BCDIC	EBCDIC (1)	ASCII			
128	80	SSM		a			12-0-1-8	1000 0000
129	81			b			12-0-1	1000 0001
130	82	LPSW		c			12-0-2	1000 0010
131	83	Diagnose		d			12-0-3	1000 0011
132	84			e			12-0-4	1000 0100
133	85			f			12-0-5	1000 0101
134	86	BXH		g			12-0-6	1000.0110
135	87	BXLE		h			12-0-7	1000 0111
136	88	SRL		i			12-0-8	1000 1000
137	89	SLL					12-0-9	1000 1001
138	8A	SRA					12-0-2-8	1000 1010
139	8B	SLA					12-0-3-8	1000 1011
140	8C	SRDL					12-0-4-8	1000 1100
141	8D	SLDL					12-0-5-8	1000 1101
142	8E	SRDA					12-0-6-8	1000 1110
143	8F	SLDA					12-0-7-8	1000 1111
144	90	STM					12-11-1-8	1001 0000
145	91	TM		i			12-11-1	1001 0001
146	92	MVI		k			12-11-2	1001 0010
147	93	TS		l			12-11-3	1001 0011
148	94	NI		m			12-11-4	1001 0100
149	95	CLI		n			12-11-5	1001 0101
150	96	OI		o			12-11-6	1001 0110
151	97	XI		p			12-11-7	1001 0111
152	98	LM		q			12-11-8	1001 1000
153	99			r			12-11-9	1001 1001
154	9A						12-11-2-8	1001 1010
155	9B						12-11-3-8	1001 1011
156	9C	SIO, SIOF					12-11-4-8	1001 1100
157	9D	TIO, CLRIO					12-11-5-8	1001 1101
158	9E	HIO, HDV					12-11-6-8	1001 1110
159	9F	TCH					12-11-7-8	1001 1111
160	A0			~			11-0-1-8	1010 0000
161	A1			s			11-0-1	1010 0001
162	A2			t			11-0-2	1010 0010
163	A3			u			11-0-3	1010 0011
164	A4			v			11-0-4	1010 0100
165	A5			w			11-0-5	1010 0101
166	A6			x			11-0-6	1010 0110
167	A7			y			11-0-7	1010 0111
168	A8			z			11-0-8	1010 1000
169	A9						11-0-9	1010 1001
170	AA						11-0-2-8	1010 1010
171	AB						11-0-3-8	1010 1011
172	AC	STNSM					11-0-4-8	1010 1100
173	AD	STOSM					11-0-5-8	1010 1101
174	AE						11-0-6-8	1010 1110
175	AF	MC					11-0-7-8	1010 1111
176	B0	CTP					12-11-0-1-8	1011 0000
177	B1						12-11-0-1	1011 0001
178	B2	See below					12-11-0-2	1011 0010
179	B3						12-11-0-3	1011 0011
180	B4	IPB					12-11-0-4	1011 0100
181	B5	SPB					12-11-0-5	1011 0101
182	B6	STCTL					12-11-0-6	1011 0110
183	B7	LCTL					12-11-0-7	1011 0111
184	B8	LF1					12-11-0-8	1011 1000
185	B9						12-11-0-9	1011 1001
186	BA	CS					12-11-0-2-8	1011 1010
187	BB	CDS					12-11-0-3-8	1011 1011
188	BC						12-11-0-4-8	1011 1100
189	BD	CLM					12-11-0-5-8	1011 1101
190	BE	STCM					12-11-0-6-8	1011 1110
191	BF	ICM					12-11-0-7-8	1011 1111

OP Code: B202 - STIDP B207 - STCKC B213 - RRB B21E - MUN
 B203 - STIDC B208 - SPT B215 - CLRP B21F - STCAP
 B204 - SCK B209 - STPT B21B - DECP
 B205 - STCK B20A - SPKA B21C - DCTP
 B206 - SCKC B20B - IPK B21D - MAD

CODE TRANSLATION TABLE (. . . Cont'd)

Dec	Hex	Instruction (SS)	Graphics and Controls			7-Track Tape		Card Code	Binary
			BCDIC	EBCDIC (1)	ASCII	BCDIC (2)			
192	C0		?	{		B A 8 2	12-0	1100 0000	
193	C1		A	A		B A 4 1	12-1	1100 0001	
194	C2		B	B		B A 2	12-2	1100 0010	
195	C3		C	C		B A 2 1	12-3	1100 0011	
196	C4		D	D		B A 4	12-4	1100 0100	
197	C5		E	E		B A 4 1	12-5	1100 0101	
198	C6		F	F		B A 4 2	12-6	1100 0110	
199	C7		G	G		B A 4 2 1	12-7	1100 0111	
200	C8		H	H		B A 8	12-8	1100 1000	
201	C9		I	I		B A 8	12-9	1100 1001	
202	CA						12-0-2-8-9	1100 1010	
203	CB						12-0-3-8-9	1100 1011	
204	CC			J			12-0-4-8-9	1100 1100	
205	CD						12-0-5-8-9	1100 1101	
206	CE			Y			12-0-6-8-9	1100 1110	
207	CF						12-0-7-8-9	1100 1111	
208	D0		I	}		B 8 2	11-0	1101 0000	
209	D1	MVN	J	J		B 2 1	11-1	1101 0001	
210	D2	MVC	K	K		B 2	11-2	1101 0010	
211	D3	MVZ	L	L		B 2 1	11-3	1101 0011	
212	D4	NC	M	M		B 4	11-4	1101 0100	
213	D5	CLC	N	N		B 4 1	11-5	1101 0101	
214	D6	OC	O	O		B 4 2	11-6	1101 0110	
215	D7	XC	P	P		B 4 2 1	11-7	1101 0111	
216	D8	RSP	Q	Q		B 8	11-8	1101 1000	
217	D9		R	R		B 8 1	11-9	1101 1001	
218	DA						12-11-2-8-9	1101 1010	
219	DB						12-11-3-8-9	1101 1011	
220	DC	TR					12-11-4-8-9	1101 1100	
221	DD	TRT					12-11-5-8-9	1101 1101	
222	DE	ED					12-11-6-8-9	1101 1110	
223	DF	EDMK					12-11-7-8-9	1101 1111	
224	E0		#	\		A 8 2	0-2-8	1110 0000	
225	E1						11-0-1-9	1110 0001	
226	E2		S	S		A 2	0-2	1110 0010	
227	E3		T	T		A 2 1	0-3	1110 0011	
228	E4		U	U		A 4	0-4	1110 0100	
229	E5		V	V		A 4	0-5	1110 0101	
230	E6		W	W		A 4 2	0-6	1110 0110	
231	E7		X	X		A 4 2 1	0-7	1110 0111	
232	E8	MVCIN	Y	Y		A 8	0-8	1110 1000	
233	E9		Z	Z		A 8 1	0-9	1110 1001	
234	EA						11-0-2-8-9	1110 1010	
235	EB						11-0-3-8-9	1110 1011	
236	EC			H			11-0-4-8-9	1110 1100	
237	ED						11-0-5-8-9	1110 1101	
238	EE						11-0-6-8-9	1110 1110	
239	EF						11-0-7-8-9	1110 1111	
240	F0	SRP	0	0		8 2	0	1111 0000	
241	F1	MVO	1	1			1	1111 0001	
242	F2	PACK	2	2			2	1111 0010	
243	F3	UNPK	3	3			2 1 3	1111 0011	
244	F4		4	4			4	1111 0100	
245	F5		5	5			4 1 5	1111 0101	
246	F6		6	6			4 2 6	1111 0110	
247	F7		7	7			4 2 1 7	1111 0111	
248	F8	ZAP	8	8		8	8	1111 1000	
249	F9	CP	9	9		8	1 9	1111 1001	
250	FA	AP		I				12-11-0-2-8-9	1111 1010
251	FB	SP						12-11-0-3-8-9	1111 1011
252	FC	MP						12-11-0-4-8-9	1111 1100
253	FD	DP						12-11-0-5-8-9	1111 1101
254	FE							12-11-0-6-8-9	1111 1110
255	FF							12-11-0-7-8-9	1111 1111

MACHINE INSTRUCTIONS FORMATS

	FIRST HALFWORD 1	SECOND HALFWORD 2	THIRD HALFWORD 3				
	REGISTER OPERAND 1	REGISTER OPERAND 2					
RR	Op Code	R1	R2				
	0 7 8 11 12 15						
	REGISTER OPERAND 1	ADDRESS OF OPERAND 2					
RX	Op Code	R1	X2	B2	D2		
	0 7 8 11 12 15 16 19 20				31		
	REGISTER OPERAND 1	REGISTER OPERAND 3	ADDRESS OF OPERAND 2				
RS	Op Code	R1	R3	B2	D2		
	0 7 8 11 12 15 16 19 20				31		
		IMMEDIATE OPERAND	ADDRESS OF OPERAND 1				
SI	Op Code	I2	B1	D1			
	0 7 8 15 16 19 20				31		
			ADDRESS OF OPERAND 1				
S	Op Code		B2	D2			
	0 15 16 19 20				31		
	LENGTH OPERAND 1	LENGTH OPERAND 2	ADDRESS OF OPERAND 1	ADDRESS OF OPERAND 2			
SS	Op Code	L1	L2	B1	D1	B2	D2
	0 7 8 11 12 15 16 19 20					31 32 35 36	47
		LENGTH	ADDRESS OF OPERAND 1	ADDRESS OF OPERAND 2			
SS	Op Code	L	B1	D1	B2	D2	
	0 7 8 15 16 19 20					31 32 35 36	47

CONTROL REGISTER ALLOCATION

	0	1	2	3
0	SYSTEM CONTR	TRANSL CONTR	EXTERNAL INTERRUPTION MASKS	
1	SEGM TBL LENGTH	SEGMENT TABLE ORIGIN ADDRESS		
2	CHANNEL MASKS			
3				
4				
5				
6				
7				
8				MONITOR MASKS
9	PER EVENT MASKS		PER GR ALTERATION MASKS	
10		PER STARTING ADDRESS		
11		PER ENDING ADDRESS		
12				
13				
14	ERROR RECOVERY CONTR & MASKS			
15				

ASSIGNMENT OF CONTROL REGISTER FIELDS

CR	Bits	Name of Field	Associated with	Initial Value
0	0	Block-Multiplexing Control	Block-Multiplexing Channels	0
0	1	SSM-Suppression Control	SET System Mask	0
0	8-9	Page Size**	Dynamic Addr. Translation	0
0	10	Reserved**	Dynamic Addr. Translation	0
0	11-12	Segment Size**	Dynamic Addr. Translation	0
0	20	Clock-Comparator Mask	Clock Comparator	0
0	21	CPU-Timer Mask	CPU Timer	0
0	24	Interval-Timer Mask	Interval Timer	1
0	25	Interrupt-Key Mask	Interrupt Key	1
0	26	External-Signal Mask	External Signal	1
2	0-31	Channel Masks	Channels	1
8	16-31	Monitor Masks	Monitor Call	0
9	0	Successful-Branching-Event Mask	Program-Event Recording	0
9	1	Instruction-Fetching-Event Mask	Program-Event Recording	0
9	2	Storage-Alternation-Event Mask	Program-Event Recording	0
9	3	GR-Alternation-Event Mask	Program-Event-Recording	0
9	16-31	PER* General-Register Masks	Program-Event-Recording	0
10	8-31	PER Starting Address	Program-Event Recording	0
11	8-31	PER Ending Address	Program-Event Recording	0
14	0	Check Stop Control**	Machine Check Handling	1
14	1	Synchronous MCEL Control**	Machine Check Handling	1
14	2	I/O Extended Logout Control**	Machine Check Handling	0
14	4	Recovery-Report Mask	Machine-Check Handling	0
14	5	Degradation-Report Mask	Machine-Check Handling	0
14	6	External-Damage-Report Mask	Machine-Check Handling	1
14	7	Warning Mask	Machine-Check Handling	0
14	8	Asynchronous MCEL Control**	Machine-Check-Handling	0
14	9	Asynchronous Fixed Log Contr.**	Machine-Check-Handling	0
15	8-28	MCEL Address**	Machine-Check-Handling	512

Explanation:

* PER Means Program-Event Recording

** Only Used in /370 Mode


PERMANENT MAIN STORAGE ASSIGNMENT

Storage Loc		Byte	Byte	Byte	Byte
Hex	Dec				
0	0	Restart New PSW (IPL PSW)			
4	4				
8	8	Restart Old PSW (IPL CCW1)			
C	12				
10	16	(IPL CCW2)			
14	20				
18	24	External Old PSW			
1C	28				
20	32	Supervisor Call Old PSW			
24	36				
28	40	Program Old PSW			
2C	44				
30	48	Machine Check Old PSW			
34	52				
38	56	Input/Output Old PSW			
3C	60				
40	64	Channel Status Word			
44	68				
48	72	Channel Address Word			
4C	76				
50	80	Interval Timer			
54	84				
58	88	External New PSW			
5C	92				
60	96	Supervisor Call New PSW			
64	100				
68	104	Program New PSW			
6C	108				
70	112	Machine Check New PSW			
74	116				
78	120	Input/Output New PSW			
7C	124				
80	128				
84	132	0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0	External Interruption Code		
88	136	0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0	ILC	0	SVC Interruption Code
8C	140	0 0 0 0 0 0 0 0 0 0 0 0 0 0 0 0	ILC	0	Program Interruption Code
90	144	0 0 0 0 0 0 0 0	ACCESS Exception Address		
94	148	0 0 0 0 0 0 0 0	Monitor Class #	PER Code	0 0 0 0 0 0 0 0 0 0 0 0
98	152	0 0 0 0 0 0 0 0	PER Address		
9C	156	0 0 0 0 0 0 0 0	Monitor Code		
A0	160				
A4	164				
A8	168	Channel ID			
AC	172	Reserved			

PERMANENT MAIN STORAGE ASSIGNMENT (. . . Cont'd)

Storage Loc		Byte	Byte	Byte	Byte
Hex	Dec				
B0	176	Limited Channel Logout			
B4	180				
B8	184	0 0 0 0 0 0 0 0 I/O Address			
BC	188	Zero if an I/O Address is stored here →			
⋮	⋮				
D4	212				
D8	216	CPU-Timer Save Area			
DC	220				
E0	224	Clock-Comparator Save Area			
E4	228				
EB	232	Machine Check Interruption Code			
EC	236				
F0	240				
F4	244				
F8	248	0 0 0 0 0 0 0 0	Failing Storage Address		
FC	252	Reserved			
⋮	⋮				
15C	348				
160	352	Floating Point Register Save Area			
⋮	⋮				
17C	380				
⋮	⋮				
180	384	General Register Save Area			
⋮	⋮				
18C	444				
1C0	448	Control Register Save Area			
⋮	⋮				
1FC	508				

PROGRAM STATUS WORD (PSW) (EC-mode)




Bit	Description	Bit	Description	
0	*Always zero	15	Problem state	
1	PER mask	16-17	*Always zero	
2-4	*Always zero	18-19	Condition code	
5	**Translate mode	20	} Prog. mask {	
6	I/O interrupt mask	21		Fixed-point overflow mask
7	External interrupt mask	22		Decimal overflow mask
8-11	KEY	23	Exponent underflow mask	
12	Always one in EC mode	24-31	Significance mask	
13	Machine check mask	32-39	*Always zero	
14	Wait state	40-63	*Always zero	
			Instruction address	

*If not zero a Specification Exception is recognized


**Only used in /370 mode

PROGRAM STATUS WORD (PSW) (BC-mode)




Bit	Description	Bit	Description	
0	Channel 0 mask	14	Wait state	
1	Channel 1 mask	15	Problem state	
2	Channel 2 mask	16-31	Instruction code	
3	Channel 3 mask	32-33	Instruction length code	
4	Channel 4 mask	34-35	Condition code	
5	Channel 5 mask	36	} Prog. mask {	
6	Mask for channel 6 and up	37		Fixed-point overflow mask
7	External interrupt mask	38		Decimal overflow mask
8-11	Protection key	39	Exponent underflow mask	
12	Always 0 in BC mode	40-63	Significance mask	
13	Machine check mask		Instruction address	

CHANNEL ADDRESS WORD (CAW) (X'48')




CHANNEL COMMAND WORD (CCW)



Flags

Bit	Description
32	CD-bit (80) : causes use of address portion of next CCW (Chaining Data)
33	CC-bit (40) : causes use of command code and data address of next CCW(Chain Command)
34	SLI-bit (20) : causes suppression of possible incorrect length indication
35	Skip bit (10) : suppresses transfer of information to main storage
36	PCI-bit (08) : causes a channel Program Controlled Interruption
37	IDA-bit (04) : specifies indirect data addressing (only /370 mode)

CHANNEL STATUS WORD (CSW) (X'40')



Status

Bit	Description	Bit	Description
5	Logout pending	40	(0080) Program controlled interruption
6, 7	(8000) Deferred cond. code	41	(0040) Incorrect length
32	(8000) Attention	42	(0020) Program check
33	(4000) Status Modifier	43	(0010) Protection check
34	(2000) Control unit end	44	(0008) Channel data check
35	(1000) Busy	45	(0004) Channel control check
36	(0800) Channel end	46	(0002) Interface control check
37	(0400) Device end	47	(0001) Chaining check
38	(0200) Unit check		
39	(0100) Unit exception		

Byte count: Bits 48-63 form the residual count for the last CCW used.

CODES FOR PROGRAM INTERRUPTION (X'8E')

Interruption Code		Program Interruption Cause	Interruption Code		Program Interruption Cause
Dec	Hex		Dec	Hex	
1	0001	Operation	12	000C	Exponent overflow
2	0002	Privileged operation	13	000D	Exponent underflow
3	0003	Execute	14	000E	Significance
4	0004	Protection	15	000F	Floating point divide
5	0005	Addressing	16	0010	Segment translation*
6	0006	Specification	17	0011	Page translation*
7	0007	Data	18	0012	Translation specification*
8	0008	Fixed-point overflow	19	0013	Special operation
9	0009	Fixed-point divide	24	0018	Page access
10	000A	Decimal overflow	26	001A	Page state
11	000B	Decimal divide	27	001B	Page transition
			64	0040	Monitor event
			128	0080	Program event

*Used only in /370 mode

CODES FOR EXTERNAL INTERRUPTIONS (X'86')

Interruption Code (Hex)	External Interruption Cause	Indication of Concurrent Condition by Bit Positions
0080	Interval timer	9-15
0040	Interrupt key	8 and 10-15
0020	External signal 2	8, 9, 11-15
0010	External signal 3	8-10, 12-15
0008	External signal 4	8-11, 13-15
0004	External signal 5	8-12, 14, 15
0002	External signal 6	8-13, 15
0001	External signal 7	8-14
1004	Clock comparator	
1005	CPU timer	

CODES FOR INPUT/OUTPUT INTERRUPTIONS (X'8A')

Interruption Code (Hex)	Input/Output Interruption Cause
00 dd	Channel 0
01 dd	Channel 1
02 dd	Channel 2
03 dd	Channel 3
04 dd	Channel 4
05 dd	Channel 5
06 dd - xx dd	Channel 6 - and up

Note: d = device address

CODES FOR SUPERVISOR CALL INTERRUPTIONS (X'8A')

Interruption Code (Hex)	Supervisor Call Interruption Cause
00 rr	Instruction (0A)

Note: r = R1 and R2 field of SUPERVISOR CALL

CHANNEL COMMANDS

Standard Command Code Assignments (CCW bits 0-7) for I/O Operations

xxxx	0000	Invalid	†††† ††01	Write
††††	0100	Sense	†††† ††10	Read
xxxx	1000	Transfer in Channel	†††† ††11	Control
††††	1100	Read backward	0000 0011	Control No Operation

x = Bit ignored † = Modifier bit for specific type of I/O device

CHANNEL COMMANDS (. . . Cont'd)

3210, 3215 CONSOLES

Source: GA 24-3557

Write, No Carrier Return	01	Sense	04
Write, Auto Carrier Return	09	Audible Alarm	0B
Read Inquiry	0A		

3504/5 CARD READER / 3525 CARD PUNCH

Source: GA 21-9124

Command	Binary	Hex	Bit Meanings
Sense	0 0 0 0	0 1 0 0	0 4
Feed, Select Stacker	S S 1 0	F 0 1 1	SS Stacker
Read Only*	1 1 D 0	F 0 1 0	00 1
Diagnostic Read (inval.3504)	1 1 0 1	0 0 1 0	01 2
Read, Feed, Select Stacker*	S S D 0	F 0 1 0	10 2
Write RCE Format* †	0 0 0 1	0 0 0 1	1 1
			F Format Mode
			0 Unformatted
			1 Formatted
3504, 3505 only			
Write OMR Format	0 0 1 1	0 0 0 1	3 1
			D Data Mode
			0 1-EBCDIC
			1 2-Card Image
3525 only			
Write, Feed, Select Stacker	S S D 0	0 0 0 1	
Print Line*	L L L L	L 1 0 1	L Line Position
			5 Bit Binary Value

*Special feature on 3525 † Special feature

PRINTERS: 3211/3811; 3203/IPA; 1403*/2821

Source: GA24-3312

Source: GA24-3543

	After Write	Immed.		
			Load UCSB and Fold (exc.3211)	F3
			UCS Gate Load (1403 only)	EB
			Write without spacing	01
			Sense	04
Space 1 Line	09	0B	Load UCSB	FB
Space 2 Lines	11	13	Fold †	43
Space 3 Lines	19	1B	Unfold †	23
Skip to Channel 0 †	-	83	Load FCB (exc.1403)	63
Skip to Channel 1	89	8B	Block Data Check	73
Skip to Channel 2	91	93	Allow Data Check	7B
Skip to Channel 3	99	9B	Read PLB †	02
Skip to Channel 4	A1	A3	Read UCSB †	0A
Skip to Channel 5	A9	AB	Read FCB †	12
Skip to Channel 6	B1	B3	Check Read (exc.3203)	06
Skip to Channel 7	B9	BB	Diagnostic Write †	05
Skip to Channel 8	C1	C3	Raise Cover †	6B
Skip to Channel 9	C9	CB	Diagnostic Gate †	07
Skip to Channel 10	D1	D3	Diagnostic Read (1403 only)	02
Skip to Channel 11	D9	DB	Adv. to End of Sheet (3203 only)	5B
Skip to Channel 12	E1	E3		

*UCS special feature; IPA model dependent

† 3211 only

3420/3803, 3410/3411 Magnetic Tape

Source: GA32-0020

Write	01	Data Security Erase	97
Read Forward	02	Diagnostic Write Mode Set	0B
Read Backward	0C	Set Mode 1 (7-track) †	
Sense	04		
Sense Reserve*	F4	Density	Parity
Sense Release*	D4	DC	Trans
Request Track in Error	1B	556	Cmd
Loop Write to Read*	8B	odd	on
Set Diagnose*	4B	off	off
Rewind	07	even	on
Rewind Unload	0F	off	off
Erase Gap	17	on	off
Write Tape Mark	1F	off	off
Backspace Block	27	on	on
Backspace File	2F	off	off
Forward Space Block	37	on	on
Forward Space File	3F	off	on
Data Security Erase*	97	on	off
Diagnostic Mode Set*	0B	off	on
		800	off
		even	on
		off	off
		on	on
		Set Mode 2 (9-track)	
		6250 bpi*	D3
		1600 bpi	C3
		800 bpi †	CB

*3420 only

† Special feature for NRZI operation

CHANNEL COMMANDS (. . . Cont'd)

DIRECT ACCESS DEVICES
3330 – 3340 – 3350
2305/2835; 2314/2319

Source: GA26-1592 for 3830/3330
GA26-3599, GA26-1606 for 2314, 2319

Command		MT Off	MT On*	Count		
Control	Orient (c)	2B	B9	Nonzero		
	Recalibrate	13		Nonzero		
	Seek	07		6		
	Seek cylinder	0B		6		
	Seek Head	1B		6		
	Space Count	0F		3 (a); nonzero (d)		
	Set File Mask	1F		1		
	Set Sector (a, f)	23		1		
	Restore (a)	17		Nonzero		
	Vary Sensing (c)	27		1		
	Diagnostic Load (a)	53		1		
Diagnostic Write (a)	73		512			
Search	Home Address Equal	39	B9	4		
	Identifier Equal	31	B1	5		
	Identifier High	51	D1	5		
	Identifier Equal or High	71	F1	5		
	Key Equal	29	A9	KL		
	Key High	49	C9	KL		
	Key Equal or High	69	E9	KL		
	Key and Data Equal (d)	2D	AD	} Number of bytes (incl. mask bytes) in search argument		
	Key and Data High (d)	4D	CD			
	Key and Data Equal or High (d)	6D	ED			
Continue Scan	Search Equal (d)	25	A5	} Number of bytes to be transferred		
	Search High (d)	45	C5			
	Search High or Equal (d)	65	E5			
	Set Status Modifier (d)	35	B5			
	Set Status Modifier (d)	75	F5			
Read	No Status Modifier (d)	55	D5	} Number of bytes to be transferred		
	Home Address	1A	9A		5	
	Count	12	92		8	
	Record 0	16	96		} Number of bytes to be transferred	
	Data	06	86			
	Key and Data	0E	8E			
	Count, Key and Data	1E	9E		} >max. track length	
	IPL	02				1
	Sector (a, f)	22				1
Multiple Count, Key, Data (b)	5E		>max. track length			
Sense	Sense I/O	04		24 (a); 6 (d)		
	Read, Reset Buffered Log (b)	A4		24		
	Read Buffered Log (c)	24		128		
	Device Release (e)	94		24 (a); 6 (d)		
	Device Reserve (e)	84		24 (a); 6 (d)		
	Read Diagnostic Status 1 (a)	44		16 or 512		
Write	Home Address	19		5		
	Record 0	15		8+KL+DL or R0		
	Erase	11		8+KL+DL		
	Count, Key and Data	1D		8+KL+DL		
	Special Count, Key and Data	01		8+KL=DL		
	Data	05		DL		
	Key and Data	0D		KL+DL		

* Code same as MT Off except as listed

a Except 2314/19

b 3330/40/50 only

c 2835/2305 only

d 2314, 2319 only

e Channel attachment and 2-channel switch feature required; standard on 2314 with 2844

CHANNEL COMMAND (. . .Cont'd)

DIRECT ACCESS DEVICES (3310, 3370) FBA MODE

Command		MT Off	MT On*	Count
Control	No-Operation	03		
	Define Extent	63		
	Locate	43		
Read	Read	42		
	Read IPL	02		
Write	Write	41		
Sense	Test I/O	00		
	Sense I/O	E4		
	Sense	04		
	Read and Reset Buffered Log	A4		
	Read Device Characteristics	64		
	*Device Reserve	B4		
	*Unconditional Reserve	14		
Diagnostic	*Device Release	94		
	Diagnostic Control	F3		
	Diagnostic Sense	C4		

*These commands are executed as sense.

8809 MAGNETIC TAPE

Command	Command Code
Write	01
Read	02
Rewind	07
Rewind-Unload	0F
Erase Gap	17
Write Tape Mark	1F
Backspace Block	27
Backspace File	2F
Forwardspace Block	37
Forwardspace File	3F
Data Security Erase	97
Set Low Speed	83
Set Long Gap	13
Set Normal Gap	23
Set High Speed and Long Gap	93
Set High Speed and Normal Gap	33
Set Low Speed and Long Gap	53
Set Low Speed and Normal Gap	63
Set High Speed	E3
ERP Loop Write-to-Read	8B
Control-No Op	03
Sense	04
Sense I/O	E4
Read and Reset Buffered Log	A4

HEXADECIMAL AND DECIMAL CONVERSION

- From Hex:** Locate each hex digit in its corresponding column position and note the decimal equivalents. Add these to obtain the decimal value.
- From Dec:** Locate the largest decimal value in the table that will fit into the decimal number to be converted.
 Note its hex equivalent and hex column position.
 Find the decimal remainder.
 Repeat the process on this and subsequent remainders.

Hexadecimal Columns											
6		5		4		3		2		1	
Hex	Dec	Hex	Dec	Hex	Dec	Hex	Dec	Hex	Dec	Hex	Dec
0	0	0	0	0	0	0	0	0	0	0	0
1	1 048 576	1	65 536	1	4 096	1	256	1	16	1	1
2	2 097 152	2	131 072	2	8 192	2	512	2	32	2	2
3	3 145 728	3	196 608	3	12 288	3	768	3	48	3	3
4	4 194 304	4	262 144	4	16 384	4	1 024	4	64	4	4
5	5 242 880	5	327 680	5	20 480	5	1 280	5	80	5	5
6	6 291 456	6	393 216	6	24 576	6	1 536	6	96	6	6
7	7 340 032	7	458 752	7	28 672	7	1 792	7	112	7	7
8	8 388 608	8	524 288	8	32 768	8	2 048	8	128	8	8
9	9 437 184	9	589 824	9	36 864	9	2 304	9	144	9	9
A	10 485 760	A	655 360	A	40 960	A	2 560	A	160	A	10
B	11 534 336	B	720 896	B	45 056	B	2 816	B	176	B	11
C	12 582 912	C	786 432	C	49 152	C	3 072	C	192	C	12
D	13 631 488	D	851 968	D	53 248	D	3 328	D	208	D	13
E	14 680 064	E	917 504	E	57 344	E	3 584	E	224	E	14
F	15 728 640	F	983 040	F	61 440	F	3 840	F	240	F	15
0 1 2 3		4 5 6 7		0 1 2 3		4 5 6 7		0 1 2 3		4 5 6 7	
Byte				Byte				Byte			

POWERS OF 2

2 ⁿ	n
256	8
512	9
1 024	10
2 048	11
4 096	12
8 192	13
16 384	14
32 768	15
65 536	16
131 072	17
262 144	18
524 288	19
1 048 576	20
2 097 152	21
4 194 304	22
8 388 608	23
16 777 216	24

$2^n = 16^{n:4}$

POWERS OF 16

16 ⁿ	n
1	0
16	1
256	2
4 096	3
65 536	4
1 048 576	5
16 777 216	6
268 435 456	7
4 294 976 296	8
68 719 476 736	9
1 099 511 627 776	10
17 592 186 044 416	11
281 474 976 710 656	12
4 503 599 627 370 496	13
72 057 594 037 927 936	14
1 152 921 504 606 846 976	15

SENSE INFORMATION SUMMARY

1017 – Paper Tape Reader

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention reject 2 : bus-out check 3 : – 4 : data check 5 : – 6 : – 7 : broken tape

1018 – Paper Tape Punch

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : data check 5 : – 6 : – 7 : –

1287 – Optical Reader

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : data check 5 : overrun 6 : non-recovery 7 : keyboard correction (tape only)
1	Bit 0 : tape mode 1 : late stacker select 2 : no document found 3 : – 4 : invalid operation 5 : – 6 : – 7 : –

1288 – Optical Reader

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : data check 5 : overrun 6 : non-recovery 7 : –
1	Bit 0 : – 1 : end-of-page 2 : no document found 3 : – 4 : invalid operation 5 : – 6 : – 7 : –

SENSE INFORMATION SUMMARY (. . . Cont'd)

1403 – Printer

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : data check 5 : parity check (UCS storage) 6 : – 7 : channel 9
1	Not used
2	Bit 0 : chain interlock 1 : forms check 2 : coil protect check 3 : subscan ring check 4 : chain buffer address register check 5 : – 6 : any hammer on check 7 : –
3	Not used
4	Bit 0 : hammer reset failure check 1 : no fire check 2 : misfire check 3 : print data buffer parity check 4 : check bit buffer parity check 5 : chain buffer parity check 6 : buffer address register parity check 7 : clock check
5	Bit 0 : open hammer coil check 1-7 : –

1419 – PCU – MICR

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : – 4 : data check 5 : overrun 6 : autoselect 7 : –
1	Bit 0 : – 1 : – 2 : document under read head 3 : amount field valid 4 : process-control field valid 5 : account-number field valid 6 : transit field valid 7 : serial-number field valid

1419 – SCU – MICR

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : – 4 : – 5 : late stacker select 6 : autoselect 7 : operator attention

SENSE INFORMATION SUMMARY (. . . Cont'd)

1442 – Card Read-Punch / Card Punch

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : data check 5 : overrun 6 : – 7 : –

1443 – Printer

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : type bar 5 : type bar 6 : – 7 : –

2260 – Display Station

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4-7 : –

2311 – Disk Storage

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : data check 5 : overrun 6 : track condition check 7 : seek check
1	Bit 0 : data check in count area 1 : track overrun 2 : end of cylinder 3 : invalid sequence 4 : no record found 5 : file protect 6 : missing address marker 7 : overflow incomplete

SENSE INFORMATION SUMMARY (. . . Cont'd)

2311 – Disk Storage (Cont'd)

<u>Sense Byte</u>	<u>Designation</u>
2	Bit 0 : unsafe 1 : – 2 : serializer check 3 : – 4 : ALU check 5 : unselected file status 6 : – 7 : –
3	Bit 0 : ready 1 : on line 2 : unsafe 3 : – 4 : on line 5 : end of cylinder 6 : – 7 : seek incomplete
4	Bit 0-7 : –
5	Bit 0-7 : command in progress when overflow incomplete occurs

2314/2319 – Direct Access Storage

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : data check 5 : overrun 6 : track condition check 7 : seek check
1	Bit 0 : data check in count area 1 : track overrun 2 : end of cylinder 3 : invalid sequence 4 : no record found 5 : file protect 6 : missing address marker 7 : overflow incomplete
2	Bit 0 : unsafe 1 : – 2 : SERDES check 3 : – 4 : ALU check 5 : unselected status 6 : – 7 : –
3	Bit 0 : busy 1 : on line 2 : unsafe 3 : wr current sense 4 : pack change 5 : end of cylinder 6 : multi-module select 7 : seek incomplete

SENSE INFORMATION SUMMARY (. . . Cont'd)

2314/2319 – Disk Access Storage (Cont'd)

<u>Sense Byte</u>	<u>Designation</u>																						
4	Bit 0 : wrong length record (2314 with multiplex storage control feature only) 1 : pending status (2314 with multiplex storage control feature only) 2 : – 3 : – 4-7 : Module identification																						
	<table border="1"> <thead> <tr> <th><u>bits 4567</u></th> <th><u>physical drive</u></th> </tr> </thead> <tbody> <tr><td>0000</td><td>A</td></tr> <tr><td>0001</td><td>B</td></tr> <tr><td>0010</td><td>C</td></tr> <tr><td>0011</td><td>D</td></tr> <tr><td>0100</td><td>E</td></tr> <tr><td>0101</td><td>F</td></tr> <tr><td>0110</td><td>G</td></tr> <tr><td>0111</td><td>H</td></tr> <tr><td>1000</td><td>J</td></tr> <tr><td>1111</td><td>module not defined</td></tr> </tbody> </table>	<u>bits 4567</u>	<u>physical drive</u>	0000	A	0001	B	0010	C	0011	D	0100	E	0101	F	0110	G	0111	H	1000	J	1111	module not defined
<u>bits 4567</u>	<u>physical drive</u>																						
0000	A																						
0001	B																						
0010	C																						
0011	D																						
0100	E																						
0101	F																						
0110	G																						
0111	H																						
1000	J																						
1111	module not defined																						
5	Bit 0-7 : command in progress when overflow incomplete occurs.																						

2400 – Magnetic Tape

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : data check 5 : overrun 6 : word count zero 7 : data converter check
1	Bit 0 : noise 1-2 : B'00' = not existent B'01' = not ready B'10' = ready and not rewinding B'11' = ready and rewinding 3 : seven-track 4 : at loadpoint 5 : selected and write status 6 : file protect 7 : not capable
2	Bit 0-7 : contains the track-in-error indicator bits that are set at the end of a read, or read-backward command if a data check has been encountered. Bits 6 and 7 on together indicate either more than one error or no error found.
3	Bit 0 : R/W VRC 1 : LRCR 2 : skew 3 : CRC 4 : skew register VRC 5 : phase encoding 6 : backward 7 : C compare
4	Bit 0 : echo check 1 : reject TU 2 : read clock error 3 : write clock error 4 : delay counter 5 : sequence indicator C 6 : sequence indicator B 7 : sequence indicator A

SENSE INFORMATION SUMMARY (. . . Cont'd)

2501 – Card Reader

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : data check 5 : overrun 6 : – 7 : –

2520 – Card Read-Punch/Card Punch

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : data check 5 : overrun 6 : – 7 : –

2540 – Card Reader/Card Punch

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : data check 5 : – 6 : unusual command 7 : –

2560 – Multifunction Card Machine

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : – 3 : equipment check 4 : data check 5 : feed/Machine check 6 : no card available 7 : print operation in progress
1	Bit 0 : cover interlock/punch pusher check 1 : jam bar check 2 : corner station check 3 : call 8 to 9 feed check 4 : print station feed check 5 : punch station feed check 6 : read station feed check 7 : input station feed check
2	Location of individual card: Bit 0 : secondary select 1 : card in punch station 2 : preprint SC7 exposed 3 : prepunch SC5 exposed 4 : prepunch SC4 exposed 5 : pre-read SC3 exposed 6 : pre-read SC2 exposed 7 : input station SC1 exposed

SENSE INFORMATION SUMMARY (. . . Cont'd)

2560 – Multifunction Card Machine (. . . Cont'd)

<u>Sense Byte</u>	<u>Designation</u>
3	Stacker Select Information: Bit 0 : primary card 0) 1 : binary value 4) card at primary 2 : binary value 2) prepunch station 3 : binary value 1) 4 : secondary card 1) 5 : binary value 4) card at secondary 6 : binary value 2) prepunch station 7 : binary value 1)
4	Stacker Select Information: Bit 0 : primary (0)) secondary (1)) 1 : binary value 4) card at punch or 2 : binary value 2) preprint station 3 : binary value 1) 4 : primary (0)) secondary (1)) 5 : binary value 4) card after print 6 : binary value 2) station 7 : binary value 1)
5	Stacker Select Information: Bit 0 : primary (0)) secondary (1)) 1 : 4) card at corner station 2 : 2) 3 : 1) 4 : primary (0)) secondary (1)) card in stacker pocket 5 : 4) (was just stacked) 6 : 2) 7 : 1)
6	Card column in which first (possibly only) error was detected: Bit 0 : multi data check 1 : binary value 64 2 : binary value 32 3 : binary value 16 4 : binary value 8 5 : binary value 4 6 : binary value 2 7 : binary value 1

2596 – Card Read-Punch

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : data check 5 : overrun 6 : – 7 : –

2671 – Paper Tape Reader

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : data check 5 : – 6 : – 7 : –

SENSE INFORMATION SUMMARY (. . . Cont'd)

3203 – Printer

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : — 3 : equipment check 4 : data check 5 : chain buffer parity check 6 : no channel found 7 : channel 9
1	Bit 0-7 : —
2	Bit 0 : interlock (chain gate open) 1 : form check (jam) 2 : coil protect check 3 : subscan ring check 4 : chain buffer address register check 5 : hammer unit shift check (model 1 only) 6 : any hammer on check 7 : device ready check
3	Bit 0 : — 1 : — 2 : — 3 : carriage inhibit check 4 : — 5 : — 6 : step check 7 : move check
4	Bit 0 : hammer reset failure check 1 : no fire check 2 : misfire check 3 : print data buffer parity check 4 : check bit buffer parity check 5 : chain buffer parity check 6 : buffer address register check 7 : clock check
5	Bit 0 : open coil check 1-7 : —

3210/3215 – Console Printer Keyboard

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : — 3 : equipment check 4-7 : —

PRT1 (3203-4, 3203-5, 3211, 3289)

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : data check 5 : buffer parity check 6 : load check 7 : channel 9
1	Bit 0 : command parity 1 : print check 2 : print quality 3 : line position check 4 : forms check 5 : command suppress 6 : mechanical motion 7 : —

SENSE INFORMATION SUMMARY (. . . Cont'd)

PRT1 (3203-4, 3203-5, 3211, 3289) (Cont'd)

<u>Sense Byte</u>	<u>Designation</u>
2	Bit 0 : carriage failed to move 1 : carriage sequence check 2 : carriage stop 3 : platen failed to advance 4 : platen failed to retract 5 : forms jam 6 : ribbon motion 7 : train overload
3	Bit 0 : UCSB parity 1 : PLB parity 2 : FCB parity 3 : coil protect 4 : hammer fire check 5 : service aid 6 : UCSAR sync check 7 : PSE sync check
4	Bit 0-7 : information used by service personnel
5	Bit 0-7 : —

3272 – (3270 Local)

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus out check 3 : equipment check 4 : data check 5 : unit specify 6 : control check 7 : operation check

FBM (3310 and 3370) Disk Storage

<u>Sense Byte</u>	<u>Designation</u>	<u>Format</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus out parity (not used) 3 : equipment check 4 : data check 5 : overrun 6 : (unused) 7 : (unused)	0 1 0 1 4 0 — —
1	Bit 0 : permanent error 1 : (unused) 2 : (unused) 3 : (unused) 4 : (unused) 5 : file protected 6 : write inhibited 7 : operation incomplete	any — — — — 0 — 0
2	Bit 0 : check data error 1 : correctable 2 : (unused) 3 : environmental data present 4 : (unused) 5 : (unused) 6 : (unused) 7 : only logging required	4 5 — 6,4,1 — — — —
3-6	physical address	
7	Bit 0-3 : hex: format number 4-7 : hex: message code	
8-23	only for diagnose information	

SENSE INFORMATION SUMMARY (. . . Cont'd)

3330 – Disk Storage

<u>Sense Byte</u>	<u>Designation</u>																		
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : data check 5 : overrun 6 : – 7 : –																		
1	Bit 0 : permanent error 1 : invalid track format 2 : end of cylinder 3 : – 4 : no record found 5 : file protected 6 : write inhibited 7 : operation incomplete																		
2	Bit 0 : – 1 : correctable 2 : – 3 : environmental data present 4 : – 5 : – 6 : – 7 : –																		
3	Bit 0-7 : restart command																		
4	Bit 0-1 : storage control identification 2-7 : physical drive identification <table border="1" data-bbox="507 833 730 1030" style="margin-left: 40px;"> <thead> <tr> <th><u>bits 2 to 7</u></th> <th><u>physical drive</u></th> </tr> </thead> <tbody> <tr><td>111000</td><td>A</td></tr> <tr><td>110001</td><td>B</td></tr> <tr><td>101010</td><td>C</td></tr> <tr><td>100011</td><td>D</td></tr> <tr><td>011100</td><td>E</td></tr> <tr><td>010101</td><td>F</td></tr> <tr><td>001110</td><td>G</td></tr> <tr><td>000111</td><td>H</td></tr> </tbody> </table>	<u>bits 2 to 7</u>	<u>physical drive</u>	111000	A	110001	B	101010	C	100011	D	011100	E	010101	F	001110	G	000111	H
<u>bits 2 to 7</u>	<u>physical drive</u>																		
111000	A																		
110001	B																		
101010	C																		
100011	D																		
011100	E																		
010101	F																		
001110	G																		
000111	H																		
5	Bit 0-7 : identify the eight low-order bits of the cylinder address in the most recent seek argument																		
6	Bit 0 : reserve 1 : cylinder number (high order bit of cylinder address) 2 : difference 3 : 16) 4 : 8) 5 : 4) head number 6 : 2) 7 : 1)																		
7	Bit 0-3 : format type of remaining sense bytes (8-23) 4-7 : encoded error message																		
8-23	Meaning depends on format type																		

3340 – Disk Storage

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : data check 5 : overrun 6 : track condition check 7 : seek check

SENSE INFORMATION SUMMARY (. . . Cont'd)

3340 – Disk Storage

<u>Sense Byte</u>	<u>Designation</u>
1	Bit 0 : permanent error 1 : invalid track format 2 : end of cylinder 3 : – 4 : no record found 5 : file protected 6 : write inhibited 7 : operation incomplete
2	Bit 0 : RPS feature present 1 : correctable 2 : – 3 : environmental data present 4 : – 5 : – 6 : data module size) 01 = 35MB 7 : data module size) 10 = 70MB
3	Bit 0-7 : restart command
4	Physical drive identification: Bit 0 : drive A 1 : drive B 2 : drive C 3 : drive D 4 : drive E 5 : drive F 6 : drive G 7 : drive H
5	Bit 0-7 : Identifies the eight low-order bits of the cylinder address in the most recent seek argument
6	Bit 0-2 : identifies the three high-order bits of the cylinder address 3 : – 4 : 8) 5 : 4) head number 6 : 2) 7 : 1)
7	Bit 0-3 : format type of remaining sense bytes (8-23) 4-7 : encoded error message
8-23	Meaning depends on format type

3344 – Direct Access Storage (3340 Mode)

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : data check 5 : overrun 6 : track condition check 7 : seek check
1	Bit 0 : permanent error 1 : invalid track format 2 : end of cylinder 3 : – 4 : no record found 5 : file protected 6 : write inhibited 7 : operation incomplete
2	Bit 0 : RPS feature present 1 : correctable 2 : – 3 : environmental data present 4 : Compatibility Mode / 3344 5 : HDA Size 3 Bit 6 : HDA Size 2 Bit 7 : HDA Size 1 Bit

SENSE INFORMATION SUMMARY (. . . Cont'd)

3344 – Direct Access Storage (Cont'd)

<u>Sense Byte</u>	<u>Designation</u>
3	Bit 0-7 : restart command
4	Controller device address Bit 0 : Controller Addr. Bit 2 1 : Controller Addr. Bit 1 2 : } 3 : } Controller Device Address 4 : } 5 : Device Addr. Bit 4 6 : Device Addr. Bit 2 7 : Device Addr. Bit 1
5	Bit 0-7 : Identifies the eight low-order bits of the cylinder address
6	Bit 0-3 : Identifies the four high-order bits of the cylinder address 0 : 1024 1 : 512 2 : 256 3 : 2048 4 : 8) 5 : 4) head number 6 : 2) 7 : 1)
7	Bit 0-3 : format type of remaining sense bytes (8-23) 4-7 : encoded error message
8-23	Meaning depends on format type

3350 - Direct Access Storage

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : channel bus out parity 3 : equipment check 4 : overrun 5 : not used 7 : not used
1	Bit 0 : permanent error 1 : invalid track format 2 : end of cylinder 3 : not used 4 : no record found 5 : file protected 6 : write inhibited 7 : operation incomplete
2	Bit 0 : not used 1 : correctable 2 : not used 3 : environmental data present 4 : computibility mode 5 : not used 6 : not used 7 : not used
3	Bit 0-7 : restart command
4	Bit 0-7 : physical drive identification Bit : physical drive 0 : A 1 : B 2 : C 3 : D 4 : E 5 : F 6 : G 7 : H

SENSE INFORMATION SUMMARY (. . . Cont'd)

3350 – Direct Access Storage (Cont'd)

<u>Sense Byte</u>	<u>Designation</u>
5	Bit 0-7 : low order logical cylinder address Bit : Value 0 : 128 1 : 64 2 : 32 3 : 16 4 : 8 5 : 4 6 : 2 7 : 1
6	Bit 0-2 : Identifies the three high-order bits of the cylinder address Bit 0 : CE Cylinder 1 : 3330 - 11 = 512 3330 - 1 = 256 2 : 3330 - 11 = 256 3330 - 1 = 0 3 : 16) 4 : 8) 5 : 4) Head number 6 : 2) 7 : 1)
7	Bit 0-3 : FORMAT TYPE of remaining sense bytes (8-23)
8-23	Meaning depends on format type (see 3350 MLM)

3370 – Disk Storage

<u>Sense Byte</u>	<u>Designation</u>	<u>Format</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus out parity (not used) 3 : equipment check 4 : data check 5 : overrun 6 : (unused) 7 : (unused)	0 1 0 1 4 0 – –
1	Bit 0 : permanent error 1 : (unused) 2 : (unused) 3 : (unused) 4 : (unused) 5 : file protected 6 : write inhibited 7 : operation incomplete	any – – – – 0 – 0
2	Bit 0 : check data error 1 : correctable 2 : (unused) 3 : environmental data present 4 : (unused) 5 : (unused) 6 : (unused) 7 : only logging required	4 5 – 6, 4, 1 – – – –
3-6	physical address	
7	Bit 0-3 : hex: format number 4-7 : hex: message code	
8-23	Only for diagnose Information	

SENSE INFORMATION SUMMARY (. . . Cont'd)

3410/3411 – Magnetic Tape

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : data check 5 : overrun 6 : word count zero 7 : data converter check
1	Bit 0 : noise 1-2 : B'00' = non-existent B'01' = not ready B'10' = ready and not busy B'11' = ready and busy 3 : seven track 4 : at load point 5 : write status 6 : file protected 7 : not capable
2	Bit 0-7 : track in error bits
3	Bit 0 : VRC 1 : multiple track error (PE) or LRC (NRZI) 2 : skew 3 : end data check (PE) or CRC (NRZI) 4 : envelope check (PE only) 5 : phase encoding 6 : backward 7 : -
4	Bit 0 : tape unit positioning check 1 : tape unit reject 2 : end of tape 3 : - 4 : - 5 : diagnostic track check 6 : tape unit check 7 : illegal command
5	Bit 0 : new subsystem 2 : write tape mark check 3 : PE identification burst 4 : PE compare 5 : tachometer check 6 : false end mark 7 : RPQ
6	Bit 0 : seven track 1 : short gap mode 2 : dual density 4-7 : tape unit model
7	Bit 0 : lamp check 1 : left column check 2 : right column check 3 : ready reset 4 : data security erase 5-7 : -
8	Bit 0 : - 1 : feedthrough 2 : - 3 : end velocity check 4 : no read-back data 5 : start velocity check 6 : - 7 : -

SENSE INFORMATION SUMMARY (. . . Cont'd)

3420/3803 - Magnetic Tape

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : data check 5 : overrun 6 : word count zero 7 : data converter check
1	Bit 0 : noise 1-2 : B'00' = non-existent B'01' = not ready B'10' = ready and not rewinding B'11' = ready and rewinding 3 : seven track 4 : at load point 5 : write status 6 : file protected 7 : not capable
2	Bit 0-7 : track in error bits
3	Bit 0 : VRC 1 : multiple track error (PE) or LPC (NRZI) 2 : skew 3 : end data check (PE) or CRC (NRZI) 4 : envelope check (PE only) 5 : phase encoding 6 : backward 7 : C-compare
4	Bit 0 : ALU hardware error 1 : reject tape unit 2 : tape indicate 3 : write trigger VRC 4 : microprogram detected error 5 : LWR 6 : tape unit check 7 : RPO
5	Bit 0 : new subsystem 1 : new subsystem 2 : write tape mark check 3 : PE ID burst check 4 : start read check 5 : partial record 6 : excessive postable or tape mark 7 : RPO
6	Bit 0 : seven track 1 : write current failure 2 : dual density 3 : NRZI density 4-7 : tape unit model
7	Bit 0 : lamp failure 1 : tape bottom left 2 : tape bottom right 3 : reset key 4 : data security erase 5 : erase head 6 : air bearing pressure 7 : load failure
8	Bit 0 : IBG drop while writing 1 : feed through check 2 : SDR counter 3 : early begin readback check 4 : early ending readback check 5 : slow begin readback check 6 : slow ending readback check 7 : velocity retry/restart

SENSE INFORMATION SUMMARY (. . . Cont'd)

3420/3803 - Magnetic Tape (. . . Cont'd)

Sense Byte	Designation
9	Bit 0 : SDR counter 1 : velocity change during write 2-3 : SDR counter 4 : - 5 : - 6 : - 7 : tape control reserved
10	Bit 0 : command status reject 1 : - 2 : control status reject 3 : no block on record readback check 4 : WTM not detected block 5 : tachometer start fail 6 : - 7 : velocity check
11	Bit 0 : B bus parity error, ALU 1 1 : - 2 : low ROS parity/low IC/parity on branch instr. 3 : high IC/high ROS reg parity 4 : micro program detected hardware error 5 : D bus parity error, ALU1 6 : - 7 : branch condition error, ALU2
12	Bit 0 : B bus parity error, ALU 2 1 : - 2 : low ROS parity/low IC/parity on branch instr. 3 : high IC/BC/high ROS reg parity 4 : microprogram detected hardware error 5 : D bus parity error, ALU 2 6 : - 7 : branch condition error, ALU 2
13	Bit 0-1 : tape control density 2-7 : tape control unique ID high
14	Bit 0-7 : tape control unique ID low
15	Bit 0-7 : tape unit unique ID
16	Bit 0-7 : tape unit unique ID
17	Bit 0 : two-channel switch 1-3 : tape control device switch features 4-7 : EC level of tape control
18	Bit 0 : Power check/air flow 1-3 : - 4-7 : EC level of tape unit
19	Bit 0 : primed for device and tape unit 7 1 : primed for device and tape unit 6 2 : primed for device and tape unit 5 3 : primed for device and tape unit 4 4 : primed for device and tape unit 3 5 : primed for device and tape unit 2 6 : primed for device and tape unit 1 7 : primed for device and tape unit 0
20	Bit 0 : primed for device and tape unit F 1 : primed for device and tape unit E 2 : primed for device and tape unit D 3 : primed for device and tape unit C 4 : primed for device and tape unit B 5 : primed for device and tape unit A 6 : primed for device and tape unit 9 7 : primed for device and tape unit 8

SENSE INFORMATION SUMMARY (. . . Cont'd)

3420/3803 – Magnetic Tape (. . . Cont'd)

<u>Sense Byte</u>	<u>Designation</u>
21	Bit 0 : load button depressed 1 : left reel turning 2 : right reel turning 3 : tape present 4 : reels loaded 5 : load rewind 6 : load complete 7 : load check
22	Bit 0-7 : FRU identifiers for tape control
23	Bit 0-7 : FRU identifiers for tape control

3504/3505/3525 – Card I/O

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : data check 5 : — 6 : abnormal format reset 7 : permanent error key
1	Bit 0 : permanent error 1 : automatic retry 2 : motion malfunction 3 : retry after intervention complete 4-7 : —
2-3	Used for diagnostic purposes only

3540 – Diskette

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : data check 5-7 : —
1	Bit 0 : permanent error 1 : automatic retry 2 : motion malfunction 3 : retry after intervention complete 4 : special record transferred 5-7 : —
2	Used for diagnostic purposes only
3	Bit 0-7 : cylinder address in binary
4	Bit 0-7 : head address, must be binary zero
5	Bit 0-7 : record address in binary

3881 – Optical Mark Reader

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : — 5 : — 6 : unusual command sequence 7 : —

SENSE INFORMATION SUMMARY (. . . Cont'd)

3886 – Optical Character Reader

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : – 5 : – 6 : non-initialized 7 : RCP error
1	Bit 0 : – 1 : mark check 2 : invalid format 3 : – 4 : incomplete scan 5 : – 6 : non-recovery 7 : outboard

5203 – Printer

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : – 3 : equipment check 4 : data check 5 : chain buffer parity check 6 : no channel found 7 : channel 9
1	Bit 0-7 : –
2	Bit 0 : interlock (chain gate open) 1 : forms check (jam) 2 : coil protect check 3 : subscan ring check 4 : chain buffer address register check 5 : hammer unit shift check 6 : any-hammer-on check 7 : thermal overload
3	Bit 0-7 : –
4	Bit 0 : hammer reset failure check 1 : no fire check 2 : misfire check 3 : print data buffer parity check 4 : check bit buffer parity check 5 : chain buffer parity check 6 : buffer address register check 7 : clock check
5	Bit 0 : open coil check 1-7 : –

5424/5425 – Multifunction Card Unit

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : bus-out check 3 : equipment check 4 : data check 5 : – 6 : no card available 7 : –

SENSE INFORMATION SUMMARY (. . . Cont'd)

5424/5425 – Multifunction Card Unit (. . . Cont'd)

<u>Sense Byte</u>	<u>Designation</u>
1	Bit 0 : read check 1 : punch check 2 : – 3 : print data check 4 : print clutch check 5 : hopper check 6 : feed check 7 : –
2	Bit 0 : – 1 : – 2 : card in primary wait station 3 : card in secondary wait station 4 : NPRO allowed 5 : hopper cycle not complete 6 : card in transport counter bit 2 7 : card in transport counter bit 1
3	Contains a hexadecimal number whose value can represent feedchecks and emitter checks in the 5425
4	Defines the card column group and tier where the error was detected which caused the first read check or punch check of a card cycle: Bit 0 : multiple error 1-2 : B'00' Tier 1 B'01' Tier 2 B'10' Tier 3 3-7 : B'00000' column group 1 B'00001' column group 2 B'11111' column group 32
5	Bit 0 : D row miscompare 1 : C row miscompare 2 : B row miscompare 3 : A row miscompare 4 : 8 row miscompare 5 : 4 low miscompare 6 : 2 row miscompare 7 : 1 row miscompare
6-10	Forms a table of the five most recent command strings Bit 0 : Secondary 1 : print four lines 2 : stacker select M2 3 : stacker select M3 4 : punch 5 : feed command sample 6 : print 7 : read

8809 – Tape Unit

<u>Sense Byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : – 3 : equipment check 4 : data check 5 : overrun 6 : – 7 : –
1	Bit 0 : noise 1 : tape unit status A 2 : tape unit status B 3 : – 4 : at load point 5 : write status 6 : file protected 7 : not capable

SENSE INFORMATION SUMMARY (. . . . Cont'd)

8809 – Tape Unit (Cont'd)

<u>Sense Byte</u>	<u>Designation</u>
2	Bit 0-7 : represent track in error pointers
3	Bit 0 : 128 ERP number 1 : 64 ERP number 2 : 32 ERP number 3 : 16 ERP number 4 : 8 ERP number 5 : 4 ERP number 6 : 2 ERP number 7 : 1 ERP number
4	Bit 0 : – 1 : – 2 : tape indicate 3 : permanent error 4 : host detected error 5 : loop write to read error 6 : not used 7 : not used
5	Bit 0 : – 1 : – 2 : – 3 : PE-ID burst check 4 : – 5 : – 6 : – 7 : –
6	Contains all zeros
7	Bit 0 : 8 format code 1 : 4 format code 2 : 2 format code 3 : 1 format code 4 : Data security erase 5 : – 6 : – 7 : –
8-31	Sense bytes 8-31 are only used for hardware diagnostics

DOC – Display Operator Console

<u>Sense byte</u>	<u>Designation</u>
0	Bit 0 : command reject 1 : intervention required 2 : – 3 : equipment check 4 : – 5 : – 6 : – 7 : operation check

CHAPTER II
VSE/AF2 GENERAL INFORMATION



IPL CONTROL STATEMENTS

Operation	Operand	Remarks
ADD	cuu[:cuu]...cuu][,(S)],device-type [,ss],ssss,sssss,SHR]	<p>The ADD command is used to define the physical devices attached to the system. Either a single device or a series of devices of the same type can be added with one command.</p> <p>cuu Indicates the channel and unit number of the device(s) to be added.</p> <p>cuu:cuu A series of devices of the same type is to be added. or cuu...cuu</p> <p>S Device can be switched. The lock-file-device must not be defined as switchable. S must be in brackets.</p> <p>device-type Specifies the device type code.</p> <p>ss Device specifications.</p> <p>ssss Tape. ss specifies the mode setting (see ASSGN Statement). If absent, the following values are assigned: C0 for 9-track tapes (2400, 3410 series) D0 for 9-track tapes (3420 series) 60 for 8809 Magnetic Tape Unit 90 for 7-track tapes 00 for non-tapes 00, 01, 02, and 03 are invalid as ss for magnetic tape. 1053, 3284, 3286, 3287, 3288, 3289. ss must be entered as 01. ss is required for a 3284/3286/3287 printer used as console printer for a 3277 operator console. The required entry is 02 or 04. 2702. ss specifies SADxxx (Set Address) requirements: 00 for SADO (default) 01 for SAD1 02 for SAD2 04 for SAD3</p> <p>1270, 1275, 1419, 1419P, and 1419S. ss specifies the external interrupt bit associated with magnetic ink or optical character readers. The settings 01 through 20 correspond to the external interrupt code in low storage byte 87, bits 7 through 2 respectively. The corresponding external lines to which the control units are attached are as follows: 01 byte 87 bit 7 02 byte 87 bit 6 04 byte 87 bit 5 08 byte 87 bit 4 10 byte 87 bit 3 20 byte 87 bit 2</p> <p>1018. ss can be: 00 no error correction feature (default) 01 error correction feature</p> <p>3704/3705. ss is required and specifies the type of channel adapter:</p>

IPL CONTROL STATEMENTS (. . . Cont'd)

Operation	Operand	Remarks
ADD (Cont'd)		<p>01: Type 1/4 channel adapter 02: Type 2/3 channel adapter 10: 3705 SDLC ICA on 4300</p> <p>2703. For the 2703 of the Model 115 or 125, ss, ssss, or sssss is used to specify the line mode setting for a Start/Stop line or a BSC line. The specified value is right-justified and the rest is filled with zeros.</p> <p>SHR Indicates that the device to be added may be shared by two or more CPUs. SHR is valid only for 33xx CKD and 3370 FBA. SHR may not be specified together with S.</p>
DEF	<p>SYSREC=cuu,SYSCAT={cuu UA} [,SYSDMP=cuu]</p>	<p>The DEF command is used to assign SYSREC, SYSCAT, SYSDMP.</p> <p>SYSCAT=cuu Indicates the channel and unit number of the physical device to be assigned to SYSCAT.</p> <p>SYSCAT=UA Must be specified if VSE/VSAM not installed.</p> <p>SYSREC=cuu Indicates the channel and unit number of the physical device to be assigned to SYSREC.</p> <p>SYSDMP=cuu Indicates the channel and unit number of the physical device assigned to SYSDMP. SYSDMP can be assigned to any CKD or FBA device.</p> <p>The assignment cannot be changed until the next IPL.</p>
DEL	<p>cuu{:cuu ...cuu}</p>	<p>The DEL command is used to delete one or more devices from the PUB table.</p> <p>cuu Indicates the channel and unit number of the device(s) to be deleted.</p> <p>cuu:cuu A series of devices of the same or cuu...cuu type is to be deleted.</p>
DLA	<p>NAME=areaname[,UNIT=cuu] [,DSF={Y IN}] [CYL=n[,NCYL=m] ,BLK=n[,NBLK=m]]</p>	<p>NAME=areaname Specifies the name of the label area, which can be one to eight alphanumeric characters.</p> <p>UNIT=cuu Specifies channel and unit number. Default = SYSRES.</p> <p>DSF=Y IN Specifies whether the label area is to be data-secured. If the operand is omitted, DSF=Y (YES) is assumed.</p> <p>CYL=n Indicates, for CKD devices, the sequential number of the cylinder, relative to zero, where the label area is to begin. n must be a decimal number with one to three digits.</p> <p>NCYL=m Defines the size of the label area in cylinders. m must be a decimal number with one to three digits. Default is for 2314 2 cyl. 3330 2 cyl. 3340 3 cyl. 3350 1 cyl.</p>

IPL CONTROL STATEMENTS (. . . Cont'd)

Operation	Operand	Remarks
DLA Cont'd		<p>BLK=n Indicates, for FBA devices, the sequential number of the block, relative to zero, where the label area is to begin. n must be a decimal number minimum 2.</p> <p>NBLK=m Defines the size of the label area in blocks. m must be a decimal number minimum 12. Default is 200 blocks.</p>
DLF	UNIT=cuu[,CYL=n BLK=n] [,DSF={Y N}]	<p>The DLF command defined the cross communication area (lock file). DLF command must be the first command after ADD and DEL.</p> <p>UNIT=cuu Channel and Unit number of the device containing the lock file.</p> <p>If a new lock file, or a reallocation is required:</p> <p>CYL=n Specifies, for CKD, the sequential number (one to three digits decimal) of the cylinder, where the lock file is to begin.</p> <p>BLK=n Specifies, for FBA, the sequential number (minimum 2 decimal) of blocks, where the lock file is to begin.</p> <p>DSF=Y N Y=lock file is data-secured.</p>
DPD	UNIT=cuu,{CYL=n BLK=n} [,NCYL=m ,NBLK=m ,TYPE={N F}] [,DSF={Y N}] ,VOLID=xxxxx]	<p>The DPD command defined the page data set. The operands may be given in any order.</p> <p>UNIT=cuu Channel and unit number.</p> <p>CYL=n Specifies, for CKD, the sequential number (decimal), where the page data set is to begin.</p> <p>BLK=n Specifies, for FBA, the sequential number (decimal minimum 2) of block, where the page data set is to begin.</p> <p>NCYL=m Specifies, for a multi-extent CKD page data set, the size of one page data set extent (in cylinders). m must be a decimal number with up to three digits.</p> <p>NBLK=m Specifies, for a multi-extent FBA page data set, the size of one page data set extent (in blocks). m must be a decimal number with minimum of 4.</p> <p>TYPE=N Indicates that page data set need not be formatted.</p> <p>TYPE=F Indicates that page data set is to be formatted during IPL.</p> <p>The TYPE operand is ignored for FBA devices.</p> <p>DSF=Y N Y = page data set is data-secured.</p> <p>VOLID=xxxxx Identifies the volume serial number (one to six alphanumeric characters). If VOLID is omitted, serial number is not checked.</p> <p>For each extent of a multi-extent page data set, a separate DPD command is to be entered.</p>

IPL CONTROL STATEMENTS (. . . Cont'd)

Operation	Operands	Remarks
SET	DATE=value 1, CLOCK=value 2 [,ZONE={EAST WEST}/hh/mm]	<p>value 1 Specifies the Date in following format: mm/dd/yy mm: month (01-12) dd: day (01-31) yy: year (00-99)</p> <p>value 2 Specifies the local time in the following format: hh/mm/ss hh: hours (00-23) mm: minutes (00-59) ss: seconds (00-59)</p> <p>EAST Specifies a geographical position east of Greenwich.</p> <p>WEST Specifies a geographical position west of Greenwich.</p> <p>hh/mm A decimal value which indicates the difference in hours and minutes between local and Greenwich Mean Time. hh: 0-23 mm: 0-59</p> <p>Note: After the SET command, the TOD clock must always be enabled.</p>
SVA	[SDL=n][,PSIZE=nK][,GETVIS=nK] [,PSLD=n]	<p>SDL=n Specifies the decimal number of entries in the system directory list to be reserved for user phases and IBM-supplied phases. The maximum number that can be specified is 862.</p> <p>PSIZE=nK Specifies the size of the area within the SVA which is to be reserved for user phases. n must be a decimal number and a multiple of 2. The specified size should be large enough for the user phases and for a maintenance area which is required when a phase in the system core image library, with a copy in the SVA, is replaced. Do not specify space for the phases loaded automatically into the SVA during IPL, as IPL will reserve the necessary space.</p> <p>GETVIS=nK Indicates the size of the additional system GETVIS area. n must be a decimal number and a multiple of 2.</p> <p>PSLD=n Specifies the number of entries for a private second level directory (PSLD). Minimum and default is 5, maximum is 32.</p> <p>SVA must be the last IPL command.</p>

IPL CONTROL STATEMENTS (. . . Cont'd)

Operation	Operand	Remarks
SYS	[PAGEIN=n],[EXTENT=mK]	<p>SYS command specifies the number of page-in requests that may be queued concurrently and the amount of storage allocated for extent blocks.</p> <p>PAGEIN=n Maximum number of page-in requests. Default is 8.</p> <p>EXTENT=mK Amount of storage in the system GETVIS area for extent blocks. m should be a multiple of 2; default is 4K.</p>

JOB CONTROL - AND ATTENTION ROUTINE COMMANDS

Job Control Overview

Type of Command or Statement	Operation	Valid for		
		JCS	AR	JCC
Job Identification	JOB	X		
	/&	X		
	/+	X		
User Identification	ID	X		X
File Definition	DLBL	X		
	EXTENT	X		
	TLBL	X		
	/*	X		
Library Definition	LIBDEF	X		X
	LIBDROP	X		X
	LIBLIST	X		X
Pass Information to Operator	*	X		
Pass Information to Program	DATE	X		
	OPTION	X		
	OVEND	X		X
	UPSI	X		
Job Stream Control	BATCH		X	
	CANCEL		X	X
	PAUSE	X	X	X
	PRTY		X	
	START		X	X
	STOP			X
	TPBAL		X	
UNBATCH			see Note	
Setting System Parameters	ALLOC		X	X
	ALLOCR		X	X
	SET			X
	SIZE		X	X
	STDOPT	X		X
Operator Communications	ALTER		X	
	DSPLY		X	
	DUMP		X	
	END or ENTER key		X	X
	IGNORE		X	X
	LOG		X	X
	MAP		X	X
	MODE		X	
	MSG		X	
	NEWVOL		X	
	NOLOG		X	X
	RC		X	
	REPLID		X	
	SETMOD		X	
	UNLOCK		X	
ZONE	X			

JOB CONTROL AND ATTENTION ROUTINE COMMANDS (. . . Cont'd)

Type of Command or Statement	Operation	Valid for		
		JCS	AR	JCC
Control of I/O System	ASSGN	X		X
	CLOSE	X		X
	DVCDN			X
	DVCUP			X
	FREE		X	
	HOLD			X
	LFCB		X	
	LISTIO	X		X
	LUCB		X	
	MTC	X		X
	RESERV		X	
	RESET	X		X
	ROD			X
	SETDF		X	
	SETPRT	X		X
UCS			X	
VOLUME		X		
Execution of Program	EXEC	X		X
	RSTRT	X		
Note: Valid only in a foreground partition.				

JOB CONTROL- AND ATTENTION ROUTINE COMMANDS (. . . Cont'd)

JOB CONTROL STATEMENTS SUMMARY

ASSGN	Used at execution time to assign a specific device address to the symbolic unit name used.
CLOSE	Closes either a system or a programmer logical unit assigned to tape, disk, or diskette.
DATE	Contains a date that is put in the communications region.
DLBL	Contains file label information for DASD or diskette label checking and creation.
EXEC	Indicates the end of job control statements for a job step and that the job step is executed.
EXTENT	Defines each area, or extent, of a DASD file or diskette volume.
ID	Used to specify user identification and password.
JOB	Indicates the beginning of control information for a job.
LBLTYP	LBLTYP statement is no longer needed, since the Open/Close routines dynamically allocate label processing storage based on DLBL/EXTENT specification. If LBLTYP is included, the requested storage is allocated, but it is not used.
LIBDEF	Defines private libraries.
LIBDROP	Drops private library definitions.
LIBLIST	Lists private library definitions.
LISTIO	Used to get a listing of I/O assignments on SYSLOG or SYSLST.
MTC	Controls operations on magnetic tapes.
OPTION	Specifies one or more of the job control options.
OVEND	Indicates that no more overwrite statements will follow for the respective procedure.
PAUSE	Causes a pause immediately after processing this statement.
RESET	Resets I/O assignments to the standard assignments.
RSTRT	Restarts a checkpointed program.
SETPRT	Loads the IBM 3800 buffers.
STDOPT	Resets system defaults.
TLBL	Contains file label information for tape label checking and writing.
UPSI	(User Program Switch Indicators.) Allows the user to set program switches that can be tested.
ZONE	Initializes the zone field in the communications region.
/*	Indicates the end of a file or the end of a job step.
/&	Indicates the end of a job.
*	Job control comments.
/+	Indicates the end of a procedure.
Programming support continues for the following job control statements provided in previous versions of the system (they should, however, not be used for new applications):	
DLAB	Contains file label information for DASD label checking and creation.
LBLTYP	Defines the amount of storage to be reserved at link-edit time for processing tape and nonsequential DASD file labels in the partition.
TPLAB	Contains file label information for tape label checking and writing.
VOL	Used when a set of label information for a magnetic tape file or a DASD file is specified. It is not required with the current DLBL, EXTENT, or TLBL statements.
XTENT	Defines each area, or extent, of a DASD file. It is used in conjunction with the VOL and DLAB statements.

JOB CONTROL - AND ATTENTION ROUTINE COMMANDS (. . . Cont'd)

Operation	Operands	Remarks	Accepted by		
ALLOC	Fn=mK[,Fn=mK]...	n Indicates the number of the foreground partition. m Indicates the amount of storage to be allocated to the specified foreground partition. m must not be smaller than 128.	JCC AR		
ALLOCR	PARTITION=mK [,PARTITION=mK]...	partition Indicates the partition (BG, F1, F2, ...) to which storage is to be allocated. BGR and FnR will also be accepted. m Indicates the amount of storage to be allocated to the specified partition. m should be even. m may also be zero.	JCC AR		
ALTER	XXXXXX	Alters 1 to 16 bytes of virtual storage. XXXXXX is the hex address where alteration is to start.	AR		
[//]ASSGN	SYSxxx, <table border="1" style="display: inline-table; vertical-align: middle;"> <tr> <td>cuu (address-list) UA IGN SYSyyy device class device type</td> </tr> </table>	cuu (address-list) UA IGN SYSyyy device class device type	<table border="1" style="display: inline-table; vertical-align: middle;"> <tr> <td>,TEMP ,PERM ,VOL=volserno ,SHR ,ss ,ALT ,H1 ,H2</td> </tr> </table> <p>SYSxxx = symbolic unit name, can be: SYSRDR; SYSIPT; SYSIN; SYSPCH; SYSLST; SYSOUT; SYSLNK; SYSLOG; SYSSLB; SYSRLB; SYSCLB SYS000 to SYS254 SYSCAT, SYSREC and SYSDMP can only be assigned with DEF command at IPL time.</p> <p>cuu = channel and unit number (address-list) = a list of up to seven device addresses in the form: (cuu,...,cuu)</p> <p>UA = logical unit is to be unassigned IGN = unassign the logical unit, ignore any logical IOCS commands. Not valid for SYSRDR, SYSIPT, SYSIN, SYSCLB. Can be made temporary by TEMP option.</p> <p>SYSyyy = any system or programmer logical unit, except SYSCAT and SYSDMP</p> <p>device class = Reader, Printer, Punch, Tape (not 8809), Disk, CKD, FBA or Diskette.</p> <p>device type = device type code of any supported device.</p> <p><u>Optional Operands</u></p> <p>TEMP = the assignment is temporary PERM = the assignment is permanent VOL=volserno = specify the volume serial number, only to tapes, disks and diskettes.</p> <p>SHR = indicate the shared option for a disk device.</p> <p>ALT = specifies alternate tape unit.</p>	,TEMP ,PERM ,VOL=volserno ,SHR ,ss ,ALT ,H1 ,H2	JCS JCC
cuu (address-list) UA IGN SYSyyy device class device type					
,TEMP ,PERM ,VOL=volserno ,SHR ,ss ,ALT ,H1 ,H2					

JOB CONTROL- AND ATTENTION ROUTINE COMMANDS (. . . Cont'd)

Operation	Operands	Remarks	Accepted by																																																																																																																																		
[//]JASSGN (Cont'd)		<p>H1 = specifies input hopper 1 on 2560, 5424 or 5425. If neither H1 nor H2 is specified, H1 is assumed.</p> <p>H2 = specifies input hopper 2 on 2560, 5424 or 5425.</p> <p>H1 and H2 only valid for assignment to SYSIPT, SYSRDR, SYSIN and SYSPCH.</p> <p>ss = specifies mode setting for tapes If ss is not specified at IPL time the system assumes:</p> <p>90 for 7-track tapes C0 for 9-track (2400,3410) D0 for 9-track (3420) 60 for 9-track (8809)</p> <table border="1" data-bbox="267 580 718 1261"> <thead> <tr> <th>ss</th> <th>Density (bpi)</th> <th>Parity</th> <th>Convert Feature</th> <th>Translate</th> </tr> </thead> <tbody> <tr><td>10</td><td>200</td><td>odd</td><td>on</td><td>off</td></tr> <tr><td>30</td><td>200</td><td>odd</td><td>off</td><td>off</td></tr> <tr><td>38</td><td>200</td><td>odd</td><td>off</td><td>on</td></tr> <tr><td>20</td><td>200</td><td>even</td><td>off</td><td>off</td></tr> <tr><td>28</td><td>200</td><td>even</td><td>off</td><td>on</td></tr> <tr><td>50</td><td>556</td><td>odd</td><td>on</td><td>off</td></tr> <tr><td>70</td><td>556</td><td>odd</td><td>off</td><td>off</td></tr> <tr><td>78</td><td>556</td><td>odd</td><td>off</td><td>on</td></tr> <tr><td>60</td><td>556</td><td>even</td><td>off</td><td>off</td></tr> <tr><td>68</td><td>556</td><td>even</td><td>off</td><td>on</td></tr> <tr><td>90</td><td>800</td><td>odd</td><td>on</td><td>off</td></tr> <tr><td>B0</td><td>800</td><td>odd</td><td>off</td><td>off</td></tr> <tr><td>B8</td><td>800</td><td>odd</td><td>off</td><td>on</td></tr> <tr><td>A0</td><td>800</td><td>even</td><td>off</td><td>off</td></tr> <tr><td>A8</td><td>800</td><td>even</td><td>off</td><td>on</td></tr> <tr><td>C8</td><td>800</td><td colspan="3">single-density 9-track tapes</td></tr> <tr><td>C8</td><td>800</td><td colspan="3">dual-density 9-track tapes</td></tr> <tr><td>C0</td><td>1600</td><td colspan="3">single-density 9-track tapes</td></tr> <tr><td>C0</td><td>1600</td><td colspan="3">dual-density 9-track tapes</td></tr> <tr><td>D0</td><td>6250</td><td colspan="3">single/dual density, 9-track</td></tr> <tr><td>C0</td><td>1600</td><td colspan="3">3420 Models 4, 6, and 8</td></tr> <tr><td>90</td><td>1600</td><td colspan="3">Streaming: high speed and long gap</td></tr> <tr><td>30</td><td>(for 8809)</td><td colspan="3">Streaming: high speed and short gap</td></tr> <tr><td>50</td><td></td><td colspan="3">Start-Stop: low speed and long gap</td></tr> <tr><td>60</td><td></td><td colspan="3">Start-Stop: low speed and short gap</td></tr> </tbody> </table>	ss	Density (bpi)	Parity	Convert Feature	Translate	10	200	odd	on	off	30	200	odd	off	off	38	200	odd	off	on	20	200	even	off	off	28	200	even	off	on	50	556	odd	on	off	70	556	odd	off	off	78	556	odd	off	on	60	556	even	off	off	68	556	even	off	on	90	800	odd	on	off	B0	800	odd	off	off	B8	800	odd	off	on	A0	800	even	off	off	A8	800	even	off	on	C8	800	single-density 9-track tapes			C8	800	dual-density 9-track tapes			C0	1600	single-density 9-track tapes			C0	1600	dual-density 9-track tapes			D0	6250	single/dual density, 9-track			C0	1600	3420 Models 4, 6, and 8			90	1600	Streaming: high speed and long gap			30	(for 8809)	Streaming: high speed and short gap			50		Start-Stop: low speed and long gap			60		Start-Stop: low speed and short gap			
ss	Density (bpi)	Parity	Convert Feature	Translate																																																																																																																																	
10	200	odd	on	off																																																																																																																																	
30	200	odd	off	off																																																																																																																																	
38	200	odd	off	on																																																																																																																																	
20	200	even	off	off																																																																																																																																	
28	200	even	off	on																																																																																																																																	
50	556	odd	on	off																																																																																																																																	
70	556	odd	off	off																																																																																																																																	
78	556	odd	off	on																																																																																																																																	
60	556	even	off	off																																																																																																																																	
68	556	even	off	on																																																																																																																																	
90	800	odd	on	off																																																																																																																																	
B0	800	odd	off	off																																																																																																																																	
B8	800	odd	off	on																																																																																																																																	
A0	800	even	off	off																																																																																																																																	
A8	800	even	off	on																																																																																																																																	
C8	800	single-density 9-track tapes																																																																																																																																			
C8	800	dual-density 9-track tapes																																																																																																																																			
C0	1600	single-density 9-track tapes																																																																																																																																			
C0	1600	dual-density 9-track tapes																																																																																																																																			
D0	6250	single/dual density, 9-track																																																																																																																																			
C0	1600	3420 Models 4, 6, and 8																																																																																																																																			
90	1600	Streaming: high speed and long gap																																																																																																																																			
30	(for 8809)	Streaming: high speed and short gap																																																																																																																																			
50		Start-Stop: low speed and long gap																																																																																																																																			
60		Start-Stop: low speed and short gap																																																																																																																																			
BATCH	[BGIFn]	Start or continue processing	AR																																																																																																																																		
CANCEL	blank		JCC																																																																																																																																		
CANCEL	{BGIFn}[,DUMPI ,PARTDUMPI ,NODUMPI][,SYSDMPI ,NOSYSMDPI]	<p>Cancels current job in specified partition, not for VSE/POWER.</p> <p>DUMP = causes a dump</p> <p>PARTDUMP = causes a dump of the specified partition</p> <p>NODUMP = suppresses the DUMP option</p> <p>SYSDUMP = DUMP is to be written on SYSDMP</p> <p>NOSYSMDPI = DUMP is to be written on SYSLST</p>	AR																																																																																																																																		

JOB CONTROL- AND ATTENTION ROUTINE COMMANDS (. . . Cont'd)

Operation	Operands	Remarks	Accepted by
CANCEL	(BGIFn cuu)	After message 1140D Request Cancel	AR
[//]CLOSE	SYSxxx[,cuu[,ss ,UA ,IGN ,ALT ,SYSyyy ,device-class ,device-type]	Closes system or programmer logical units assigned to tape, disk or diskette. SYSxxx: JCC for Disk or Diskette: SYSIN, SYSRDR, SYSIPT, SYSPCH, SYSLST. JCC or JCS for Tape: SYSPCH, SYSLST, SYSOUT, SYS000 - SYS254. All other operands described in ASSGN command.	JCC JCS
//DATE	{mm/dd/yy or dd/mm/yy }	mm month (01-12) dd day (01-31) yy year (00-99)	JCS
//DLBL	filename,['file-ID'], [date],[codes][,(DSF) [,BUFSP=n] [,CAT=filename] [,BLKSIZE=n] [,CISIZE=n] [,DISP=m] [,RECORDS=n] [,RECSIZE=n]	filename: 1 to 7 alphameric characters, the first of which must be alphabetic file-ID: 1 to 44 alphameric characters (one to eight alphameric characters for the 3540 diskette) date: 1 to 6 characters (yy/ddd) codes: 2 to 4 alphabetic characters (SD, DA, DU, ISC, ISE, VSAM) DSF: specifies that a data secured file is to be created or processed BUFSP=n: specifies, for a VSE/VSAM file, the number of bytes of virtual storage (0-999999) to be allocated as buffer space CAT=filename: specifies filename (1 to 7 alphameric characters) of the DLBL statement for the catalog owning this VSAM file. BLKSIZE=n: a number from 1 to 32,768 (only valid for SAM files on 3350 and 3330-11) CISIZE=n: Permits specification of an FBA control interval size for SAM and DAM files or FBA devices in order to improve space utilization on such devices. A number from 1 to 32,768. DISP=m: Permits specification of data set disposition, only for a VSE/VSAM file. m can be: NEW(NEW, KEEP)(NEW, DELETE)(NEW,DATE) OLD(OLD,KEEP)(OLD, DELETE)(OLD,DATE) (,KEEP)(,DELETE) (,DATE) RECORDS=n: Permits specification of the number of records for prim. and sec. data set allocation, only for a VSE/VSAM file. Formats: RECORDS=n or RECORDS=(n1,n2) n or n1,n2 must not be zero. RECSIZE=n: Permits the average record length of the VSE/VSAM file. n must not be zero.	JCS

JOB CONTROL- AND ATTENTION ROUTINE COMMANDS (. . . Cont'd)

Operation	Operands	Remarks	Accepted by		
DSPLY	ADDRESS xxxxxx	Displays 16 bytes of virtual storage, begin with Hex Addr. xxxxxx	AR		
DUMP	<table border="0"> <tr> <td style="border: 1px solid black; padding: 2px;">S BG Fn BGS FnS SVA SVAS BUFFER addr,addr ALL</td> <td style="padding: 0 10px;">,cuu</td> </tr> </table>	S BG Fn BGS FnS SVA SVAS BUFFER addr,addr ALL	,cuu	<p>The DUMP command allows the operator to DUMP part or all of virtual storage on a printer, tape, or disk device (CKD or FBA). Note: There must be no blank between the operands.</p> <p>If the first operand is omitted, the following is dumped: Control Registers, General and Floating-Point Registers for each partition, contents of all partitions in which programs are currently running.</p> <p>S Same as above, the contents of the supervisor area are also dumped.</p> <p>BG The contents of the specified partition and its associated registers are dumped. If a program is running in real mode in the specified partition, only the real, not the associated virtual partition, is dumped. If a program is running in virtual mode in the specified partition, the virtual partition is dumped, including any fixed pages. The areas acquired through GETVIS in the partition are also dumped.</p> <p>BGS Same as if BG or Fn was specified; however, the contents of the supervisor area are also dumped.</p> <p>FnS</p> <p>SVA The contents of the SVA are dumped.</p> <p>SVAS The contents of the SVA and of the supervisor are dumped.</p> <p>BUFFER The contents of the SDAID buffer are dumped on tape or disk. This operand is rejected in case of output to the printer.</p> <p>address,address Specifies storage area between the two hexadecimal addresses and associated registers.</p> <p>cuu Specifies the device on which the output is to be written.</p> <p>ALL The contents of the supervisor, the SVA, and all partitions are dumped.</p>	AR
S BG Fn BGS FnS SVA SVAS BUFFER addr,addr ALL	,cuu				
DVCDN	cuu	cuu channel and unit number	JCC		
DVCUP	cuu	cuu channel and unit number	JCC		
END or ENTER	blank	End of SYSLOG communications Press END key for the 3210 and 3215 printer keyboards Press ENTER key for DOC	JCC AR		
[/]/EXEC	[[PGM=]progrname] [,REAL] [,SIZE=size][,GO]	<p>PGM=progrname The name of the program in CIL.</p> <p>REAL Job step will be executed in real mode.</p> <p>SIZE=size Can be specified in following formats: SIZE=nk SIZE=AUTO SIZE=(AUTO,nk)</p>	JCS JCC		

JOB CONTROL- AND ATTENTION ROUTINE COMMANDS (. . . Cont'd)

Operation	Operands	Remarks	Accepted by
[//]EXEC (Cont'd)		GO Specifies, for the compiler step, that the program is to be link-edited and executed automatically after it has been compiled.	
[//]EXEC	PROC=procname[,OV]	PROC=procname Name of procedure retrieved from procedure library. OV Overriding statements follow EXEC	JCS
//EXTENT	{symbolic-unit}, {serial-number},{type}, {sequence-number}, {relative-track block}, {number-of-tracks blocks}, {split-cylinder-track}	symbolic unit 6 alphameric characters serial number 1 to 6 alphameric characters type 1 numeric character sequence number 1 to 3 numeric characters 0 - 255 relative track/block 1 to 5 numeric characters (CKD-DEVICES) more than 2 for FBA number of tracks/blocks 1 to 5 numeric characters (CKD-DEVICES) number of blocks (FBA-DEVICES) split cylinder track 1 or 2 numeric characters (CKD only)	JCS
FREE	cuu	channel and unit number of the device to be freed.	AR
HOLD	Fn[,Fn]...	Causes the assignments for the specified foreground parttion(s) to remain in affect until the end of the next job.	JCC
[//]ID	USER=user-id, PWD=password	user-id Specifies the user identifier, which must be four alphameric characters. password Specifies the password of the user, which can be three to six alphameric characters.	JCS JCC
IGNORE	blank	Ignore abnormal condition	AR JCC
//JOB	jobname {accounting information}	jobname One to eight alphameric characters accounting information One to sixteen characters	JCS
LFCB	cuu,phasename {,FORMS=xxxx} {,LPI=n},{,NULMSG}	cuu channel and unit number of the printer phasename Name of CIL phase that contains the buffer load image. FORMS=xxxx Forms number of the paper, used with the new FCB load. LPI=n Indicates the required setting of the carriage clutch, 6 or 8 lines per inch. Not for PRT1. NULMSG Suppressed the printing of buffer load verification message.	AR
[//] LIBDEF	{CL RL SL PL} {,SEARCH=(name, name,...)} {,FROM=name} {,TO=name} {,NEW=name} {,PERM TEMP}	Defines a chain of libraries. At least one of SEARCH, FROM, TO or NEW must be specified. CL/RL/SL/PL Type of library SEARCH=(name,name,...) Specifies the names of libraries to be chained. 1 to 7 alphameric characters.	JCC JCS

JOB CONTROL - AND ATTENTION ROUTINE COMMANDS (. . . Cont'd)

Operation	Operands	Remarks	Accepted by
[//] LIBDEF (Cont'd)		<p>FROM=name Name of an input library to be used by XSERV or CORGZ MERGE. 1 to 7 alphameric characters.</p> <p>TO=name Name of library to be used for output, update, delete, or condense by LNKEDT, MAINT or CORGZ MERGE. 1 to 7 alphameric characters.</p> <p>NEW=name Name of library which is to be created by CORGZ NEWVOL program. 1 to 7 alphameric characters. Not specify PERM.</p> <p>PERM/TEMP Permanent or temporary.</p>	
[//] LIBDROP	{CL RL SL PL} [,SEARCH][,FROM] [,TO][,NEW][,ALL] [,PERM],TEMP]	<p>Reset a or all libraries, defines by LIBDEF. At least one of SEARCH, FROM, TO, NEW or ALL must be specified.</p> <p>CL/RL/SL/PL Type of library</p> <p>SEARCH Specify the library name, FROM defined with LIBDEF state- TO ment, which is to be dropped. NEW</p> <p>ALL Indicates that all library defini- tions for the specified library type are to be dropped.</p> <p>PERM/TEMP Indicates whether the per- manent or the temporary library definitions are to be dropped.</p>	JCC JCS
[//] LIBLIST	{CL RL SL PL} [,BG Fn,*],ALL] [,SYSLST],SYSLOG]	<p>CL/RL/SL/PL Indicates the type of library definition which is to be displayed.</p> <p>BG Fn Indicates, that the libraries of the specified partition are to be listed.</p> <p>* Indicates that the libraries of the partition in which the LIBLIST statement was given are to be listed (default).</p> <p>ALL Indicates that the libraries of all partitions are to be listed.</p> <p>SYSLST/SYSLOG The device on which the libraries are to be listed.</p>	JCC JCS
[//] LISTIO	{ ALL ASSGN BG cuu DOWN Fn PROG SYS SYSxxx UA UNITS }	Causes listing of I/O assignments on SYSLST for JCS and SYSLOG for JCC appropriate the specified operand.	JCS JCC
LOG	blank	Causes logging of job control commands and statements on SYSLOG.	JCC AR
LUCB	cuu,phasename [,FOLD][,NOCHK] [,TRAIN=xxxxxx] [,NULMSG]	Causes the UCB of printer to be loaded. cuu channel and unit number of the printer phasename name of system CIL phase which contains the buffer	AR

JOB CONTROL- AND ATTENTION ROUTINE COMMANDS (. . . Cont'd)

Operation	Operands	Remarks	Accepted by
LUCB (Cont'd)		FOLD lower case as upper case characters NOCHK suppresses data check between printline character and UCB TRAIN indicates the train (chain) 1 to 6 characters NULMSG suppressed the buffer load verification message	
MAP	blank	Causes a map of areas in real and virtual storage to appear on SYSLOG	JCC AR
MODE	IR CR CE, cuu, I[xx, y] , D[xx, y] , N R STATUS HIR] ECC] , M, C, R, Q, TH[, E=eeee] [, T=tttt]	Allows to alter the recording mode For 115/125 or 4300 only IR, CR and CE may be used. For 135/138 only valid operands are: MOCE CE, ... MODE STATUS MODE ECC, Q MODE ECC, R For explanation of operands see System Control Statements.	AR
MSG	{BGIFn}	Transfers control to message routine	AR
[//]MTC	opcode, {cuu SYSxxx} [, nn]	opcode BSF, BSR, DSE, ERG, FSF, FSR, REW, RUN, or WTM SYSxxx Any logical unit cuu Specifies the channel and unit number (in hex) nn dec. number (01-99) of times	JCS JCC
NEWVOL	{BGIFn}[, IGNORE]	Indicates that a new volume has been mounted for the specified partition.	AR
NOLOG	blank	Suppresses logging of same job control commands and statements on SYSLOG .	JCC AR
//OPTION	option[, option] . . .	Options can any of the following: ACANCEL Cancel job if attempt to assign device is unsuccessful NOACANCEL Await operator action if a device cannot be assigned ALIGN Align constants and date areas on boundaries NOALIGN Suppress ALIGN option CATAL Catalog program or phase in core image library after completion of Linkage Editor run DECK Output object module on SYSPCH NODECK Suppress DECK option DUMP Dumps the registers, supervisor area, partition, the used part of the system GETVIS area, and the SVA phase in error if the error occurred in the SVA. The dump will be recorded on SYSLST, if assigned, in the case of an abnormal program end (such as program check). PARTDUMP Dump registers, selected supervisor control blocks, and temporary real or virtual partition on SYSLST in case of abnormal program end.	JCS

JOB CONTROL- AND ATTENTION ROUTINE COMMANDS (. . . Cont'd)

Operation	Operands	Remarks	Accepted by
//OPTION (Cont'd)		<p>NODUMP Suppress DUMP or PARTDUMP option.</p> <p>EDECK Punch source macro definitions on SYSPCH</p> <p>NOEDECK Suppress EDECK option</p> <p>ERRS Output listing of all errors in source program on SYSLST.</p> <p>NOERRS Suppress ERRS option</p> <p>LINK Write output of language translator on SYSLNK for linkage editing</p> <p>NOLINK Suppress LINK option</p> <p>LIST Output listing of source module on SYSLST</p> <p>NOLIST Suppress LIST option</p> <p>LISTX Output of object module on SYSLST</p> <p>NOLISTX Suppress LISTX option</p> <p>LOG Log control statements on SYSLST</p> <p>NOLOG Suppress LOG option</p> <p>ONLINE Causes fetching of all programs for execution from the system core image library, although a private core image library is assigned.</p> <p>PARSTD Causes all DASD, diskette, or tape labels to be written on the partition standard subarea.</p> <p>PARSTD=ADD All label information stored permanently in partition standard subarea.</p> <p>PARSTD=DELETE Deletes from the partition standard subarea. Must be the last option.</p> <p>PARSTD=Fn All label information stored perm. in the partition standard subarea of specified foreground partition.</p> <p>RLD Output listing of RLD information on SYSLST.</p> <p>NORLD Suppress RLD option.</p> <p>STDLABEL Causes all DASD, diskette, or tape labels to be written on the system standard subarea.</p> <p>STDLABEL=ADD All label information stored perm. in the system standard subarea.</p> <p>STDLABEL=DELETE Deletes from the system standard subarea. Must be the last option.</p> <p>SUBLIB=DF Causes assembler and ESERV program to retrieve nonedited macros and copy-books from D-sublibrary and edited macros from the F-sublibrary of the source statement library.</p>	

JOB CONTROL AND ATTENTION ROUTINE COMMANDS (. . . Cont'd)

Operation	Operands	Remarks	Accepted by
//OPTION (Cont'd)		<p>SUBLIB=AE Causes assembler and ESERV program to retrieve nonedited macros from the A-sublibrary and edited macros from the E-sublibrary of the source statement library.</p> <p>SYM Produce symbol table or data division map on SYSLST.</p> <p>NOSYM Suppress SYM option.</p> <p>SYSDMP Indicates that dumps are to be written on SYSDMP.</p> <p>NOSYSDMP Indicates that dumps are to be written on SYSLST.</p> <p>SYSPARM=string Specifies a value for assembler system variable symbol and SYSPARM.</p> <p>TERM Error messages are written on SYSLOG.</p> <p>NOTERM Suppress the TERM option.</p> <p>USRLABEL Causes all DASD, diskette, or tape labels to be written temp. in the partition temp. subarea.</p> <p>XREF Output symbolic cross-reference list on SYSLST.</p> <p>SXREF The assembler writes the symbolic cross-reference list on SYSLST; printing of all unreferenced labels is suppressed.</p> <p>NOXREF Suppress XREF or SXREF option.</p> <p>NOFASTTR Suppresses fast CCW translation for the current job.</p> <p>48C 48-character set on SYSIPT 60C 60-character set on SYSIPT</p>	
// OVEND	[comments]	Indicates end of override statements for a cataloged procedure.	JCS JCC
// PAUSE	[comments]	Causes pause immediately after processing this statement. PAUSE statement is always printed on SYSLOG. If no 3210, 3215 or DOC is available the statement is ignored.	JCS JCC
// PAUSE	[BGIFn][,EOJ]	Causes pause at end of current job step or at end of job.	AR
PRTY	blank partition[,partition] partition=partition [=partition]...	Allows the operator to display or change the priority of partitions.	AR AR AR
RC	blank	The RC (Request Cancel) Command is used to cancel a partition and the attention routine is not available.	AR
REPLID	blank	The REPLID command allows the operator to display the reply-ID's for all messages for which replies are still pending.	AR
RESERV	cuu	Reserve a device for VSE/VSAM space management.	AR
// RESET	{ SYS PROG ALL SYSxxx }	Resets I/O device assignments.	JCS JCC

JOB CONTROL- AND ATTENTION ROUTINE COMMANDS (. . . Cont'd)

Operation	Operands	Remarks	Accepted by
ROD	blank	Causes all SDR counters for all non-teleprocessing devices on the recorder file on SYSREC to be updated from the SDR counters in main storage.	JCC
//RSTRT	SYSxxx,nnnn [,filename]	SYSxxx Symbolic unit name of the device on which the checkpoint records are stored. Can be SYS000 - SYSnnn. nnnn four character identification of the checkpoint record to be used for restart. filename symbolic name of the DASD file to be used for restarting.	JCS
SET	[,UPSI=value 1] [,LINECT=value 2] [,RCLST=value 3] [,RCPCH=value 4] [,RF=value 5] [,DATE=value 6] [,HC=value 7] [,SDL]	value 1 0, 1 or X value 2 standard number of lines for output on each page of SYSLST value 3 decimal number indicating minimum number of SYSLST disk records remaining to be written before operator warning value 4 decimal number indicating minimum number of SYSPCH disk records remaining to be written before operator warning value 5 defines to the system the status of the recorder file (IJSYSREC) on SYSREC used by the RMSR feature RF= { YES } -file exists { CREATE } -create file value 6 in one of the following formats: mm/dd/yy or dd/mm/yy mm: month (01-12) dd: day (01-31) yy: year (00-99) value 7 HC= { YES } { NO } { CREATE } YES: hard-copy file exists NO: no recording performed CREATE: create a hard-copy file SDL This operand makes it possible to ADD phase names to the system directory list and, optionally, to load phases into the SVA	JCC
SETDF	{3800 cuu} [,BURST={Y N}] [,CHARS={table name}] [,FCB={fcb name}] [,FLASH={overlay name}] [,FORMS={forms name}] [,LIST] [,MODIFY={copymod name}] [,RESET]	SETDF allows to set and/or reset default values for 3800, or display the default values.	AR
SETMOD	cuu[,MODE]	The SETMOD command, valid for the 8809 magnetic tape unit cuu Specifies the channel and unit number of the 8809	AR

JOB CONTROL- AND ATTENTION ROUTINE COMMANDS (. . . Cont'd)

Operation	Operands	Remarks	Accepted by
SETMOD (Cont'd)		<p>mode Can be one of the following: 90 or HL — high speed and long gap (streaming) 30 or HS — high speed and short gap (streaming) 50 or LL — low speed and long gap (start-stop) 60 or LS — low speed and short gap (start-stop)</p> <p>If the mode operand is omitted, the default mode setting of 60 (or LS) is assumed.</p>	
SETPRT	<p>SYSxxx[,BURST={N Y *}]</p> <p>[,CHARS={table name}* {(table name, . . .)}]</p> <p>[,COPIES=number][,DCHK={B U}]</p> <p>[,DEBUG={ (NORM) TERM DUMP TRAC }]</p> <p>[,DFLT={N Y}]</p> <p>[,FCB={fcb name}* {(fcb name,V)} {(*,V)}]</p> <p>[,FLASH={overlay name}*[,count] {(overlay name, {count 255})} {(*[{count 255})}]}</p> <p>[,FORMS={forms name}*][INIT={N Y}]</p> <p>[,MODIFY={copymod name}* {(copymod name,table name)}]</p> <p>[,SEP=O][,TRC={N Y}]</p>	<p>Allows to set the IBM 3800 Printing Subsystem with user-specified values.</p>	JC
SIZE	partition=mK [,partition=mK] . . .		JCC AR
START	[BG Fn] Fn	Same as BATCH	AR JCC
[//] STDOPT	option[,option] . . .	<p>The STDOPT command can be used to reset in all partitions the permanent job control options which were established at system initialization.</p> <p>The command can only be given in the background partition.</p> <p>The options, which can appear in any order, are as follows (the first keyword is always the default value):</p> <p>ALIGN <i>yes/no</i> Specifies if the assembler is to align data on halfword or fullword boundaries, according to the type of instruction used. A supervisor must be assembled with ALIGN=YES to avoid hard waits.</p> <p>ACANCEL <i>No/yes</i> Specifies if job control is to cancel jobs automatically (ACANCEL=YES) or to wait for operator intervention (ACANCEL=NO) after an unsuccessful attempt to assign a device. (Note that the LOG command suppresses the ACANCEL function).</p>	JCC JCS

JOB CONTROL- AND ATTENTION ROUTINE COMMANDS (. . . Cont'd)

Operation	Operands	Remarks	Accepted by
[//] STDOPT (Cont'd)		<p>CHARSET <u>48C/60C</u> Specifies either the 48- or 60-character set for PL/I translator input on SYSIPT.</p> <p>DATE <u>MDY DMY</u> Specifies the format of the date: MDY=month/date/year. DMY=day/month/year.</p> <p>DECK <u>YES NO</u> Specifies if language translators are to produce object modules on SYSPCH.</p> <p>DUMP <u>YES NO PART</u> Specifies if a dump of the registers and virtual storage is to be written on SYSLST in case of an abnormal program end. PART specifies that a dump of the supervisor control blocks and the virtual storage of the partition is to be written on SYSLST.</p> <p>EDECK <u>NO YES</u> Specifies if the assembler is to create and punch edited macros on SYSPCH.</p> <p>ERRS <u>YES NO</u> Specifies if compilers are to summarize all errors in source programs on SYSLST. Assembler and PL/I always assume ERRS=YES.</p> <p>LINES <u>50 nn</u> Specifies the number of lines per page on SYSLST. The minimum is 30, the maximum is 99. (If job control is running in another partition at the same time, the new value becomes effective in that partition when the next page is started).</p> <p>LIST <u>YES NO</u> Specifies if language translators are to write source module listings and diagnostics on SYSLST.</p> <p>LISTX <u>NO YES</u> Specifies if compilers are to write hexadecimal object module listings on SYSLST.</p> <p>LOG <u>YES NO</u> Specifies if all job control statements are to be listed on SYSLST. Invalid statements and commands will be listed on SYSLST if it is assigned.</p> <p>RLD <u>NO YES</u> Specifies if the relocation dictionary information is to be printed.</p>	

JOB CONTROL- AND ATTENTION ROUTINE COMMANDS (. . . Cont'd)

Operation	Operands	Remarks	Accepted by
//] STDOPT (Cont'd)		<p>SXREF <u>NO</u>YES Specifies whether the assembler is to print short cross-reference lists on SYSLST. The printing of unreferenced labels is suppressed instead. SXREF=YES forces XREF=NO.</p> <p>SYM <u>NO</u>YES SYM=YES specifies that the PL/I compiler is to produce a symbol and offset table listing on SYSLST, or that American National Standard Cobol is to produce a data division glossary.</p> <p>SYSDMP <u>NO</u>YES YES indicates that dumps are to be written on SYSDMP and NO that they are to be written on SYSLST.</p> <p>TERM <u>NO</u>YES Specifies whether messages from a compiler are to be displayed on SYSLOG.</p> <p>XREF <u>YES</u>NO XREF=YES specifies that the assembler is to write symbolic cross-reference lists on SYSLST, or that American National Standard Cobol is to produce a cross-reference listing. XREF=YES forces SXREF=NO.</p>	
STOP	blank	Stops batched-job progr. processing	JCC
//TLBL	<p>filename, ['file-ID'], [date], [file serial number], [volume sequence number], [file sequence number], [generation number], [version number]</p> <p>Note: For ASCII file processing the fourth and fifth operands are called set identifier and file section number, respectively.</p>	<p>filename One to seven alphameric characters, the first of which must be alphabetic.</p> <p>'file-ID' One to seventeen alphameric characters.</p> <p>date One to six characters (yy/ddd or d-dddd)</p> <p>{ [file serial number (EBCDIC): One to six alphameric characters] [set identifier (ASCII): Six alphameric characters]</p> <p>{ [volume sequence number (EBCDIC)] [file section number (ASCII)] } One to four numeric characters</p> <p>file sequence number One to four numeric characters.</p> <p>generation number One to four numeric characters.</p> <p>version number One to two numeric characters.</p>	JCS
TPBAL	[n]	<p>n = number of partitions in which processing can be delayed (0, 1, 2, . . . , number of partitions minus one).</p> <p>Allows the operator to display or alter the status of the Teleprocessing Balancing function.</p>	AR

JOB CONTROL- AND ATTENTION ROUTINE COMMANDS (. . . Cont'd)

Operation	Operands	Remarks	Accepted by
UCS	SYSxxx,phasename [,FOLD][,BLOCK] [,NULMSG]	Causes the 240-character universal character set contained in the core image library phase specified by phasename to be loaded as buffer storage in the IBM 2821 CU. SYSxxx must be assigned to a 1403 Printer with the UCS feature.	JCC
UNBATCH	blank	Terminates foreground processing	JCC
UNLOCK	SYSTEM=sys-id	sys-id Specifies the CPU-ID of the CPU which broke down. Release all locks belonging to the named system.	AR
//UPSI	nnnnnnnn	n 0, 1 or X	JCS
VOLUME	[c cu cuu]	The VOLUME command provides the operator with a short summary of the volumes mounted on DASD devices, together with an indication of whether or not a volume is in use.	AR
//ZONE	{EAST} {WEST} /hh/mm	EAST A geographical position east of Greenwich. WEST A geographical position west of Greenwich. hh/mm A decimal value which indicates difference in hours and minutes between local time and Greenwich Mean Time. hh may be in the range 0 - 12; mm in the range 0 - 59.	JCS
/+	[comments]	Indicates end of procedure.	JCS
/*	[comments]	Indicates end of data file.	JCS
/&	[comments]	Columns 1 and 2 are the only columns checked. Comments appear on SYSLOG and SYSLST at EOJ.	
*	comments	Column 2 must be blank.	JCS

LINKAGE EDITOR CONTROL STATEMENTS

Operation	Operands	Remarks
ACTION	[CLEAR][,MAP ,NOMAP] [,NOAUTO][,CANCEL] [,SMAP][,ICMAP]	Indicates Linkage Editor options: CLEAR Indicates that the unused portion of the core image library will be set to binary zero before the beginning of the Linkage Editor function. MAP Indicates that SYSLSY is available for diagnostic messages. In addition, a virtual storage map is printed on SYSLSY. NOMAP Indicates that SYSLSY is not available when performing the linkedit function. NOAUTO Indicates that the AUTO LINK function is to be suppressed. CANCEL Cancels the job automatically if any of the errors 2100I through 2170I occur. SMAP Indicates that in addition to the CSECT listing ordered by load address, a listing of the CSECT names ordered alphabetically is also generated. This list may be useful if a phase consists of many CSECTs. ICMAP Indicates that a table containing information on the storage layout of the phase is appended to each phase. This information may be useful for problem determination.
ENTRY	[entrypoint]	entrypoint Symbolic name of an entry point. If the operand field is blank, the Linkage Editor uses as transfer address the first significant address provided in an END record encountered during generation of the first phase.
INCLUDE	[modulename][,(name list)]	If both operands are omitted the object module to be included is assumed to be on SYSIPT. If the first operand is present, the object module is assumed to be in either the private- or the system relocatable library. If the first operand is omitted and the second operand is present, the object module to be included is assumed to be in the input stream (SYSLNK). modulename Symbolic name of the module as used when cataloged in the relocatable library. It consists of one to eight alphanumeric characters. (namelist) The Linkage Editor constructs a phase from only the control sections specified. The namelist is in the following format: (cs name 1, cs name 2, ...) Entries within the parentheses are the names of the control sections that are used to constitute the phase.
PHASE	name, origin[,NOAUTO] [,SVA][,PBDY]	name Symbolic name of the phase. One to eight alphanumeric characters. origin Specifies the load address of the phase. Load address can be in one of the following formats: 1) symbol[(phase)] {+relocation}

LINKAGE EDITOR CONTROL STATEMENTS (. . . Cont'd)

Operation	Operands	Remarks
PHASE (Cont'd)		<p>2) * [+relocation] } *</p> <p>3) S [+relocation] } *</p> <p>* addresses relativ to begin of virtual partition.</p> <p>4) ROOT</p> <p>5) +displacement } **</p> <p>6) F +address } **</p> <p>** absolute addresses</p> <p>Note: A phase is eligible for relocation by the relocating loader if its origin is specified as a relative address (formats 1 - 4 above). However, if a phase is relative to another phase whose origin is specified as an absolute address (formats 5 or 6 above), none of the phases can be made relocatable during this linkage editor execution. Refer to ACTION statement for additional information about the relocating loader.</p> <p>NOAUTO Indicates that the automatic library lookup (AUTOLINK) feature is suppressed for both the private- and system relocatable libraries.</p> <p>SVA Indicates that the phase is SVA-eligible.</p> <p>PBDY Indicates that the phase is to be link-edited on a page boundary.</p>

LIBRARIAN

Maintenance Functions

Function	Unit	Element	Control Statements
BKEND	Source Statem. Library	Book	// EXEC MAINT BKEND [sublib.bookname], [seq-chck],[count], [CMPRSD]
Catalog	Core Image Library	Phase	// OPTION CATAL (Linkage Editor control statements and if in card form, the phase to be cataloged) /* // EXEC LNKEDT
	Relocatable Library	Module	// EXEC MAINT CATALR modulename [,v,m] (module to be cataloged)
	Source Statem. Library	Book	// EXEC MAINT CATALS sublib.bookname [,v,m [,c]] (book to be cataloged)
	Procedure Library	Procedure	// EXEC MAINT CATALP procedurename [,VM=v,m] [,EOP=yy] [DATA= $\begin{matrix} \text{NO} \\ \text{YES} \end{matrix}$] (procedure to be cataloged) /*(or delimiter as specified in EOP parameter
Condense	Core Image Library	Library	// EXEC MAINT CONDS CL
	Relocatable Library	Library	// JOB jobname // EXEC MAINT CONDS RL
	Source Statem. Library	Library	// EXEC MAINT CONDS SL
	Procedure Library	Library	// EXEC MAINT CONDS PL
Delete	Core Image Library	Phase	// EXEC MAINT DELETC phase 1 [,phase 2,]
		Program	// EXEC MAINT DELETC prog1.ALL[,prog2.ALL,]
	Relocatable Library	Module	// EXEC MAINT DELETR module 1[,module 2,]
		Program	// EXEC MAINT DELETR prog1.ALL[,prog2.ALL,]
		Library	// EXEC MAINT DELETR ALL
	Source Statem. Library	Book	// EXEC MAINT DELETS sublib.book1[,sublib.book2, . .]
		Sub Library	// EXEC MAINT DELETS sublib.ALL
		Library	// EXEC MAINT DELETS ALL
Procedure Library	Procedure	// EXEC MAINT DELETP procedurename[,procedure-name2,]	
	Library	// EXEC MAINT DELETP ALL	
Rename	Core Image Library	Phase	// EXEC MAINT RENAMC oldname,newname[,oldname, newname,]
	Relocatable Library	Module	// EXEC MAINT RENAMR oldname,newname[,oldname, newname,]

LIBRARIAN (. . . Cont'd)

Function	Unit	Element	Control Statements
	Source Statem. Library	Book	// EXEC MAINT RENAMS sublib.oldname,sublib.newname [,sublib.oldname,sublib.newname,]
	Procedure Library	Procedure	// EXEC MAINT RENAMP oldname,newname[,oldname, newname,]
Update	Source Statem. Library	Book	// EXEC MAINT -UPDATE sublib.bookname[,s.book1]: [v.m],[nn]) ADD,) DEL, or) REP statements as required with source statements to be added) END [v.m[C]]
Set Parameter for Automatic Condense	Libraries	Any or All	// EXEC MAINT CONDL lib=nnnnn[,lib=nnnnn[,lib=nnnnn]] Notes: Values to be substituted for lib: CL – Core image library RL – Relocatable library SL – Source statement library PL – Procedure library Values to be substituted for nnnnn: for CKD devices one to five decimal digits with a maximum value of 65536 for FBA devices, one to nine digits.
Reallocation	System	Library	// DLBL IJSYSRS, 'DOS SYSTEM RESIDENCE FILE' date, code // EXTENT SYSRES, balance of extent information // EXEC MAINT ALLOC CL=cylin(tracks),RL=cylin(tracks), SL=cylin(tracks),PL=cylin(tracks) Notes: CL – Core image library RL – Relocatable library SL – Source statement library PL – Procedure library For FBA devices, CYLIN and TRACKS are to be substituted by blocks.

Note: //JOB, /* and /& must be included where needed.

Service Functions

Display Unit	Element	Control Statements
Core Image Library	Phase	// EXEC CSERV DSPLY phase1[,phase2,]
	Program	// EXEC CSERV DSPLY prog1.ALL[,prog2.ALL,]
	Library	// EXEC CSERV DSPLY ALL
	Directory	// EXEC DSERV DSPLY CD or DSPLYS CD
	Phase(s) with Version and Modification Level	<u>In the standard position:</u> // EXEC DSERV DSPLY[S] CD(phasename) or CD(phasename) <u>In the nonstandard position or higher than DSERV in use:</u> // EXEC DSERV DSPLY[S] CD(phasename,nn) or CD(phasename,nn)
Relocatable Library	Module	// EXEC RSERV DSPLY module1[,module2,]
	Program	// EXEC RSERV DSPLY prog1.ALL[,prog2.ALL,]
	Library	// EXEC RSERV DSPLY ALL
	Directory	// EXEC DSERV DSPLY RD or DSPLYS RD

LIBRARIAN (. . . Cont'd)

Display Unit	Element	Control Statements
Source Statem. Library	Book	// EXEC SSERV DSPLY sublib.book1[,sublib.book2, . . .][,HEX]
	Sublibrary	// EXEC SSERV DSPLY sublib1.ALL[,sublib2.ALL, . . .][,HEX]
	Library	// EXEC SSERV DSPLY ALL[,HEX]
	Directory	// EXEC DSERV DSPLY SD or DSPLYS SD
	Macro-Sublibrary	// EXEC ESERV GENEND DSPLY sublib.bookname[,sublib.bookname, . . .]
Procedure Library	Procedure	// EXEC PSERV DSPLY procedurename1[,procedurename2, . . .]
	Library	// EXEC PSERV DSPLY ALL
	Directory	// EXEC DSERV DSPLY PD or DSPLYS PD
Transient Directory	Directory	// EXEC DSERV DSPLY TD or DSPLYS TD
System Directory	Directory	// EXEC DSERV DSPLY SDL or DSPLYS SDL
Directories	All	// EXEC DSERV DSPLY ALL or DSPLYS ALL
Punch Unit	Element	Control Statements
Core Image Library	Phase	// EXEC CSERV PUNCH phase1[,phase2, . . .]
	Program	// EXEC CSERV PUNCH prog1.ALL[,prog2.ALL, . . .]
	Library	// EXEC CSERV PUNCH ALL
Relocatable	Module	// EXEC RSERV PUNCH module1[,module2, . . .]
	Program	// EXEC RSERV PUNCH prog1.ALL[,prog2.ALL, . . .]
	Library	// EXEC RSERV PUNCH ALL
Source Statem. Library	Book	// EXEC SSERV PUNCH sublib.book1[,sublib.book2, . . .][,CMPRSD]
	Sublibrary	// EXEC SSERV PUNCH sublib1.ALL[,sublib2.ALL, . . .][,CMPRSD]
	Library	// EXEC SSERV PUNCH ALL[,CMPRSD]
	Macro Sublibrary	// EXEC ESERV GENEND PUNCH sublib.bookname[,sublib.bookname, . . .]
Procedure Library	Procedure	// EXEC PSERV PUNCH procedurename1[,procedurename2, . . .]
	Library	// EXEC PSERV PUNCH ALL
Display and Punch Unit	Element	Control Statements
Core Image Library	Phase	// EXEC CSERV DSPCH phase1[,phase2, . . .]
	Program	// EXEC CSERV DSPCH prog1.ALL[,prog2.ALL, . . .]
	Library	// EXEC CSERV DSPCH ALL

LIBRARIAN (. . . Cont'd)

Display and Punch Unit	Element	Control Statements
Relocatable Library	Module	// EXEC RSERV DSPCH module1[,module2,]
	Program	// EXEC RSERV DSPCH prog1.ALL[,prog2.ALL,]
	Library	// EXEC RSERV DSPCH ALL
Source Statem. Library	Book	// EXEC SSERV DSPCH sublib.book1[,CMPRSD1,HEX1,COMPHEX]
	Sublibrary	// EXEC SSERV DSPCH sublib1.ALL[,sublib2.ALL,] [,CMPRSD1,HEX1,COMPHEX]
	Library	// EXEC SSERV DSPCH ALL[,CMPRSD1,HEX1,COMPHEX]
	Macro Sublibrary	// EXEC ESERV GENEND DSPCH sublib.bookname[,sublib.bookname,]
Procedure Library	Procedure	// EXEC PSERV DSPCH procedurename1[,procedurename2,]
	Library	// EXEC PSERV DSPCH ALL

Note: //JOB, /* and /& must be included where needed.

Copy Functions

Copy Unit	Element	Control Statements
Core Image Library	Phase	// ASSGN SYS002,cuu // DLBL IJSYSRS,'DOS SYSTEM RESIDENCE FILE', date, code // EXTENT SYS002, balance of extent information // EXEC CORGZ ALLOC CL=cylin(tracks),RL=cylin(tracks) } For FBA: SL=cylin(tracks),PL=cylin(tracks) } =blocks(blocks) * ALLOC STATEMENT MUST ALWAYS BE PRESENT COPYC phase1[,phase2,]
		Program
	Library	// ASSGN SYS002,cuu // DLBL IJSYSRS,'DOS SYSTEM RESIDENCE FILE', date, code // EXTENT SYS002, balance of extent information // EXEC CORGZ ALLOC CL=cylin(tracks),RL=cylin(tracks) } For FBA: SL=cylin(tracks),PL=cylin(tracks) } =blocks(blocks) * ALLOC STATEMENT MUST ALWAYS BE PRESENT COPYC ALL
	Library	// ASSGN SYS002,cuu // DLBL IJSYSRS,'DOS SYSTEM RESIDENCE FILE', date, code // EXTENT SYS002, balance of extent information // EXEC CORGZ ALLOC CL=cylin(tracks),RL=cylin(tracks) } For FBA: SL=cylin(tracks),PL=cylin(tracks) } =blocks(blocks) * ALLOC STATEMENT MUST ALWAYS BE PRESENT COPYC NEW

LIBRARIAN (. . . . Cont'd)

Copy Unit	Element	Control Statements
Relocatable Library	Module	// ASSGN SYS002,cuu // DLBL IJSYSRS,'DOS SYSTEM RESIDENCE FILE', date, code // EXTENT SYS002, balance of extent information // EXEC CORGZ ALLOC CL=cylin(tracks),RL=cylin(tracks), } For FBA: SL=cylin(tracks),PL=cylin(tracks) } =blocks(blocks) * ALLOC STATEMENT MUST ALWAYS BE PRESENT COPYR module1[,module2, . . .]
	Program	// ASSGN SYS002,cuu // DLBL IJSYSRS,'DOS SYSTEM RESIDENCE FILE', date, code // EXTENT SYS002, balance of extent information // EXEC CORGZ ALLOC CL=cylin(tracks),RL=cylin(tracks), } For FBA: SL=cylin(tracks),PL=cylin(tracks) } =blocks(blocks) * ALLOC STATEMENT MUST ALWAYS BE PRESENT COPYR prog1.ALL[,prog2.ALL, . . .]
	Library	// ASSGN SYS002,cuu // DLBL IJSYSRS,'DOS SYSTEM RESIDENCE FILE', date, code // EXTENT SYS002, balance of extent information // EXEC CORGZ ALLOC CL=cylin(tracks),RL=cylin(tracks), } For FBA: SL=cylin(tracks),PL=cylin(tracks) } =blocks(blocks) * ALLOC STATEMENT MUST ALWAYS BE PRESENT COPYR ALL
	Library	// ASSGN SYS002,cuu // DLBL IJSYSRS,'DOS SYSTEM RESIDENCE FILE', date, code // EXTENT SYS002, balance of extent information // EXEC CORGZ ALLOC CL=cylin(tracks),RL=cylin(tracks), } For FBA: SL=cylin(tracks),PL=cylin(tracks) } =blocks(blocks) * ALLOC STATEMENT MUST ALWAYS BE PRESENT COPYR NEW
Source Statem. Library	Book	// ASSGN SYS002,cuu // DLBL IJSYSRS,'DOS SYSTEM RESIDENCE FILE', date, code // EXTENT SYS002, balance of extent information // EXEC CORGZ ALLOC CL=cylin(tracks),RL=cylin(tracks), } For FBA: SL=cylin(tracks),PL=cylin(tracks) } =blocks(blocks) * ALLOC STATEMENT MUST ALWAYS BE PRESENT COPYS sublib.book1[,sublib.book2, . . .]
	Sublibrary	// ASSGN SYS002,cuu // DLBL IJSYSRS,'DOS SYSTEM RESIDENCE FILE', date, code // EXTENT SYS002, balance of extent information // EXEC CORGZ ALLOC CL=cylin(tracks),RL=cylin(tracks), } For FBA: SL=cylin(tracks),PL=cylin(tracks) } =blocks(blocks) * ALLOC STATEMENT MUST ALWAYS BE PRESENT COPYS sublib1.ALL[,sublib2.ALL, . . .]
	Library	// ASSGN SYS002,cuu // DLBL IJSYSRS,'DOS SYSTEM RESIDENCE FILE', date, code // EXTENT SYS002, balance of extent information // EXEC CORGZ ALLOC CL=cylin(tracks),RL=cylin(tracks), } For FBA: SL=cylin(tracks),PL=cylin(tracks) } =blocks(blocks) * ALLOC STATEMENT MUST ALWAYS BE PRESENT COPYS ALL
	Library	// ASSGN SYS002,cuu // DLBL IJSYSRS,'DOS SYSTEM RESIDENCE FILE', date, code // EXTENT SYS002, balance of extent information

LIBRARIAN (. . . Cont'd)

Copy Unit	Element	Control Statements
Source System Library	Library (Cont'd)	// EXEC CORGZ ALLOC CL=cylin(tracks),RL=cylin(tracks), } For FBA: SL=cylin(tracks),PL=cylin(tracks) } =blocks(blocks) * ALLOC STATEMENT MUST ALWAYS BE PRESENT COPY NEW
Procedure Library	Procedure	// ASSGN SYS002,cuu // DLBL IJSYSRS,'DOS SYSTEM RESIDENCE FILE', date, code // EXTENT SYS002, balance of extent information // EXEC CORGZ ALLOC CL=cylin(tracks),RL=cylin(tracks), } For FBA: SL=cylin(tracks),PL=cylin(tracks) } =blocks(blocks) * ALLOC STATEMENT MUST ALWAYS BE PRESENT COPY procedurename1[,procedurename2, . . .]
	Library	// ASSGN SYS002,cuu // DLBL IJSYSRS,'DOS SYSTEM RESIDENCE FILE', date, code // EXTENT SYS002, balance of extent information // EXEC CORGZ ALLOC CL=cylin(tracks),RL=cylin(tracks), } For FBA: SL=cylin(tracks),PL=cylin(tracks) } =blocks(blocks) * ALLOC STATEMENT MUST ALWAYS BE PRESENT COPY ALL
	Library	// ASSGN SYS002,cuu // DLBL IJSYSRS,'DOS SYSTEM RESIDENCE FILE', date, code // EXTENT SYS002, balance of extent information // EXEC CORGZ ALLOC CL=cylin(tracks),RL=cylin(tracks), } For FBA: SL=cylin(tracks),PL=cylin(tracks) } =blocks(blocks) * ALLOC STATEMENT MUST ALWAYS BE PRESENT COPY NEW
Libraries	All	// ASSGN SYS002,cuu // DLBL IJSYSRS,'DOS SYSTEM RESIDENCE FILE', date, code // EXTENT SYS002, balance of extent information // EXEC CORGZ ALLOC CL=cylin(tracks),RL=cylin(tracks), } For FBA: SL=cylin(tracks),PL=cylin(tracks) } =blocks(blocks) * ALLOC STATEMENT MUST ALWAYS BE PRESENT COPY ALL
Definition of a Private Library (See note 2)	Core Image	// ASSGN SYS003,cuu // DLBL IJSYSPC,'user identification of private library', date, code // EXTENT SYS003, balance of extent information // EXEC CORGZ NEWVOL CL=cylin(tracks) For FBA: =blocks or // DLBL IJSYSPC,'. . . . // EXTENT SYS003, // LIBDEF CL, NEW=IJSYSPC // EXEC CORGZ NEWVOL CL=cyl(tracks) blocks
	Relocatable	// ASSGN SYSRLB,cuu // DLBL IJSYSRL,'user identification of private library', date, code // EXTENT SYSRLB, balance of extent information // EXEC CORGZ NEWVOL RL=cylin(tracks) For FBA: =blocks or // DLBL IJSYSRL,'. . . . // EXTENT SYSRLB, // LIBDEF RL, NEW=IJSYSRL // EXEC CORGZ NEWVOL RL=cyl(tracks) blocks

LIBRARIAN (. . . Cont'd)

Copy Unit	Element	Control Statement
Definition of a Private Library (See note 2) (Cont'd)	Source Statement	//ASSGN SYSSLB,cuu //DLBL IJSYSSL,'user identification of private library', date, code //EXTENT SYSSLB, balance of extent information //EXEC CORGZ NEWVOL SL=cylin(tracks) For FBA: =blocks or //DLBL IJSYSSL,'. . . . //EXTENT SYSSLB, //LIBDEF SL, NEW=IJSYSSL //EXEC CORGZ NEWVOL SL=cyl(tracks) blocks
	Procedure	//DLBL xxx xxx //EXTENT yyy yyy //LIBDEF PL, NEW=xxx xxx //EXEC CORGZ NEWVOL PL=cyl(tracks) blocks
Definition and Creation of a Private Library (See note 2)	Core Image	//ASSGN SYS003,cuu //DLBL IJSYSPC,'user identification of private library', date, code //EXTENT SYS003, balance of extent information //EXEC CORGZ NEWVOL CL=cylin(tracks) (For FBA: =blocks(blocks)) COPYC operands or //DLBL IJSYSPC,'. . . . //EXTENT SYS003, //LIBDEF CL, NEW=IJSYSPC //EXEC CORGZ NEWVOL CL=cyl(tracks) blocks COPYC operands
	Relocatable	//ASSGN SYSRLB,cuu //DLBL IJSYSRL,'user identification of private library', date, code //EXTENT SYSRLB, balance of extent information //EXEC CORGZ NEWVOL RL=cylin(tracks) For FBA: =blocks COPYR operands or //DLBL IJSYSRL,'. . . . //EXTENT SYSRLB, //LIBDEF RL, NEW=IJSYSRL //EXEC CORGZ NEWVOL RL=cyl(tracks) blocks COPYR operands
	Source Statement	//ASSGN SYSSLB,cuu //DLBL IJSYSSL,'user identification of private library', date, code //EXTENT SYSSLB, balance of extent information //EXEC CORGZ NEWVOL SL=cylin(tracks) For FBA: =blocks COPYS operands or //DLBL IJSYSSL,'. . . . //EXTENT SYSSLB, //LIBDEF SL, NEW=IJSYSSL //EXEC CORGZ NEWVOL SL=cyl(tracks) blocks COPYS operands
	Procedure	//DLBL xxx xxx //EXTENT yyy yyy //LIBDEF PL, NEW= xxx xxx //EXEC CORGZ NEWVOL PL=cyl(tracks) blocks COPYP operands

LIBRARIAN (. . .Cont'd)

Copy Unit	Element	Control Statement
Merge System Residence to New System Residence (See note 3)		// ASSGN (statement as required) // DLBL IJSYSRS,'NEW SYSTEM RESIDENCE', date, code // EXTENT SYS002, balance of extent information // EXEC CORGZ MERGE RES,NRS COPY statements (COPYC,COPYR,COPYS,COPYP,COPYI) as required
Merge New System Residence to System Residence (See note 3)		// ASSGN (statements as required) // DLBL IJSYSRS,'NEW SYSTEM RESIDENCE', date, code // EXTENT SYS002, balance of extent information // EXEC CORGZ MERGE NRS,RES COPY statements (COPYI,COPYC,COPYR,COPYS,COPYP, COPY) as required
Merge System Residence to Private Libraries (See note 3)		// ASSGN (statements as required) // DLBL IJSYSRL,'PRIVATE RELOCATABLE LIBRARY', date, code // EXTENT SYSRLB, balance of extent information // DLBL IJSYSSL,'PRIVATE SOURCE STATEMENT LIBRARY', date, code // EXTENT SYSSLB, balance of extent information // DLBL IJSYSCL,'PRIVATE CORE IMAGE LIBRARY', date, code // EXTENT SYSCLB, balance of extent information ASSGN SYSCLB,uuu // EXEC CORGZ MERGE RES,PRV COPY statements (COPYI,COPYR,COPYS,COPYC) as required
Merge New System Residence to Private Libraries (See note 3)		// ASSGN (statements as required) // DLBL IJSYSRS,'NEW SYSTEM RESIDENCE', date, code // EXTENT SYS002, balance of extent information // DLBL IJSYSRL,'PRIVATE RELOCATABLE LIBRARY', date, code // EXTENT SYSRLB, balance of extent information // DLBL IJSYSSL,'PRIVATE SOURCE STATEMENT LIBRARY', date, code // EXTENT SYSSLB, balance of extent information // DLBL IJSYSCL,'PRIVATE CORE IMAGE LIBRARY', date, code // EXTENT SYSCLB, balance of extent information ASSGN SYSCLB,uuu // EXEC CORGZ MERGE NRS,PRV COPY statements (COPYR,COPYS,COPYC) as required

LIBRARIAN (. . . Cont'd)

Copy Unit	Element	Control Statements
Merge Private Libraries to System Residence (see Note 3)		//ASSGN (statements as required) //DLBL IJSYSR,'PRIVATE RELOCATABLE LIBRARY', date, code //EXTENT SYS001, balance of extent information //DLBL IJSYSPS,'PRIVATE SOURCE STATEMENT LIBRARY', date, code //EXTENT SYS000, balance of extent information //DLBL IJSYSPC,'PRIVATE CORE IMAGE LIBRARY', date, code //EXTENT SYS003, balance of extent information //EXEC CORGZ MERGE PRV,RES COPY statements (COPYR,COPYS,COPYC) as required
Merge Private Libraries to New System Residence (see Note 3)		//ASSGN (statements as required) //DLBL IJSYSRS,'NEW SYSTEM RESIDENCE', date, code //EXTENT SYS002, balance of extent information //DLBL IJSYSR,'PRIVATE RELOCATABLE LIBRARY', date, code //EXTENT SYS001, balance of extent information //DLBL IJSYSPS,'PRIVATE SOURCE STATEMENT LIBRARY', date, code //EXTENT SYS000, balance of extent information //DLBL IJSYSPC,'PRIVATE CORE IMAGE LIBRARY', date, code //EXTENT SYS003, balance of extent information //EXEC CORGZ MERGE PRV,NRS COPY statements (COPYR,COPYS,COPYC) as required
Merge Private Libraries to Private Libraries (see Note 3)		//ASSGN (statements as required) //DLBL IJSYSRL,'NEW PRIVATE RELOCATABLE LIBRARY', date, code //EXTENT SYSRLB, balance of extent information //DLBL IJSYSR,'EXISTING PRIVATE RELOCATABLE LIBRARY', date, code //EXTENT SYS001, balance of extent information //DLBL IJSYSSL,'NEW PRIVATE SOURCE STATEMENT LIBRARY', date, code //EXTENT SYSSLB, balance of extent information //DLBL IJSYSPS,'EXISTING PRIVATE SOURCE STATEMENT LIBRARY', date, code //EXTENT SYS000, balance of extent information //DLBL IJSYSCL,'NEW PRIVATE CORE IMAGE LIBRARY', date, code //EXTENT SYSCLB, balance of extent information ASSGN SYSCLB,cuu //DLBL IJSYSPC,'EXISTING PRIVATE CORE IMAGE LIBRARY', date, code //EXTENT SYS003, balance of extent information //EXEC CORGZ MERGE PRV,PRV COPY statements (COPYR,COPYS,COPYC) as required To define the private library in the same jobstep, precede MERGE with NEWVOL statement (except for COPYC statements).

Notes: 1) //JOB, /* and /& must be included where needed.

2) The private library can be updated with either a MAINT or CORGZ MERGE function.

3) Only one type of library definitions can be used:

Either LIBDEF definitions or standard assignments.

The NRS can only be assigned as IJSYSRS on SYS002.

Direction of Transfer for Merge Operations

Logical Unit		IJSYSRS	IJSYSRL	IJSYSPR	IJSYSSL	IJSYSPS	IJSYSCL	IJSYSPC		
File Name	SYSRES	SYS002	SYSRLB	SYS001	SYSSLB	SYS000	SYSCLB	SYS003	LIBDEF FROM	LIBDEF TO
MERGE RES,NRS	from	to								
MERGE NRS,RES	to	from								
MERGE RES,PRV	from		to		to		to			to
MERGE NRS,PRV		from	to		to		to			to
MERGE PRV,RES	to			from		from		from	from	
MERGE PRV,NRS		to		from		from		from	from	
MERGE PRV,PRV			to	from	to	from	to	from	from	to

ESERV

Function: De-editing and/or updating of edited macro's.
(Refer to: Guide to DOS/VS Assembler (GC33-4024))

Control Statement	Meaning
// EXEC ESERV	
GENEND	Causes generation of an assembler END statement, and a /* statement. GENEND, when present, must be the first statement after the // EXEC ESERV statement.
GENCATALS	Causes generation of the appropriate CATALS statement before each macro in the stream, and a /* statement after the last macro. GENCATALS, when present, must be the first statement after the // EXEC ESERV statement. Note: If neither GENEND nor GENCATALS is used, GENCATALS is assumed.
DSPLY sublibl.bookname1 [sublibl.bookname2,]	Produces a printout of the de-edited macro on the device assigned to SYSLST.
PUNCH sublibl.bookname1 [sublibl.bookname2,]	Produces a de-edited deck on the device assigned to SYSPCH.
DSPCH sublibl.bookname1 [sublibl.bookname2,]	Produces a deck and printout of the de-edited macro on the devices assigned to SYSPCH and SYSLST respectively.
) COL start col,n	Specifies the columns containing the sequence numbers in the statement of a macro definition. startcol A decimal number within the range 73-80, which identifies the start column of the sequence number. n A decimal number within the range 1-8, specifying the number of columns used by the sequence number. COL, when present must be the first statement following DSPLY, PUNCH or DSPCH statement. If the COL statement is omitted startcol receives a default value of 73 and n a default value of 6.
) VER seqno+rel], len	Specifies the source statement of a macro definition which contents are to be verified. seqno+rel Identifies the source statement which is to be compared with the statement following the VER statement. seqno: The sequence number of a source statement. rel: A decimal number of 1-4 digits in length. If omitted, 0 is assumed. len A decimal number within the range 1-80. If omitted, 72 is assumed. Only the first l characters are used in the comparison.
) ADD seqno+rel]	Add statements to a source macro definition. seqno+rel Identifies the source statement after which the new statements following the ADD statement are to be inserted. (seqno: See VER statement) (rel: See VER statement)
) DEL first seqno+rel]],[last seqno+rel]]	Delete statements from a macro source definition. seqno+rel,seqno+rel Identifies the first and the last source statement of the section to be deleted. If the second operand is omitted, only the source statement identified by the first operand is deleted. (seqno: See VER statement) (rel: See VER statement)

ESERV (. . . Cont'd)

Control Statement	Meaning
) REP first seqno[+rel][,last seqno[+rel]]	Replace statements in a source macro definition. seqno+rel,seqno+rel Identifies the first and the last source statement of the section which is to be replaced by the statements following the REP statement. If the second operand is omitted, only the source statement identified by the first operand is replaced. (seqno: See VER statement) (rel: See VER statement)
) RST seqno[+rel]	Specifies a new sequence number serial starts. seqno+rel Identifies the source statement after which the new serial starts. (seqno: See VER statement) (rel: See VER statement)
) END	Indicates the end of an update to a macro definition. Required statement for all updating.

Sample coding for de-editing without updating a macro definition

```
// JOB NOUPDATE
// EXEC ESERV
PUNCH E.MAC1,E.MAC2
/*
/ &
```

Sample coding for de-editing and updating a macro definition

```
// JOB UPDATE
// EXEC ESERV
GENEND
DSPCH E.MAC1
) COL 77,3
) VER 72 + 1,5
.PP9
) ADD 72 + 1
  AIF (&PCH NE 1400)D4
) DEL 102, 103
) REP 245
JOYCE CLC 0(4,REG6),BLANKS
) END
/*
// PAUSE CHECK LIST, MOVE DECK TO READER
// OPTION EDECK, NODECK
// EXEC ASSEMBLY
```

deck produced by ESERV

```
// PAUSE MOVE SYSPCH DECK TO READER
// EXEC MAINT
```

deck produced by assembler

```
/*
/ &
```

LSERV

The label information area is part of the SYSRES file and follows the last library in SYSRES. A display of all labels can be obtained by executing LSERV. LSERV may be executed in any partition, with a minimum of 8192 bytes of the real or virtual address areas.

Executing LSERV

From the console:

```
//EXEC LSERV
```

From the reader:

```
//JOB xxx
```

```
//EXEC LSERV
```

```
/*
```

```
/&
```

The output of LSERV shows the contents of the label area on SYSRES and is to be printed on SYSLST.

When a How to use LSERV:

1. Operator action given in VSE/AF2 Messages indicates when LSERV must be executed.
2. LSERV can be used for error analysis. LSERV displays the TLBL, DLBL and EXTENT information.

Summary of information provided

The printout of LSERV will show you the following details:

- Whether the correct DLBL/EXTENT information is still on the label area.
- The permanent files.
- The temporary files.
- Extent type.
- File type.

For more information, refer to VSE/AF2 Serviceability Aids and Debugging Procedures (SC33-6099).

LVTOC

A display of a DASD volume VTOC can be obtained the LVTOC program.

Executing LVTOC

From the console:

```
Request Key
```

```
Enter:
```

```
Pause part.id., EOJ
```

```
Wait for EOJ
```

```
Enter:
```

```
// Assgn SYS004, cuu (DISK)
```

```
// Assgn SYS005, cuu (PRT)
```

```
//EXEC LVTOC
```

From the reader:

```
//JOB xxx
```

```
// Assgn SYS004, cuu (DISK)
```

```
// Assgn SYS005, cuu (PRT)
```

```
//EXEC LVTOC
```

```
/&
```

- LVTOC lists:
- The file labels in alphabetic sequence.
 - The free space on the volume.
 - The start and end addresses and sizes of the unused space.

SUPERVISOR MACROS

Supervisor Macro Instruction

Operation	Operand	Explanation
SUPVR	$ID = \left\{ \frac{1}{c} \right\}$	Specifies whether the Supervisor Select option is to be used. By specifying an alphameric character (A-Z, 1-9), a unique name will be assigned to the supervisor being generated. For example, ID=A generates a supervisor named \$\$\$ASUPA. If this parameter is omitted the supervisor will be named \$\$\$SUP1.
	$MICR = \left\{ \frac{NO}{1419} \right\}$ $\left\{ \frac{1419D}{1419D} \right\}$	Indicates support for magnetic ink or optical character reader/sorters. The specification 1419 indicates support for 1419s with Single Address Adapter, 1255s, 1259s, or 1270s. 1419D specification gives support for 1419s with Dual Address adapter, or 1275s. Burst mode and MICR devices cannot run concurrently on the same byte multiplexor channel.
	$MODE = \left\{ \frac{370}{E} \right\}$	Specifies whether 370 or ECPS:VSE mode is supported.
	$NPARTS = \left\{ \frac{5}{n} \right\}$	Specifies the number of partitions to be supported. The minimum is 2. The maximum value for n is 12. The default value is 5.
	$NTASKS = \left\{ \frac{32}{n} \right\}$	Specifies the number of user subtasks to be supported. Minimum is 8; maximum is 208.
	$TP = \{BTAM VTAM\}$	Specify TP = VTAM if your installation uses: ACF/VTAM, or VSE/POWER and VSE/POWER supported RJE, SNA.
	$VM = \{NO YES\}$	Specify VM = YES: for VM/370 Linkage function; for FBA DASDs in 370 mode.

Specify Optional Support in the Supervisor

Operation	Operand	Explanation
FOPT	$ASYNOC = \{NO YES\}$	Specify YES to obtain support for Asynchronous Operator Communication; this allows to defer the operator's reply to system messages to some later time and to reply to messages out of sequence of their issuance.
	$CBF = \left\{ \frac{NO}{n} \right\}$	Specifies whether output to a console printer assigned as SYSLOG is to be buffered. n specifies the number of buffers to be generated, value from 1 to 50.
	$DASDFP = \left\{ \frac{NO}{YES} \right\}$	Specifies support for protection of DASD files.
	$DASDSHR = \{NO YES\}$	Specify YES if DASD sharing across system domains is desired. It provides for a cross-system locking mechanism to ensure data integrity when DASDs are accessible from two or more systems via the channel and/or string switching mechanism. DASD sharing across systems is not supported for IBM 2311 and 2314/2319.
	$DOC = \left\{ \frac{3277}{125D} \right\}$ $\left\{ \frac{125D}{NO} \right\}$	Only valid in 370 mode. Specifies whether support is required for Display Operator Console (DOC). The necessary supervisor routines are generated to allow to assign SYSLOG either to a 125D or a 3277. If MODEL=115 or 125, 125D will be used. 3277 will be the default.
	$ERRQ = \left\{ \frac{5}{n} \right\}$	Specify the number of entries for the error queue. n may be from 5 to 50.
	$FASTTR = \left\{ \frac{NO}{YES} \right\}$	Specifies whether fast CCW translation is to be supported.

SUPERVISOR MACROS (. . . Cont'd)

Specify Optional Support in the Supervisor (. . . Cont'd)

Operation	Operand	Explanation																																																																																																																																																																							
FOPT (Cont'd)	$JA = \left\{ \begin{array}{c} \text{NO} \\ \text{YES} \end{array} \right\}$ $JA = \{(n1,n2,n3, \dots, nm)\}$	<p>Specifies whether Job Accounting Interface and SIO Accounting is supported. YES or (n1,n2, . . . ,nm) if Job Accounting Interface is to be supported for all partitions specified in NPARTS of SUPVR. Specify JA = (n1,n2, . . . ,nm) if SIO accounting is to be supported in addition to Job Accounting Interface. For n specify the number of I/O devices for which SIOs are to be counted for a given partition. Maximum value for n is 255; n1 always relates to BG.</p> <table border="1" style="margin-left: auto; margin-right: auto;"> <thead> <tr> <th rowspan="2">No. of Partitions</th> <th colspan="12">Relationship</th> </tr> <tr> <th>n2</th> <th>n3</th> <th>n4</th> <th>n5</th> <th>n6</th> <th>n7</th> <th>n8</th> <th>n9</th> <th>n10</th> <th>n11</th> <th>n12</th> </tr> </thead> <tbody> <tr><td>2</td><td>F1</td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td></tr> <tr><td>3</td><td>F2</td><td>F1</td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td></tr> <tr><td>4</td><td>F3</td><td>F2</td><td>F1</td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td></tr> <tr><td>5</td><td>F4</td><td>F3</td><td>F2</td><td>F1</td><td></td><td></td><td></td><td></td><td></td><td></td><td></td><td></td></tr> <tr><td>6</td><td>F5</td><td>F4</td><td>F3</td><td>F2</td><td>F1</td><td></td><td></td><td></td><td></td><td></td><td></td><td></td></tr> <tr><td>7</td><td>F6</td><td>F5</td><td>F4</td><td>F3</td><td>F2</td><td>F1</td><td></td><td></td><td></td><td></td><td></td><td></td></tr> <tr><td>8</td><td>F7</td><td>F6</td><td>F5</td><td>F4</td><td>F3</td><td>F2</td><td>F1</td><td></td><td></td><td></td><td></td><td></td></tr> <tr><td>9</td><td>F8</td><td>F7</td><td>F6</td><td>F5</td><td>F4</td><td>F3</td><td>F2</td><td>F1</td><td></td><td></td><td></td><td></td></tr> <tr><td>10</td><td>F9</td><td>F8</td><td>F7</td><td>F6</td><td>F5</td><td>F4</td><td>F3</td><td>F2</td><td>F1</td><td></td><td></td><td></td></tr> <tr><td>11</td><td>FA</td><td>F9</td><td>F8</td><td>F7</td><td>F6</td><td>F5</td><td>F4</td><td>F3</td><td>F2</td><td>F1</td><td></td><td></td></tr> <tr><td>12</td><td>FB</td><td>FA</td><td>F9</td><td>F8</td><td>F7</td><td>F6</td><td>F5</td><td>F4</td><td>F3</td><td>F2</td><td>F1</td><td></td></tr> </tbody> </table>	No. of Partitions	Relationship												n2	n3	n4	n5	n6	n7	n8	n9	n10	n11	n12	2	F1												3	F2	F1											4	F3	F2	F1										5	F4	F3	F2	F1									6	F5	F4	F3	F2	F1								7	F6	F5	F4	F3	F2	F1							8	F7	F6	F5	F4	F3	F2	F1						9	F8	F7	F6	F5	F4	F3	F2	F1					10	F9	F8	F7	F6	F5	F4	F3	F2	F1				11	FA	F9	F8	F7	F6	F5	F4	F3	F2	F1			12	FB	FA	F9	F8	F7	F6	F5	F4	F3	F2	F1	
No. of Partitions	Relationship																																																																																																																																																																								
	n2	n3	n4	n5	n6	n7	n8	n9	n10	n11	n12																																																																																																																																																														
2	F1																																																																																																																																																																								
3	F2	F1																																																																																																																																																																							
4	F3	F2	F1																																																																																																																																																																						
5	F4	F3	F2	F1																																																																																																																																																																					
6	F5	F4	F3	F2	F1																																																																																																																																																																				
7	F6	F5	F4	F3	F2	F1																																																																																																																																																																			
8	F7	F6	F5	F4	F3	F2	F1																																																																																																																																																																		
9	F8	F7	F6	F5	F4	F3	F2	F1																																																																																																																																																																	
10	F9	F8	F7	F6	F5	F4	F3	F2	F1																																																																																																																																																																
11	FA	F9	F8	F7	F6	F5	F4	F3	F2	F1																																																																																																																																																															
12	FB	FA	F9	F8	F7	F6	F5	F4	F3	F2	F1																																																																																																																																																														
	$JALIOCS = \left\{ \begin{array}{c} \text{NO} \\ s, 1 \end{array} \right\}$	<p>Generates a user save area and an alternative label area for job accounting. s specifies the number of bytes for the save area for user-written job-accounting routines. The maximum acceptable value is 1024 and the default value is 16. 1 specifies the number of bytes for the alternative label area. The maximum value is 224 and the default value is 0.</p>																																																																																																																																																																							
	$LCONCAT = \left\{ \begin{array}{c} 5 \\ n \end{array} \right\}$	<p>Specifies whether library search function is to be supported. Specify the maximum number (n) of libraries that are allowed per library concatenation chain. Minimum for n is 1, maximum is 15.</p>																																																																																																																																																																							
	$MSECS = \left\{ \begin{array}{c} 1000 \\ n \end{array} \right\}$	<p>Specifies the size of the time interval. n may be any value from 100 to 10,000 (msec).</p>																																																																																																																																																																							
	$RPS = \left\{ \begin{array}{c} \text{NO} \\ \text{YES} \end{array} \right\}$	<p>Provides support for the Rotational Position Sensing (RPS) capabilities of DASD devices supporting the feature.</p>																																																																																																																																																																							
	$SEC = \left\{ \begin{array}{c} \text{NO} \\ n \end{array} \right\}$	<p>Specify n if use access control function of VSE/ICCF. n is the number of entries in the logging queue and is a value from 10 to 32,767. Note: A SUPVR with SEC specified can only be activated if VSE/ICCF is installed.</p>																																																																																																																																																																							
	$SLD = \left\{ \begin{array}{c} 15 \\ n \end{array} \right\}$	<p>Specifies the number of entries in the Second Level Directory. The minimum value for n is 5. This value is assumed in the case of an incorrect specification. A performance decrease will result if the number specified is less than the number of actually used directory tracks of the System Core Image Library. An upper limit for CKD is 18, for FBA it is 30, although the number is not restricted.</p>																																																																																																																																																																							
	$SYNCH = \left\{ \begin{array}{c} \text{NO} \\ \text{YES} \end{array} \right\}$	<p>Specifies whether the synchronous exit function is to be supported. SYNCH = YES should be specified if problem programs use the synchronous exit facility (SVC screening) to support multiple users in one partition.</p>																																																																																																																																																																							

SUPERVISOR MACROS (. . . Cont'd)

Specify Optional Support in the Supervisor (. . . Cont'd)

Operation	Operand	Explanation
FOPT (Cont'd)	$TRKHLD = \left\{ \begin{matrix} NO \\ n \end{matrix} \right\}$	Specifies whether the Track-Hold feature is to be supported for DASD in a supervisor that supports multiprogramming. n indicates the maximum no. of tracks/blocks to be held at any one time. Accepted values are from 1 to 255. A Track-Hold Table (THTAB) with n entries is generated in the supervisor. An invalid specification results in 10 entries being generated. The NPARTS parameter in the SUPVR macro must specify more than one partition if TRKHLD = n is specified.
	$TTIME = \left\{ \begin{matrix} NO \\ \text{partition ID} \end{matrix} \right\}$	Specifies whether the timer is to be supported and if so, the partition owning the task timer. Only one partition ID can be specified. The partition ID is BG or Fn (where n is one of the foreground partitions generated into the system). If the partition ID sequence does not correspond to the appropriate NPARTS specification, or if the value specified for NPARTS is invalid, an MNOTE is issued.
	$USERID = \{id\}$	Specifies whether a supervisor id is to be printed as part of the IPL COMPLETE message. id may be up to 16 bytes long. If you specify more than 16 bytes, the id will be truncated on the right. If you specify less than 16 bytes, the id will be padded with blanks on the right. The specified id is placed in a 16 byte area that immediately precedes the BG communication region. The field contains blanks if the parameter is not specified.
	$XECB = \left\{ \begin{matrix} YES \\ n \end{matrix} \right\}$	Specifies whether Cross Partition Event Control is to be supported. If YES is specified, four XECB's are generated per partition (as specified in NPARTS). n must be specified as a numeric value and indicates the number of XECB's for which an entry is to be generated in a supervisor internal table.

Define options and Configuration requirements to be included in Physical IOCS

Operation	Operand	Explanation																							
IOTAB	$BGPGR = \left\{ \begin{matrix} 30 \\ n \end{matrix} \right\}$	Specifies the number of programmer logical units (SYSnnn) for the BG partition. The minimum value for n is 10, and the maximum is 255. A partition LUB table is generated with a two-byte entry for each system logical unit and additional entries for the number of units specified by n.																							
	$BUFSIZE = \left\{ \begin{matrix} d \\ n \end{matrix} \right\}$	Specify the number of 72-byte copy blocks for VSE/AF run in 370 mode, or the number of 36-byte work blocks for VSE/AF run in ECPS:VSE mode. 370 mode: <table border="1" style="margin-left: 20px;"> <thead> <tr> <th colspan="3">BUFSIZE</th> </tr> <tr> <th>FASTTR=</th> <th>Default</th> <th>Minimum</th> </tr> </thead> <tbody> <tr> <td>NO</td> <td>60</td> <td>10</td> </tr> <tr> <td>YES</td> <td>$60+(n-2) \cdot 20$</td> <td>30</td> </tr> </tbody> </table> n=value specified for NPARTS in SUPVR ECPS:VSE mode: <table border="1" style="margin-left: 20px;"> <thead> <tr> <th colspan="3">BUFSIZE</th> </tr> <tr> <th>FASTTR=</th> <th>Default</th> <th>Minimum</th> </tr> </thead> <tbody> <tr> <td>NO</td> <td>60</td> <td>10</td> </tr> <tr> <td>YES</td> <td>$120+(n-2) \cdot 40$</td> <td>60</td> </tr> </tbody> </table> n=value specified for NPARTS in SUPVR	BUFSIZE			FASTTR=	Default	Minimum	NO	60	10	YES	$60+(n-2) \cdot 20$	30	BUFSIZE			FASTTR=	Default	Minimum	NO	60	10	YES	$120+(n-2) \cdot 40$
BUFSIZE																									
FASTTR=	Default	Minimum																							
NO	60	10																							
YES	$60+(n-2) \cdot 20$	30																							
BUFSIZE																									
FASTTR=	Default	Minimum																							
NO	60	10																							
YES	$120+(n-2) \cdot 40$	60																							

SUPERVISOR MACROS (. . . Cont'd)

Define options and Configuration requirements to be included in Physical IOCS (. . . Cont'd)

Operation	Operand	Explanation
IOTAB (Cont'd)	$\text{CHANQ} = \left\{ \frac{d}{n} \right\}$	Specifies the maximum number n of entries to be generated for the channel queue. Maximum value is 255. Default d is 24 plus value in CBF parameter. Minimum value for n is value in CBF plus 6 if NPARTS=2 2 + NPARTS if NPARTS > 2
	$\text{FnPGR} = \left\{ \frac{20}{n} \right\}$	Specifies for foreground partition n the number of programmer logical units. The minimum value for n is 5, and the maximum value is 255.
	$\text{IODEV} = \left\{ \frac{25}{n} \right\}$	Specifies the number of I/O devices attached to the system. The maximum specification allowed is 254, the minimum is 4. Each unit requiring an ADD entry must be included in n.
	$\text{JIB} = \left\{ \frac{d}{n} \right\}$	Specifies the number of Job Information Blocks (JIBs) for the system (the minimum is 5, the default d is 10, the maximum is 255). Requirements are: 1. One JIB for each temporary logical unit assignment. 2. One JIB for each alternate logical unit assignment.
	$\text{NRES} = \left\{ \frac{d}{n} \right\}$	n specifies the number of lock names to be held concurrently in order to protect shared resources against concurrent use by different tasks and/or systems. The maximum value for n is 512. The minimum and default value is 21 plus four times the value specified for NPARTS in SUPVR.

DEVICE TYPE CODES

Card Code	Actual IBM Device	Dev. Type x'nn'	Device Type
1050A	3210, 3215 Console Printer Keyboards 3286 in Printer Keyboard Mode	00	Printer Keyboards
2501	2501 Card Reader	10	Card Readers
2540R	2540 Card Reader	11	
3504	3504 Card Reader	12	
3505	3505 Card Reader	12	
2520B2	2520 B2 Card Punch	20	Card Punches
2520B3	2520 B3 Card Punch	20	
2540P	2540 Card Punch	21	
1442N2	1442 N2 Card Punch	22	
3525P	3525 Card Punch	23	
1442N1	1442 N1 Card Read Punch	30	Card Read Punches
2520B1	2520 B1 Card Read Punch	31	
2560	2560 MFCM	33	
2596	2596 Card Read Punch	30	
3525RP	3525 Card Punch with optional read feature	32	
5425	5424/25 MFCU	34	
1403	1403 Printer	40	Printers
1403U	1403 Printer with UCS	42	
1443	1443 Printer	41	
2245	2245 KANJI Printer (only in Real mode)	44	
3203	3203-1, 3203-2 Printer	4A	
PRT1 +	3211, 3203-4, 3203-5, 3262-2, 3262-12 and	43	
3211	3289-4 Printers		
3277	all attachable Printers to 3272 or 3274-1B Contr.	80	
(local 3270)	Unit mode command must be X'01'		
3277B	all attachable Printers to 3272 or 3274-1B Contr.	80	
(local 3270)	Unit attached in Burst Mode, mode command must be X'01'. Printers attached to 3274-1B mode command must be X'06'.		
3800	3800 Printer Subsystem	45	
3800B	3800 Printer Subsystem with Burster Trimmer Stackers (BTS)	45	
3800C	3800 Printer Subsystem with Additional Character Generation Storage (CGS)	45	
3800BC	3800 Printer Subsystem with BTS and CGS	45	
5203	5203 Printer	4C	
5203U	5203 Printer with UCS	4D	
2400T9	9-track 2400 Tape unit	50	Tapes
2400T7	7-track 2400 Tape unit	50	
3410T9	9-track 3410 Tape unit	53	
3410T7	7-track 3410 Tape unit	53	
3420T9	9-track 3420 Tape unit	52	
3420T7	7-track 3420 Tape unit	52	
8809	8809 Tape unit	5A	
FBA	3310/3370	90	DASD
2311	2311	60	
2314	2314; 2319	62	
3330	3330-1; 3330-2; 3333-1	63	
3330B	3330-11	65	
3340	3340; 3344 General	68	
3340R	3340; 3344 with RPS	68	
3340	3340 without RPS	69/6A	
3350	3350	67	
1419	1255; 1259; 1419 Magnetic Character Reader	72	
1419P	1419 Dual Address Adapter Primary Control Unit	73	
1419S	1419 Dual Address Adapter Secondary Control Unit	74	
1287	1287 Optical Reader	77	Optical Readers
1288	1288 Optical Reader	77	
1419	1270 Optical Reader/Sorter	72	
1419P	1275 Optical Reader/Sorter Primary Control Unit	73	
1419S	1275 Optical Reader/Sorter Secondary Control Unit	74	
3881	3881 Optical Mark Reader	11	
3886	3886 Optical Character Reader	7C	

DEVICE TYPE CODES (. . . Cont'd)

Card Code	Actual IBM Device	Dev.Type X'nn'	Device Type
3540 7443	3540 Diskette Input/Output Unit 7443 System Recording File	80 88	Diskette
2260 3277 3277B	2260 Display Station 3277; 3278 3277; 3278, attached in Burst Mode	C0 B0 B0	Display Stations
125D 125DP 3277	115/125 Display Operator Console 138/148 Console in 115/125 Emulation Mode same as 125D, but 5213 Console Printer attached 3277 Display Operator Console; 3284, 3286 or 3287 Console Printer, mode command must be X'02'. Display units attached to 3274-1D, mode command must be X'05'.	B2 B2 B0	Display Operator Console
2701 2702 2703 3704 3705 3791L	2701/2715 Adapter Unit; 135 ICA 2702 Transmission Control Unit 2703 Transmission Control Unit; 115/125/138 ICA 3704/05 Controller in Emulation mode 3704 Controller 3705 Controller; SDLC ICA on 4300 processor, mode must be X'10' 3791 Controller; 3274-1A Local Command Controller	D0 D1 D2 DC DC DE	Teleprocessing Lines
1017 1017TP 2671	1017 Paper Tape Reader with 2826 Control Unit Mod. 1 1017 Paper Tape Reader with 2826 Control Unit Mod. 2 2671 Paper Tape Reader	78 D5 70	Paper Tape Readers
1018 1018TP	1018 Paper Tape Punch with 2826 Control Unit Mod. 1 1018 Paper Tape Punch with 2826 Control Unit Mod. 2	79 D6	Paper Tape Punch
7770 7772	7770 Audio Response Unit 7772 Audio Response Unit	D3 D4	Audio Response Unit
UNSP UNSPB	Unsupported Device Unsupported Device	FF FF	Unsupported Device

FORMAT OF THE ESD CARD

Card
Columns

1	Multiple punch (12-2-9) identifies this as a loader card.
2-4	ESD - External Symbol Dictionary card.
11-12	Number of bytes of information contained in this card.
15-16	External symbol identification number (ESID) of the first SD, PC, CM or ER on this card. Relates the SD, PC, CM or ER to a particular control section.
17-72	Variable information. 8 positions - Name 1 position - Type code hex 00, 01, 02, 04, 05, or 0A to indicate SD, LD, ER, PC, CM, or WX respectively. 3 positions - Assembled origin 1 position - Blank 3 positions - Length, if an SD type, CM type, or a PC type. If an LD type, this field contains the external symbol identification number (ESID) of the SD containing the label.
73-80	May be used by the programmer for identification.

FORMAT OF THE TXT CARD

Card
Columns

1	Multiple punch (12-2-9). Identifies this as a loader card.
2-4	TXT - Text card.
6-8	Assembled origin (Address of first byte to be loaded from this card).
11-12	Number of bytes of text to be loaded.
15-16	External symbol identification number (ESID) of the control section (SD or PC) containing the text.
17-72	Up to 56 bytes of text — data or instructions to be loaded.
73-80	May be used for program identification.

FORMAT OF THE RLD CARD

Card

Columns

- 1 Multiple punch (12-2-9).
Identifies this as a loader card.
- 2-4 RLD – Relocation List Dictionary Card.
Number of bytes of information contained in this card.
- 11-12 Variable information (multiple items).
- 17-72
- a) Two positions - (relocation identifier) pointer to the ESID number of the ESD item on which the relocation factor of the contents of the address constant is dependent.
 - b) Two positions - (position identifier) pointer to the ESID number of the ESD item on which the position of the address constant is dependent.
 - c) One position - flag indicating type of constant, as follows:
- Bits
- 0-2 Ignored
 - 3 0 - a non branch type load constant
1 - a branch type load constant
 - 4-5 00 - load constant length = 1 byte
01 - load constant length = 2 bytes
10 - load constant length = 3 bytes
11 - load constant length = 4 bytes
 - 6 0 - relocation factor is to be added
1 - relocation factor is to be subtracted
 - 7 0 - Next load constant has different R and P identifiers;
therefore, both R and P must be present.
1 - Next load constant has the same R and P identifiers;
therefore they are both omitted.
- Five significant bits of this byte are expanded in the RSERV printout.
- d) Three positions – assembled origin of load constant.
- 73-80 May be used for program identification.

FORMAT OF THE END CARD

Card

Columns

- 1 Multiple punch (12-2-9).
Identifies this as a loader card.
- 2-4 END
- 6-8 Assembled origin of the label supplied to the Assembler in the END card (optional).
- 15-16 ESID number of the control section to which this END card refers (only if 6-8 present).
- 17-22 Symbolic label supplied to the Assembler if this label was not defined within the assembly.
- 29-32 Control section length (if not specified in the last SD or PC).
- 73-80 Not used.


FORMAT OF THE REP (User Replace) CARD

Card

Columns

- 1 Multiple punch (12-2-9).
Identifies this as a loader card.
- 2-4 REP – Replace text card.
- 5-6 Blank.
- 7-12 Assembled address of the first byte to be replaced (hexadecimal).
Must be right justified with leading zero's if needed to fill the field.
- 13 Blank
- 14-16 External symbol identification number (ESID) of the control section (SD) containing the text (hexadecimal). Must be right justified with leading zero's if needed to fill the field.
- 17-70 From 1-11 4 digit hexadecimal fields separated by comma's, each replacing two bytes. A blank indicates the end of information in this card.
- 71-72 Blank
- 73-80 May be used for program identification.

CHAPTER III
VSE/AF2 IOCS (GENERAL/SAM/DAM/ISAM)



III-101

FIELD	NAME AND LENGTH	DESCRIPTION	FIELD	NAME AND LENGTH	DESCRIPTION
1	LABEL IDENTIFIER 3 bytes	Must contain VOL to indicate that this is a Volume Label.	5	RESERVED 10 bytes	Reserved
2	VOLUME LABEL NO. 1 byte	Indicates the relative position (1-8) of a volume label within a group of volume labels.	6	RESERVED 10 bytes	Reserved
3	VOLUME SERIAL NO. 6 bytes	A unique identification code which is assigned to a volume when it enters an installation. This code may also appear on the external surface of the volume for visual identification. It is normally a numeric field 000001 to 999999, however any or all of the 6 bytes may be alphameric.	7	RESERVED 10 bytes	Reserved
4	VOLUME SECURITY 1 byte (OS/VS only)	Indicates security status of the volume: 0 = No security protection 1 = Security protection.	8	OWNER NAME AND ADDRESS CODE 10 bytes	Indicates a specific customer, installation and/or system to which the volume belongs. This field may be a standardized code, name, address etc.
			9	RESERVED 29 bytes	Reserved

Note: All reserved fields should contain blanks to facilitate their use in the future.

STANDARD VOLUME LABEL , TAPE


ANSI Standard Volume Label format and contents for ASCII tapes

Field		Volume Label number						
1	2 3	4 5	6	7	8	9		
	Volume Serial Number	Reserved	Reserved	Owner name and Identification code	Reserved			
3	4 5	10 11	12 13	14 15	16 17	18 19	20 21	
Label Identifier	Accessibility					Label Standard Level		

FIELD	NAME AND LENGTH	DESCRIPTION	FIELD	NAME AND LENGTH	DESCRIPTION
1	LABEL IDENTIFIER 3 bytes	Must contain VOL to indicate that this a Volume Label.	6	RESERVED 6 bytes	Reserved for future use as required by American National Standards Institute, Inc. Should contain spaces.
2	VOLUME LABEL NR 1 byte	Must be 1. If any other standard volume labels are present (indicated by an entry other than 1 in this field) they are ignored.	7	OWNER NAME AND IDENTIFICATION CODE 14 bytes	Indicates a specific customer, installation and /or system to which the volume belongs. This field may be a standardized code, name, address etc.
3	VOLUME SERIAL NR 6 bytes	Uniquely identifies this volume. Must consist of 6 bytes and may be any character except a quote(').	8	RESERVED 28 bytes	Reserved for future use as required by the American National Standards Institute, Inc. Should contain spaces.
4	ACCESSIBILITY 1 byte	Indicates accessibility protection: Space: No accessibility protection. Nospace: Accessibility protection.	9	LABEL STANDARD LEVEL 1 byte	Indicates whether this volume observes the American National Standards: Dec. 1: Volume observes the standards (1 is also the default value) Space: Volume does not observe the standards, but it follows an agreed format.
5	RESERVED 20 bytes	Reserved for future use as required by the American National Standards Institute, Inc. Should contain spaces.			

STANDARD MAGNETIC TAPE FILE LABEL

IBM Standard Tape File Label Format and Contents



FIELD	NAME AND LENGTH	DESCRIPTION	FIELD	NAME AND LENGTH	DESCRIPTION
1	LABEL IDENTIFIER 3 bytes EBCDIC	Identifies the type of label: HDR: Header--beginning of data file. EOF: End of File--end of a set of data. EOV: End of Volume--end of the physical reel.	5	VOLUME SEQUENCE NUMBER 4 bytes	Indicates the order of a volume in a given file or multi-file set. This number must be numeric(0000-9999). Multiple volumes of an output file will be numbered in consecutive sequence.
2	FILE LABEL NUMBER 1 byte EBCDIC	Always a 1	6	FILE SEQUENCE NUMBER 4 bytes	Assign numeric sequence to a file within a multi file set.
3	FILE IDENTIFIER 17 bytes EBCDIC	Uniquely identifies the entire file, may contain only printable characters.	7	GENERATION NUMBER 4 bytes	Numerically identifies the various editions of the file.
4	FILE SERIAL NUMBER 6 bytes EBCDIC	Uniquely identifies a file-volume relationship. This field is identical to the Volume Serial Number in the volume label on the first or only volume of a multi-volume file or a multi-file set. This field will normally be numeric(000001 to 999999) but may contain any six alphanumeric characters.	8	VERSION NUMBER OF GENERATION 2 bytes	Indicates the version of the generation of a file.

STANDARD MAGNETIC TAPE FILE LABEL (...Cont'd)


FIELD	NAME AND LENGTH	DESCRIPTION												
9	CREATION DATE 6 bytes	Indicates the year and the day of the year that the file was created: <table border="1"> <thead> <tr> <th>Position</th> <th>Code</th> <th>Meaning</th> </tr> </thead> <tbody> <tr> <td>1</td> <td>blank</td> <td>none</td> </tr> <tr> <td>2-3</td> <td>00-99</td> <td>year</td> </tr> <tr> <td>4-6</td> <td>001-366</td> <td>day of year</td> </tr> </tbody> </table> (e.g., January 31, 1965 would be entered as 65031)	Position	Code	Meaning	1	blank	none	2-3	00-99	year	4-6	001-366	day of year
Position	Code	Meaning												
1	blank	none												
2-3	00-99	year												
4-6	001-366	day of year												
10	EXPIRATION DATE 6 bytes	Indicates the year and the day of the year when the file may become a scratch tape. The format of this field is identical to field 9. On a multi-file reel, processed sequentially, all files are considered to expire on the same day. Retention period dddd=0-9999.												
11	FILE SECURITY 1 byte	Indicates the security status of the file. 0: No security protection. 1: Security protection. Additional identification of the file is required before it can be processed.												
12	BLOCK COUNT 6 bytes	Indicates the number of data blocks written on the file from the last header label to the first trailer label, exclusive of tape marks. Count does not include checkpoint records. This field is used in trailer labels.												

IBM Standard Tape File Label Format and Contents

FIELD	NAME AND LENGTH	DESCRIPTION
13	SYSTEM CODE 13 bytes	Uniquely identifies the programming system.
14	RESERVED 7 bytes	Reserved

STANDARD MAGNETIC TAPE FILE LABEL

ASCII Standard Tape File Label Format and Contents



<u>FIELD</u>	<u>NAME AND LENGTH</u>	<u>DESCRIPTION</u>
1	LABEL IDENTIFIER 3 bytes,ASCII	Identifies the type of label: HDR: Header--beginning of a data file. EOF: End of File--end of a set of data. EOV: End of Volume--end of the physical reel.
2	FILE LABEL NUMBER 1 byte,ASCII	Indicates the sequence of this label within a label group(HDR, EOF, EOV).DOS/VS supports File Label 1 only and ignores subsequent numbers.
3	FILE IDENTIFIER 17 bytes,ASCII	Identifies the entire file. May be any character except a quote(").
4	SET IDENTIFIER 6 bytes,ASCII	Identifies the volume-file relationship. Generally, this field is identical to the volume serial number from the VOL label or the first or only volume of the logical file.


<u>FIELD</u>	<u>NAME AND LENGTH</u>	<u>DESCRIPTION</u>
5	FILE SECTION NUMBER 4 bytes	Indicates the order of a volume in a given file or multi-file set.(The first file must be numbered 0001).
6	FILE SEQUENCE NUMBER 4 bytes	Assigns numeric sequence to a file within a multi-file set.(The first file must be numbered 0001).
7	GENERATION NUMBER 4 bytes	Numerically identifies this edition of the file.(Must be numerical or blank).
8	VERSION NUMBER OF GENERATION 2 bytes	Indicates this version of the generation in field 7.(Must be numerical or blank).
9	CREATION DATE 6 bytes	Indicates the year and the day of the year that this file was created (byydd),where: b= blank yy= year (00-99) ddd= day (001-366)

STANDARD MAGNETIC TAPE FILE LABEL (...Cont'd)

<u>FIELD</u>	<u>NAME AND LENGTH</u>	<u>DESCRIPTION</u>
10	EXPIRATION DATE 6 bytes	Indicates the year and the day of the year that this file may become a scratch tape. Same format as above (Field 9).
11	ACCESSIBILITY 1 byte	Indicates the accessibility protection of the file. Space: no accessibility protection. Nonspace: accessibility protection.
12	BLOCK COUNT 6 bytes	Indicates the number of data blocks (physical records) written for this logical file.
13	SYSTEM CODE 13 bytes	Uniquely identifies the programming system.
14	RESERVED 7 bytes	Reserved for future use as required by ANSI.(American National Standards Institute, Inc.). Should be recorded as spaces.

ASCII Standard Tape File Label Format and Contents

<u>FIELD</u>	<u>NAME AND LENGTH</u>	<u>DESCRIPTION</u>
--------------	------------------------	--------------------




III-07

FIELD	NAME AND LENGTH	DESCRIPTION	FIELD	NAME AND LENGTH	DESCRIPTION
1	LABEL IDENTIFIER 3 bytes	Must contain VOL to indicate that this is a Volume Label.	7	CONTROL INTERVAL SIZE 4 bytes	Identifies the fixed length CI-size by which the VTOC for FBA devices is subdivided.
2	VOLUME LABEL NO. 1 byte	Indicates the relative position (1-8) of a volume label within a group of volume labels.	8	NUMBER OF BLOCKS PER CI 4 bytes	Indicates the number of physical blocks per control interval.
3	VOLUME SERIAL NO. 6 bytes	A unique identification code which is assigned to a volume when it enters an installation. This code may also appear on the external surface of the volume for visual identification. It is normally a numeric field 000001 to 999999, however any or all of the 6 bytes may be alphanumeric.	9	NUMBER OF LABELS PER CI 4 bytes	Indicates the number of slots in each CI which may contain labels.
4	VOLUME SECURITY 1 byte (OS/VS only)	Indicates security status of the volume: 0: No further identification for each file of the volume is required; 1: Further identification for each file of the volume is required before processing.	10	RESERVED 4 bytes	
5	DATA FILE DIRECTORY 5 bytes	Provides the starting address of the VTOC.	11	OWNER NAME AND ADDRESS CODE 14 bytes	Indicates a specific customer, installation or system to which this volume belongs. This field is printed on SYSLST when LVT0C is executed.
6	RESERVED 5 bytes		12	RESERVED 29 bytes	
			13	STANDARD LABEL VERSION 1 byte	Indicates FBA or non-FBA-device.

STANDARD DASD FILE LABEL , FORMAT 1

(Format 1: This format is common to all data files on Direct Access Storage Devices)



FIELD NAME AND LENGTH

DESCRIPTION

1 FILE NAME
44 bytes, alphameric
EBCDIC

This field serves as the key portion of the file label. Each file must have a unique file name. Duplication of file names will cause retrieval errors. The file name can consist of three sections:

1 File ID is an alphameric name assigned by the user and identifies the file. Can be 1-35 bytes if generation and version numbers are used, or 1-44 bytes

FIELD NAME AND LENGTH

DESCRIPTION

if they are not used.

2 Generation number. If used, this field is separated from File ID by a period. It has the format Gnnnn, where G identifies the field as the generation number and nnnn (in decimal) identifies the generation of the file.

3 Version Number of Generation. If used, this section immediately follows the

STANDARD DASD FILE LABEL , FORMAT 1 (...Cont'd)

<u>FIELD</u>	<u>NAME AND LENGTH</u>	<u>DESCRIPTION</u>
1	FILENAME (Cont'd)	generation number and has the format Vnn, where V identifies the field as the version of generation number and nnn (in decimal) identifies the version of generation of the file.
The remaining fields comprise the DATA portion of the file label:		
2	FORMAT IDENTIFIER 1 byte, EBCDIC numeric	1 = Format 1
3	FILE SERIAL NO. 6 bytes, EBCDIC alphanumeric	Uniquely identifies a file/volume relationship. It is identical to the Volume Serial Number of the first or only volume of a multivolume file.
4	VOLUME SEQUENCE NO. 2 bytes, binary	Indicates the order of a volume relative to the first volume on which the data file resides.
5	CREATION DATE 3 bytes, discontinuous binary	Indicates the year and the day of the year the file was created. It is of the form YDD, where Y signifies the year (0-99) and DD the day of the year (1-366).
6	EXPIRATION DATE 3 bytes, discontinuous binary	Indicates the year and the day of the year the file may be deleted. The form of this field is the same as that of field 5.
7A	EXTENT COUNT	Contains a count of the number of extents for this file on this volume. If user labels are used, the count does not include the user label track.

<u>FIELD</u>	<u>NAME AND LENGTH</u>	<u>DESCRIPTION</u>
7B	BYTES USED IN LAST BLOCK OF DIRECTORY 1 byte, binary	Used by OS/VS
7C	SPARE 1 byte	Reserved
8	SYSTEM CODE 13 bytes	Uniquely identifies the programming system. The character codes that can be used in this field are limited to EBCDIC characters. On input, IOCS ignores this field. On output, IOCS writes the information supplied in DLBL.
9	LAST ACCESSED DATE 3 bytes, disc. binary	Indicates the date of last access of this data set. Form = YDD; Y = year.(0-99), D = day (0-366).
9a	FILE CONTROL INTERVAL SIZE. 2 bytes	Indicates the number of physical blocks per CI for FBA device file.
10	FILE TYPE 2 bytes	The contents of this field uniquely identify the type of data file: Hex 0000: Organization not defined in the file label Hex 0008: VSAM Hex 2000: Direct access organization (DAM) Hex 4000: Sequential organization (SAM) Hex 8000: Indexed sequential organization (ISAM)

STANDARD DASD FILE LABEL , FORMAT 1 (...Cont'd)


<u>FIELD</u>	<u>NAME AND LENGTH</u>	<u>DESCRIPTION</u>
11	RECORD FORMAT 1 byte	Used by OS/VS
12	OPTION CODES 1 byte	Bits within this field indicate various options used in building the file: Bit 0: 0 Bit 1: Reserved Bit 2: Master index present (ISAM) Bit 3: Independent overflow present (ISAM) Bit 4: Cylinder overflow present (ISAM) Bit 5: Reserved
13	BLOCK LENGTH 2 bytes, binary	Indicates the block length of logical records (and therefore, the length of a physical record).
14	RECORD LENGTH 2 bytes, binary	Indicates the length of each logical record.
15	KEY LENGTH 1 byte, binary	Indicates the length of the key portion of the data records in the file.
16	KEY LOCATION 2 bytes, binary	Indicates the location of the key field.
17	DATA SET INDICATORS 1 byte	Bits within this field are used to indicate the following: Bit 0: If on, indicates that this is the last volume on which this file normally resides. Bit 1,2,4,6,7: Used by OS/VS. Bit 3,5: If on, data set security is invoked.

<u>FIELD</u>	<u>NAME AND LENGTH</u>	<u>DESCRIPTION</u>
18	SECONDARY ALLOCATION 4 bytes, binary	Byte 0: Indicates the type of request. Byte 1-3: Used by OS/VS
19	LAST RECORD POINTER 5 bytes, discontinuous binary	Used by OS/VS
20	OFFSET to NEXT RECORD SPACE 2 bytes	Starting position of next sequential record relative to the End of Data Pointer. Contains a negative displacement.
21	EXTENT TYPE INDICATOR 1 byte	Indicates the type of extent with which the following fields are associated: HEX CODE 00: Next three fields do not indicate any extent. 01: Data area (SAM, DAM), Prime data area (ISAM), Data Space (VSAM). 02: Overflow area of an indexed sequential file. 04: Cylinder index or master index area of an indexed sequential file. 40: User standard label area. 80: Shared cylinder indicator.

STANDARD DASD FILE LABEL , FORMAT 1 (...Cont'd)

<u>FIELD</u>	<u>NAME AND LENGTH</u>	<u>DESCRIPTION</u>	<u>FIELD</u>	<u>NAME AND LENGTH</u>	<u>DESCRIPTION</u>
22	EXTENT SEQUENCE NO. 1 byte, binary	Indicates the extent sequence in a multi- extent file.	33	POINTER TO NEXT FILE LABEL WITHIN THIS LABEL SET 5 bytes, discontinuous binary CCHHR or blocks	The address of a continuation label if needed to further describe the file. If field 10 indicates Indexed Sequential organi- zation, this field points to a Format 2 file label within this label set. Otherwise, it points to a Format 3 file label, and then only if the file contains more than three extent segments. This field contains all binary zeros if no additional file label is pointed to.
23	LOWER LIMIT 4 bytes, discontinuous binary CCHH or blocks	The address specifying the starting point (lower limit) of this extent component.			
* 25-28	ADDITIONAL EXTENT 10 bytes	These fields have the same format as the fields 21-24 above.			
29-32	ADDITIONAL EXTENT 10 bytes	These fields have the same format as the fields 21-24 above.	* 24	UPPER LIMIT 4 bytes CCHH or blocks	The address specifying the ending point (upper limit) of this extent component.

STANDARD DASD FILE LABEL , FORMAT 2



SEE NEXT PAGE FOR FURTHER EXPLANATION

STANDARD DASD FILE LABEL , FORMAT 2 (. . . Cont'd)

<u>FIELD</u>	<u>NAME AND LENGTH</u>	<u>DESCRIPTION</u>	<u>FIELD</u>	<u>NAME AND LENGTH</u>	<u>DESCRIPTION</u>
K1	KEY IDENTIFICATION 1 byte	This byte contains the hex code 02 in order to avoid conflict with a file name.	D2	NUMBER OF INDEX LEVELS 1 byte, binary	1 = Cylinder Index 2 = Cylinder and Master Index
K2	ADDRESS OF 2nd LEVEL MASTER INDEX 7 bytes, discontinuous binary	This field contains the address of the first track of the second level of the master index, in the form MBBCCHH. (OS/VS only)	D3	HIGH LEVEL INDEX DEVELOPMENT INDICATOR 1 byte, binary	This field contains the number of tracks determining development of Master Index. (OS/VS only)
K3	LAST 2nd LEVEL MASTER INDEX ENTRY 5 bytes, discontinuous binary	This field contains the address of the last index entry in the second level of the master index, of the form CCHHR. (OS/VS only)	D4	FIRST DATA RECORD IN CYLINDER 3 bytes	This field contains the address of the first data record on each cylinder in the form HHR.
K4	ADDRESS OF 3rd LEVEL MASTER INDEX 7 bytes, discontinuous binary	This field contains the address of the first track of the third level of the master index, in the form MBBCCHH. (OS/VS only)	D5	LAST DATA TRACK IN CYLINDERS 2 bytes	This field contains the address of the last data track on each cylinder, in the form HH.
K5	LAST 3rd LEVEL MASTER INDEX ENTRY 5 bytes, discontinuous binary	This field contains the address of the last entry in the third level of the master index, in the form CCHHR. (OS/VS only)	D6	NUMBER OF TRACKS FOR CYLINDER OVERFLOW 1 byte, binary	This field contains the number of tracks in cylinder overflow area. (OS/VS only)
K6	SPARE 11 bytes	Reserved	D7	HIGHEST "R" ON HIGH LEVEL INDEX TRACK 1 byte	This field contains the highest possible R on track containing high-level index entries.
K7	LAST PRIME TRACK ADDRESS 8 bytes	The address of the last prime track on the last prime cylinder.	D8	HIGHEST "R" ON PRIME TRACK 1 byte	This field contains the highest possible R on prime data tracks for form F records.
D1	FORMAT IDENTIFIER 1 byte, EBCDIC numeric	2: Format 2	D9	HIGHEST "R" ON OVERFLOW TRACK 1 byte	This field contains the highest possible R on overflow data tracks for form F records.

STANDARD DASD FILE LABEL , FORMAT 2 (...Cont'd)


<u>FIELD</u>	<u>NAME AND LENGTH</u>	<u>DESCRIPTION</u>	<u>FIELD</u>	<u>NAME AND LENGTH</u>	<u>DESCRIPTION</u>
D10	"R" OF LAST DATA RECORD ON SHARED TRACK 1 byte	This field contains the R of the last data record on a shared track.	D17	STATUS INDICATOR 1 byte	The eight bits of this byte are used for the following indications: Bit 0-1: must remain off Bit 2: file closed for ADD or ADDRTR Bit 3-5: must remain off Bit 6: last track full Bit 7: last block full
D11A	"R" OF LAST DATA RECORD ON UNSHARED TRACK	The record number of the last data record on an unshared track of the track index.	D18	ADDRESS OF CYLINDER INDEX 7 bytes	This field contains the address of first track of the cylinder index, in the form MBBCCHH.
D11B	HIGHEST "R" ON INDEPENDENT OVERFLOW TRACK	The highest possible record number for independent overflow tracks with format F records.	D19	ADDRESS OF LOWEST LEVEL MASTER INDEX 7 bytes	This field contains the address of the first track of the lowest-level index of the high level indexes, in the form MBBCCHH.
D12	TAG DELETION COUNT 2 bytes, binary	This field contains the number of records that have been tagged for deletion.	D20	ADDRESS OF HIGHEST LEVEL INDEX 7 bytes	This field contains the address of the first track of the highest level master index, in the form MBBCCHH.
D13	NONFIRST OVERFLOW REFERENCE COUNT 3 bytes, binary	This field contains a count of the number of random references to a nonfirst overflow record.	D21	LAST PRIME DATA RECORD ADDRESS 8 bytes	This field contains the address of the last data record in the prime data area, in the form MBBCCHHR.
D14	NUMBER OF BYTES FOR HIGHEST LEVEL INDEX 2 bytes, binary	The contents of this field indicate how many bytes are needed to hold the highest level index in main storage.	D22	LAST TRACK INDEX ENTRY ADDRESS 5 bytes	This field contains the address of the last normal entry in the track index on the last cylinder in the form CCHHR.
D15	NUMBER OF TRACKS FOR HIGHEST LEVEL INDEX 1 byte, binary	This field contains a count of the number of tracks occupied by the highest level index.	D23	LAST CYLINDER INDEX ENTRY ADDRESS 5 bytes	This field contains the address of the last index entry in the cylinder index in the form CCHHR.
D16	PRIME RECORD COUNT 4 bytes, binary	This field contains a count of the number of records in the prime data area.	D24	LAST MASTER INDEX ENTRY ADDRESS 5 bytes	This field contains the address of the last index entry in the master index, in the form CCHHR.

STANDARD DASD FILE LABEL , FORMAT 2 (...Cont'd)

<u>FIELD</u>	<u>NAME AND LENGTH</u>	<u>DESCRIPTION</u>	<u>FIELD</u>	<u>NAME AND LENGTH</u>	<u>DESCRIPTION</u>
D25	LAST INDEPENDENT OVERFLOW RECORD ADDRESS 8 bytes	This field contains the address of the last record written in the current independent overflow area, in the form MBBCCHHR.	D29	CYLINDER OVERFLOW AREA COUNT 2 bytes, binary	This field contains the number of cylinder overflow areas full.
D26	BYTES REMAINING ON OVERFLOW TRACK 2 bytes, binary	This field contains the number of bytes remaining on current independent overflow track. (OS/VS only)	D30	DUMMY TRACK INDEX ENTRY 3 bytes	This field contains the HHR portion of the dummy track index entry.
D27	NUMBER OF INDEPENDENT OVERFLOW TRACKS 2 bytes, binary	This field contains the number of tracks remaining in independent overflow area.	D31	POINTER TO FORMAT 3 FILE LABEL 5 bytes	This field contains the address (in the form CCHHR) of a Format 3 file label if more than 3 extent segments exist for the data file within this volume. Otherwise it contains binary zeros. (OS/VS only)
D28	OVERFLOW RECORD COUNT 2 bytes, binary	This field contains a count of the number of records in the overflow area.			

STANDARD DASD FILE LABEL , FORMAT 4

This format is used to describe the Volume Table of Contents and is always the first label in the VTOC. There must be one and only one of these Format 4 file labels per volume.



FIELD	NAME AND LENGTH	DESCRIPTION	FIELD	NAME AND LENGTH	DESCRIPTION
1	KEY FIELD 44 bytes, binary	Each byte of this field contains the Hex code 04 in order to provide a unique key.	5	NEXT AVAILABLE ALTERNATE TRACK 4 bytes	Contains the address (in the form CCHH) of the next track to be assigned as an alternate track. FBA = zero
2	FORMAT ID 1 byte, EBCDIC numeric	4: Format 4.	6	NUMBER OF ALTERNATE TRACKS 2 bytes, binary	Contains the number of alternate tracks available. FBA = zero
3	LAST ACTIVE FORMAT 1 5 bytes	Contains the address (in the form CCHHR) of the last active Format 1 file label. It is used to stop a search on a file name. (OS/VS only)	7	VTOC INDICATORS 1 byte	Bit 0: Always on; Off applies to OS/VS only. Bit 3: On = Volume reserved for use by Emulator programs. Bit 5: On = VSAM DADSM bit. All other Bits OFF.
4	AVAILABLE FILE LABEL RECORDS 2 bytes	Number of label records available after disk initialization.			

STANDARD DASD FILE LABEL , FORMAT 4 (...Cont'd)

FIELD	NAME AND LENGTH	DESCRIPTION
8A	NUMBER OF EXTENTS 1 byte	Contains the hexadecimal constant 01, to indicate one extent in the VTOC.
8B	RESERVED 2 bytes	Reserved.
9	DEVICE CONSTANTS 14 bytes	This field contains constants describing the device on which the volume was mounted when the VTOC was created. The following describes each of the subfields:
Device Size:	(4 bytes)—The number of cylinders (CC) and tracks per cylinder (HH).	
Track Length:	(2 bytes)—The number of available bytes on a track exclusive of home address and record zero. (Record zero is assumed to be a nonkeyed record with an eight bytes data field.)	
Record Overhead:	(3 bytes)—The number of bytes required for gaps, check bits, and count field for each record. This value varies according to the record characteristics and thus is broken down into three subfields.	
	I: Overhead required for a keyed record other than the last record on the track.	
	L: Overhead required for a keyed record that is the last record on the track.	
	K: Overhead bytes to be subtracted from I or L if the record does not have a key field.	

Flag:	(1 byte)—Further defines unique characteristics of the device.
Bits:	0–5: Do not apply to the 2311, 2314, 2319, 3330, or 3340. 4: ON indicates that I and L values share a 2 byte field for the 3350. 7: ON indicates that a tolerance factor must be applied to each record except the last on each track.
Tolerance:	(2 bytes)—A value that is to be used to determine the effective length of the record on the track. This factor is used if bit 7 of the Flag byte is on.
Labels/track:	(1 byte)—A count of the number of labels that can be written on each track in the VTOC. (Number of full records of 44-bytes key and 96-bytes data length that can be contained on one track of this device.)
Directory Blocks/Track	(1 byte)—A count of the number of directory blocks that can be written on each track for an OS/VS partitioned data set. (Number of full records of 8-bytes key and 256-bytes data length that can be contained on one track of this device.)

STANDARD DASD FILE LABEL, FORMAT 4 (...Cont'd)


<u>FIELD</u>	<u>NAME AND LENGTH</u>	<u>DESCRIPTION</u>
9	DEVICE CONSTANTS (...Cont'd)	The following illustrates the device constants field for the various direct access devices:

<u>Device</u>	<u>CC</u>	<u>HH</u>	<u>Track Length</u>	<u>I</u>	<u>L</u>	<u>K</u>	<u>Flag</u>	<u>Tol.</u>	<u>Labels Track</u>
2311	203	10	3625	81	20	20	1	537	16
2314/2319	203	20	7294	146	45	45	1	534	25
3330	411	19	13165	191	191	56	0	512	39
3330-11	815	19	13165	191	191	56	0	512	39
3340/35MB	350	12	8535	242	242	75	0	512	22
3340/70MB	700	12	8535	242	242	75	0	512	22
3350	555	30	19254	267	267	82	8	512	46


Note: Labels per track = $\frac{\text{track length}}{\text{I} + \text{label length}}$

<u>FIELD</u>	<u>NAME AND LENGTH</u>	<u>DESCRIPTION</u>
10A	VSAM INDICATORS 19 bytes	The VSAM indicators are present on any volume that contains space allocated to VSAM. If a volume does not contain any VSAM-owned space, these fields are set to zeros.

<u>FIELD</u>	<u>NAME AND LENGTH</u>	<u>DESCRIPTION</u>
	VSAM TIMESTAMP 8 bytes	Is the time the most recent VSAM data space was added to the volume.
	VSAM CATALOG 1 byte	Bit 0 = ON: This volume is owned by a VSAM catalog. Bit 1-7: Unused
	TT OF CRA 2 bytes	Relative track number of first track of catalog recovery area.
	VSAM TIMESTAMP 8 bytes	
10B	CATALOG RECOVERY AREA POINTER 4 bytes	The physical block number pointer of the catalog recovery area for this volume.
11-14	VTOC EXTENT 10 bytes	These fields describe the extent of the VTOC and are identical in format to fields 21-24 of the Format 1 file label. Extent type 01 (prime data area).
15	RESERVED 25 bytes	Reserved



<u>FIELD</u>	<u>NAME AND LENGTH</u>	<u>DESCRIPTION</u>
1	LABEL IDENTIFIER 3 bytes	Contents VOL.
2	VOLUME LABEL NO. 1 byte	Contents '1'.
3	VOLUME SERIAL NO. 6 bytes	Identification for a volume usually a number, but may also be alphanumeric.
4	ACCESSIBILITY INDICATOR 1 byte	Blank or S. Indicates that additional qualification is needed.
6	OWNER IDENTIFICATION 14 bytes	Name or a code. Specifies the owner of the volume.
8	LABEL STANDARD LEVEL 1 byte	Must contain W.



FIELD	NAME AND LENGTH	DESCRIPTION	FIELD	NAME AND LENGTH	DESCRIPTION
1	LABEL ID 3 bytes	Must contain 'HDR'.	15	INTERCHANGE LEVEL 1 byte	Identifies: Physical Record Length Record Length - Fixed Record Attributes File Organization. Blank or 'E'.
2	LABEL NUMBER 1 byte	Must contain '1'.	16	MULTIVOLUME INDICATOR 1 byte	Indicates: Blank = File complete C = File continued on another volume L = File complete.
4	FILE ID 8 bytes	Identification name, alphameric.	17	VOLUME SEQUENCE NUMBER 2 bytes	Number of Volumes in a multivolume file. Decimal digits.
6	RECORD LENGTH 5 bytes	Length of the data records. Decimal right-justified.	18	CREATION DATE 6 bytes	Date the file was created, form = YYMMDD decimal.
8	EXTENT BEGIN 5 bytes	Begin of Extent area. Decimal in form CCHHR.	20	EXPIRATION DATE 6 bytes	Date this file may be purged, form = YYMMDD decimal.
10	EXTENT END 5 bytes	End of extent area. Decimal in form CCHHR.	21	VERIFY INDICATOR 1 byte	Indicates whether or not data has been subjected to verification. Blank or 'V'.
12	BYPASS INDICATOR 1 byte	Indicates whether or not a file is interchanged. Blank or 'B'.	23	END OF DATA ADDRESS 5 bytes	Address of next higher unused record, form = CCHHR decimal.
13	FILE SECURITY 1 byte	Indicates whether or not additional qualifications must be supplied. Blank or 'S'.			
14	WRITE PROTECT 1 byte	Indicates whether or not a file may be overwritten. Blank or 'P'.			

Fields 3, 5, 7, 9, 11, 19, 22 and 24 are reserved.

DATA MANAGEMENT AND SYSTEM CONTROL MACROS

Declarative Macros

Name	Operation	Operands	Description
[name]	CDMOD	[CONTROL=YES] [.CRDERR=RETRY] [.CTLCHR={ASA YES}] [.DEVICE=nnnn] [.FUNC={R P I RPI RW RPW PW}] [.IOAREA2=YES] [.RDONLY=YES] [.RECFORM={FIXUNB VARUNB UNDEF}] [.SEPASMB=YES] [.TYPEFLE={INPUT OUTPUT CMBND}] [.WORKA=YES]	Defines a logic module for a card reader file
[name]	DFR	FONT=xxxx [.BCH=n] [.BCHSER=n] [.CHRSET=n] [.EDCHAR={x,...}] [.ERASE={NO YES}] [.NATNHP={NO YES}] [.REJECT=x]	Defines attributes common to a group of line types
[name]	DIMOD	[IOAREA2=YES] [.RDONLY=YES] [.RPS=SVA] [.SEPASMB=YES] [.TRC=YES] [.TYPEFLE={OUTPUT INPUT}]	Defines a logic module for a device-independent file
[name]	DLINT	LFR=nn,LINBEG=nn [.IMAGE={NO YES}] [.NOSCAN=(n,n)] [.FLDn=(n,n,NCRIT,xxx)] [.EDITn=(xxxxxx,EDCHAR)] [.FRIEND={NO YES}]	Describes line types, fields in the line
[name]	DRMOD	[DEVICE=3886] [.RDONLY=YES] [.SEPASMB=YES] [.SETDEV=YES]	Defines logic modules for a 3886 file
[name]	DTFCD	DEVADDR=SYSxxx .IOAREA1=xxxxxxxx [.ASOCFLE=xxxxxxxx] [.BLKSIZE=nnn] [.CONTROL=YES] [.CRDERR=RETRY] [.CTLCHR=xxx] [.DEVICE=nnnn] [.EOFADDR=xxxxxxxx] [.ERROPT=xxxxxxxx] [.FUNC=xxx] [.IOAREA2=xxxxxxxx] [.IOREG=(nn)] [.MODE=xx] [.MODNAME=xxxxxxxx] [.OUBLKSZ=nn] [.RDONLY=YES] [.RECFORM=xxxxxxxx] [.RECSIZE=(nn)] [.SEPASMB=YES] [.SSELECT=n] [.TYPEFLE=xxxxxxxx] [.WORKA=YES]	Defines a card or 3881 file

DATA MANAGEMENT AND SYSTEM CONTROL MACROS (. . .Cont'd)

Declarative Macros (Cont'd)

Name	Operation	Operands	Description
[name]	DTFCN	DEVADDR=SYSxxx .IOAREA1=xxxxxxxx [,BLKSIZE=nnn] [,INPSIZE=nnn] [,MODNAME=xxxxxxxx] [,RECFORM=xxxxxxx] [,RECSIZE=(nn)] [,TYPEFLE=xxxxxxx] [,WORKA=YES]	Defines a console file
[name]	DTFDA	BLKSIZE=nnnn .ERRBYTE=xxxxxxxx .IOAREA1=xxxxxxxx .SEEKADR=xxxxxxx .TYPEFLE=xxxxxxx [,AFTER=YES] [,CONTROL=YES] [,DEVADDR=SYSnnn] [,DSKXTNT=n] [,ERREXT=YES] [,FEOVD=YES] [,HOLD=YES] [,IDLOC=xxxxxxxx] [,KEYARG=xxxxxxxx] [,KEYLEN=nnn] [,LABADDR=xxxxxxxx] [,RDONLY=YES] [,READID=YES] [,READKEY=YES] [,RECFORM=xxxxxxx] [,RECSIZE=(nn)] [,RELTYPE=xxx] [,SEPASMB=YES] [,SRCHM=YES] [,TRLBL=YES] [,VERIFY=YES] [,WRITEID=YES] [,WRITEKY=YES] [,XTNTXIT=xxxxxxxx]	Defines a direct access file
[name]	DTFDI	DEVADDR=SYSxxx .IOAREA1=xxxxxxxx [,CISIZE=n] [,EOFADDR=xxxxxxxx] [,ERROPT=xxxxxxxx] [,FBA=YES] [,IOAREA2=xxxxxxxx] [,IOREG=(r)] [,MODNAME=xxxxxxxx] [,RDONLY=YES] [,RECSIZE=nnn] [,SEPASMB=YES] [,TRC=YES] [,WLRERR=xxxxxxxx]	Defines a device-independent file
[name]	DTFDR	COREXIT=xxxxxxxx .DEVADDR=SYSxxx .EOFADDR=xxxxxxxx .EXITIND=xxxxxxxx .FRNAME=xxxxxxxx .FRSIZE=nn .HEADER=xxxxxxxx .IOAREA1=xxxxxxxx [,BLKSIZE=nnn] [,DEVICE=3886] [,MODNAME=xxxxxxx] [,RDONLY=YES] [,SEPASMB=YES] [,SETDEV=YES]	Defines a 3886 OCR file

DATA MANAGEMENT AND SYSTEM CONTROL MACROS (. . . Cont'd)

Declarative Macros (Cont'd)

Name	Operation	Operands	Description
[name]	DTFDU	EOFADDR=xxxxxxx ,IOAREA1=xxxxxxx ,RECSIZE=nnn [,CMDCHN=nn] [,DEVADDR=SYSxxx] [,DEVICE=3540] [,ERREXT=YES] [,ERROPT=xxxxxxx] [,FEED=xxx] [,FILESEC=YES] [,IOAREA2=xxxxxxx] [,IOREG=(nn)] [,MODNAME=xxxxxxx] [,RDONLY=YES] [,SEPASMB=YES] [,TYPEFLE=xxxxxx] [,VERIFY=YES] [,VOLSEQ=YES] [,WORKA=YES] [,WRTPROT=YES]	Defines a diskette file
[name]	DTFIS	DSKXTNT=n ,IOROUT=xxxxxx ,KEYLEN=nnn ,NRECDs=nnn ,RECFORM=xxxxxx ,RECSIZE=nnnn [,CYLOFL=nn] [,DEVICE=nnnn] [,ERREXT=YES] [,HINDEX=nnnn] [,HOLD=YES] [,INDAREA=xxxxxxx] [,INDSKIP=YES] [,INDSIZE=nnnnn] [,IOAREAL=xxxxxxx] [,IOAREAR=xxxxxxx] [,IOAREAS=xxxxxxx] [,IOAREA2=xxxxxxx] [,IOREG=(nn)] [,IOSIZE=nnnnn] [,KEYARG=xxxxxxx] [,KEYLOC=nnnn] [,MODNAME=xxxxxxx] [,MSTIND=YES] [,RDONLY=YES] [,SEPASMB=YES] [,TYPEFLE=xxxxxx] [,VERIFY=YES] [,WORKL=xxxxxxx] [,WORKR=xxxxxxx] [,WORKS=YES]	Defines an indexed-sequential file
[name]	DTFMR	DEVADDR=SYSnnn ,IOAREA1=xxxxxxx [,ADDAREA=nnn] [,ADDRESS=DUAL] [,BUFFERS=nnn] [,ERROPT=xxxxxxx] [,EXTADDR=xxxxxxx] [,IOREG=(nn)] [,MODNAME=xxxxxxx] [,RECSIZE=nnn] [,SECADDR=SYSnnn] [,SEPASMB=YES] [,SORTMDE=xxx]	Defines a MICR/OCR file

DATA MANAGEMENT AND SYSTEM CONTROL MACROS (. . .Cont'd)

Declarative Macros (Cont'd)

Name	Operation	Operands	Description
[name]	DTFMT	BLKSIZE=nnnnn ,DEVADDR=SYSxxx ,EOFADDR=xxxxxxxxx ,FILABL=xxxx ,IOAREA1=xxxxxxxx [,ASCII=YES] [,BUFOF=nn] [,CKPTREC=YES] [,ERREXT=YES] [,ERROPT=xxxxxxxx] [,HDRINFO=YES] [,IOAREA2=xxxxxxxx] [,IOREG=(nn)] [,LABADDR=xxxxxxxx] [,LENCHK=YES] [,MODNAME=xxxxxxxx] [,NOTEPNT=xxxxxx] [,RDONLY=YES] [,READ=xxxxxxx] [,RECFORM=xxxxxx] [,RECSIZE=nnnn] [,REWIND=xxxxxx] [,SEPASMB=YES] [,TPMARK={YES NO}] [,TYPEFLE=xxxxxx] [,VARBLD=(nn)] [,WLRERR=xxxxxxxx] [,WORKA=YES]	Defines a magnetic tape file
[name]	DTFOR	COREXIT=xxxxxxxx ,DEVADDR=SYSnnn ,EOFADDR=xxxxxxxx ,IOAREA1=xxxxxxxx [,BLKFAC=nn] [,BLKSIZE=nn] [,CONTROL=YES] [,DEVICE=xxxxx] [,HEADER=YES] [,HPRMTY=YES] [,IOAREA2=xxxxxxxx] [,IOREG=(nn)] [,MODNAME=xxxxxxxx] [,RECFORM=xxxxxx] [,RECSIZE=(nn)] [,SEPASMB=YES] [,WORKA=YES]	Defines a 1287 or 1288 optical reader file
[name]	DTFPH	TYPEFLE=xxxxxx [,ASCII=YES] [,CISIZE=n] [,CCWADDR=xxxxxxxx] [,DEVADDR=SYSxxx] [,DEVICE=xxxx] [,HDRINFO=YES] [,LABADDR=xxxxxxxx] [,MOUNTED=xxxxxx] [,XTNTXIT=xxxxxxxx]	Defines a Physical IOCS file
[name]	DTFPR	DEVADDR=SYSxxx ,IOAREA1=xxxxxxxx [,ASOCFLE=xxxxxxxx] [,BLKSIZE=nnn] [,CONTROL=YES] [,CTLCHR=xxx] [,DEVICE=nnn] [,ERROPT=xxxxxxxx] [,FUNC=xxxx] [,IOAREA2=xxxxxxxx] [,IOREG=(nn)] [,MODNAME=xxxxxxxx]	Defines a printer file

DATA MANAGEMENT AND SYSTEM CONTROL MACROS (. . . Cont'd)

Declarative Macros (Cont'd)

Name	Operation	Operands	Description
	DTFPR (Cont'd)	[,PRINTOV=YES] [,RDONLY=YES] [,RECFORM=xxxxxxx] [,RECSIZE=(nn)] [,SEPASMB=YES] [,STLIST=YES] [,TRC=YES] [,UCS=xxx] [,WORKA=YES]	
[name]	DTFPT	BLKSIZE=n [,DEVADDR=SYSnnn] [,IOAREA1=xxxxxxx] [,DELCHAR=X'nn'] [,DEVICE=nnnn] [,EOFADDR=xxxxxxx] [,EORCHAR=X'nn'] [,ERROPT=xxxxxxx] [,FSCAN=xxxxxxx] [,FTRANS=xxxxxxx] [,IOAREA2=xxxxxxx] [,IOREG=(nn)] [,LSCAN=xxxxxxx] [,LTRANS=xxxxxxx] [,MODNAME=xxxxxxx] [,OVBLKSZ=n] [,RECFORM=xxxxxxx] [,RECSIZE=(nn)] [,SCAN=xxxxxxx] [,SEPASMB=YES] [,TRANS=xxxxxxx] [,WLRERR=xxxxxxx]	Defines a paper tape file
[name]	DTFSD	BLKSIZE=nnnn [,EOFADDR=xxxxxxx] [,CISIZE=nnnn] [,DELETFL=NO] [,DEVADDR=SYSnnn] [,ERROPT=xxxxxxx] [,FEOVD=YES] [,HOLD=YES] [,IOAREA1=xxxxxxx] [,IOAREA2=xxxxxxx] [,IOREG=(nn)] [,LABADDR=xxxxxxx] [,PWRITE=YES] [,RECFORM=xxxxxxx] [,RECSIZE=(n r)] [,SEPASMB=YES] [,TRUNCS=YES] [,TYPEFLE=xxxxxxx] [,UPDATE=YES] [,VARBLD=(r)] [,VERIFY=YES] [,WLRERR=xxxxxxx] [,WORKA=YES]	Defines a sequential DASD file
[name]	DUMOD	ERREXT=YES [,ERROPT=YES] [,RDONLY=YES] [,SEPASMB=YES]	Defines a logic module for a diskette file
[name]	ISMOD	[,CORDATA=YES] [,CORINDX=YES] [,ERREXT=YES] [,HOLD=YES] [,IOAREA2=YES] [,IOROUT=LOAD ADD] [,RETRVE ADDRTR] [,RDONLY=YES]	Defines a logic module for an indexed sequential file

DATA MANAGEMENT AND SYSTEM CONTROL MACROS (. . .Cont'd)

Declarative Macros (Cont'd)

Name	Operation	Operands	Description
	ISMOD (Cont'd)	[,RECFORM=FIXUNB FIXBLK BOTH] [,RPS=SVA] [,SEPASMB=YES] [,TYPEFLE=RANDOM SEQNTL RANSEQ]	
[name]	MRMOD	[ADDRESS={SINGLE DUAL}] [,BUFFERS=nnn] [,SEPASMB=YES]	Defines a logic module for a MICR or OCR file
[name]	MTMOD	[ASCII=YES] [,CKPTREC=YES] [,ERREXT=YES] [,ERROPT=YES] [,NOTEPT={YES POINTS}] [,RONLY=YES] [,READ={FORWARD BACK}] [,RECFORM=xxxxxx] [,SEPASMB=YES] [,TYPEFLE=xxxxxx] [,WORKA=YES]	Defines a logic module for a magnetic tape file
[name]	ORMOD	[BLKFAC=YES] [,CONTROL=YES] [,DEVICE={1287D 1287T}] [,IOAREA2=YES] [,RECFORM={FIXUNB FIXBLK UNDEF}] [,SEPASMB=YES] [,WORKA=YES]	Defines a logic module for a 1287 or 1288 optical reader file
[name]	PRMOD	[CONTROL=YES] [,CTLCHR={YES ASA}] [,DEVICE=xxxxxx] [,ERROPT=YES] [,FUNC=xxxxxx] [,IOAREA2=YES] [,PRINTOV=YES] [,RONLY=YES] [,RECFORM=xxxxxx] [,SEPASMB=YES] [,STLIST=YES] [,TRC=YES] [,WORKA=YES]	Defines a logic module for a printer file
[name]	PTMOD	[DEVICE=nnnn] [,RECFORM=xxxxxx] [,SCAN=YES] [,SEPASMB=YES] [,TRANS=YES]	Defines a logic module for a paper tape file

DATA MANAGEMENT AND SYSTEM CONTROL MACROS (...Cont'd)

Imperative Macros

Name	Operation	Operands	Description
[name]	CCB	SYSnnn ,command-list-name [,X'nnnn'] [,senseaddress]	Defines an IOCS command control block
[name]	CHECK	{filename}(1) [,control-addr],(0)]	Prevents processing until I/O data transfer is complete
[name]	{CLOSE CLOSER}	{filename1}(r1) [,filename2](r2) [,...	Deactivates a file
[name]	CNTRL	{filename}(1) ,code [,n1][,n2]	Provides non-data device commands
[name]	DISEN	{filename}(1)	Stops feeding documents through MICR or OCR devices
[name]	DSPLY	{filename}(1) ,(r2),(r3)	Displays document field on 1287 display scope
[name]	ENDFL	{filename}(0)	Ends the mode initiated by SETFL
[name]	ERET	{SKIP IGNORE RETRY}	Returns control from your error-processing routine to IOCS
[name]	ESETL	{filename}(1)	Ends sequential mode initiated by SETL
[name]	EXCP	{blockname}(1) [,REAL]	Request PIOCS to start an I/O operation
[name]	FEOV	{filename}(1)	Forces end-of-volume for magnetic tape file
[name]	FEOVD	{filename}(1)	Forces end-of-volume for DASD file
[name]	GENIORB	CCW={name1}(S,name1)(r1) ,{DEVICE=SYSxxx LOGUNIT={name2}(S,name2)(r2)} [,ADDRESS={name3}(S,name3)(r3)] [,LENGTH=fieldlength] [,ECB={name4}(S,name4)(r4)] [,ERREXIT={name5}(S,name5)(r5)] [,FIXLIST={name6}(S,name6)(r6)] [,FIXFLAG={option1 1,...}] [,IOFLAG={option21,...}]	Generates an I/O Request Block at execution time
[name]	GET	{filename}(1) [,workname],(0)]	Obtains the next sequential logical record from an input file
[name]	IORB	DSECT=YES or CCW=name1,DEVICE=SYSxxx [,ECB=name2] [,FIXLIST=name3] [,FIXFLAG={option 11,...}] [,IOFLAG={option 21,...}]	Displays the I/O Request Block or Generates an I/O Request Block at assembly time
[name]	LBRET	{1 2 3}	Returns control to IOCS after label processing
[name]	LITE	{filename}(1) [,light-switches],(0)]	Lights pocket lamps on 1419 or 1275
[name]	NOTE	{filename}(1)	Obtains identification for a physical record or logical block
[name]	OPEN OPENR	{filename1}(r1) [,filename2](r2) [,...	Activates a file

DATA MANAGEMENT AND SYSTEM CONTROL MACROS (. . .Cont'd)

Imperative Macros (Cont'd)

Name	Operation	Operands	Description
[name]	POINTR	{filename}(1) ,{address}(0)	Repositions a file to a specified record
[name]	POINTS	{filename}(1)	Repositions a file to its beginning
[name]	POINTW	{filename}(1) ,{address}(0)	Repositions a file to a specified record
[name]	PRTOV	{filename}(1),{0 12} [,routinename],(0)	Specifies printer action when carriage overflow occurs
[name]	PUT	{filename}(1) [,workname],(0) [,STLSP={controlfield}(r1)] [,STLSK={controlfield}(r2)]	Moves (outputs) a logical record to I/O device
[name]	PUTR	{filename}(1) [,workname1](0) [,workname2](2)	Sends message to operator's console, requiring a reply
[name]	RDLINE	{filename}(1)	Reads a 1287 journal tape line in correction mode
[name]	READ	{filename}(1) {,SQ,{areal}(0)},{length},{r1},S} ,ID ,KEY ,OR,{name}(r2) ,DR,{name}(r3)nn,nn ,MR	Transfers data from an input file to an area in virtual storage
[name]	RELSE	{filename}(1)	Skip the remaining records in a block
[name]	RESCN	{filename}(1) ,(r1),(r2) [,n1],[n2]	Rescans a field on an OCR document
[name]	SECTVAL	[DDKR={name1}(0)] [,DVCTYP=name2]	Calculates the sector value for a CKD disk file record
[name]	SEOV	filename	Forces end-of-volume for a system file on tape
[name]	SETDEV	{filename}(1) ,{phasename}(r)	Changes 3886 format records
[name]	SETFL	{filename}(0)	Sets file-load mode in ISAM
[name]	SETL	{filename}(r1) ,{id-name}(r2) KEY BOF GKEY}	Sets sequential retrieval mode in ISAM
[name]	TRUNC	{filename}(1)	Writes a short block of records
[name]	WAIT	{blockname}(1)	PIOCS waits for an I/O operation to be completed before continuing
[name]	WAITF	{filename}(r1)},{filename2} ,(r2),...	LIICS waits for an I/O operation to be completed before continuing
[name]	WRITE	{filename}(1) {,{SQ UPDATE},{areal}(0) [,length},{r1}] ,AFTER[,EOF]} ,ID ,KEY ,NEWKEY ,RZERO}	Transfers a record from virtual storage to an output file

DATA MANAGEMENT AND SYSTEM CONTROL MACROS (...Cont'd)

System Control Macros

Name	Operation	Operands	Description
[name]	ASPL	[DSECT={NO YES}]	Generates a mapping DSECT for the ASSIGN macro
[name]	ASSIGN	ASPL={name1}(r1) SAVE={name2}(r2)	Assigns or releases tape drives dynamically
[name]	ATTACH	{entrypoint}(S,entrypoint) (r1) SAVE={savearea}(S,savearea) (r2) [ABSAVE={savearea}(S,savearea) (r3)] [ECB={ecbname}(S,ecbname) (r4)] [MFG={area}(S,area) (r5)]	Initiates a subtask
[name]	CALL	{entrypoint}(r15) [,parameterlist]	Passes control to a specified entry point in another program
[name]	CANCEL	[ALL]	Terminates a task or subtask
[name]	CDLOAD	{phasename}(1) [PAGE={NO YES}] [,RETPNF={NO YES}]	Loads a specified phase into the partition GETVIS area
[name]	CHAP		Lowers the priority of the issuing subtask
[name]	CHKPT	SYSnnn [,restart-addr](r1) [,end-addr](r2) [,tpointer](r3) [,dpointer](r4) [,filename](r5)	Records the status of your program for later restarting
[name]	COMRG	[REG=r]	Places the partition's communication region address into the specified register
[name]	CPCLOSE	[arglist](r1)	Issues a CPCLOSE command to VM/370 to release a print or punch file for output
[name]	DEQ	{rcbname}(0)	Releases an ENQed resource
[name]	DETACH	[SAVE={savearea}(1)]	Terminates (normally) a subtask
[name]	DTL	NAME=resource [,CONTROL={E S}] [,LOCKOPT={1 2}] [,KEEP={NO YES}] [,OWNER={TASK PARTITION}] [,SCOPE={INT EXT}]	Generates a DTL (Define The Lock) control block at assembly time
[name]	DUMP		Produces a hexadecimal dump
[name]	ENQ	{rcbname}(0)	Protects a resource
[name]	EOJ		Ends a job step or subtask
[name]	EXIT	[AB IT MR OC PC TT]	Returns control from your interrupt-checking routine
[name]	EXTRACT	ID={PUB BDY} AREA={name1}(S,name1) (r1) LEN={length}(r2) [MFG={name3}(r3)] [PID={name4}(S,name4) (r4)] [SEL={name5}(S,name5) (r5)] [DISP={name6}(S,name6) (r6)]	Displays unit information from the PUB table or partition boundaries
[name]	FCEPGOUT	{listname}(1) beginaddr,endaddr [,beginaddr,endaddr],...	Forces an area to be paged-out

DATA MANAGEMENT AND SYSTEM CONTROL MACROS (. . .Cont'd)

System Control Macros (Cont'd)

Name	Operation	Operands	Description
[name]	FETCH	{phasename}(S,addr) (1) [,entrypoint](S,entrypoint) (0) [,LIST={listname}(S,listname) (r1)] [,SYS=YES] [,DE=YES] [,MFG={area}(S,area) (r2)]	Loads a phase; transfers control to it
[name]	FREE	{filename}(1)	Makes a previously held track or CI available to other tasks
[name]	FREEVIS	[ADDRESS={name1}(1)] [,LENGTH={name2}(0)] [,SVA=YES]	Releases blocks of virtual storage previously obtained by a GETVIS
[name]	GENDTL	[ADDR={name1}(S,name1) (r1)] [,CONTROL={E S}] [,KEEP={NO YES}] [,LENGTH={NO YES}] [,LOCKOPT={1 2}] [,NAME={name2}(S,name2) (r2)] [,OWNER={TASK PARTITION}] [,SCOPE={INT EXT}]	Generates a DTL (Define The Lock) control block at execution time
[name]	GENL	phasename1,phasename2,... [,{ADDRESS={area}(S,area) (r1)} [,LENGTH=number] [,{ADDRESS={DYNAMIC DYN}} [,ERREXT={addr}(S,addr) (r2)}]]	Generates a local directory list in the partition
[name]	GETIME	[STANDARD BINARY TU] [,LOCAL GMT] [,MFG={area}(S,area) (r)]	Obtains the time of day
[name]	GETVIS	[ADDRESS={name1}(1)] [,LENGTH={name2}(0)] [,PAGE=YES] [,POOL=YES] [,SVA=YES]	Obtains a block of virtual storage from a GETVIS area
[name]	IJB PUB		Generates a mapping DSECT for the EXTRACT ID=PUB macro
[name]	JDUMP		Produces a hexadecimal dump; terminates the main or subtask
[name]	JOB COM	FUNCT={PUTCOM GETCOM}, AREA={address}(r1), LENGTH={length}(r2)	Permits communication between jobs or job steps in a partition
[name]	LFCB	SYSxxx,phasename [,NULMSG] [,FORMS=xxxx] [,LPI=n]	Loads the forms-control buffer
[name]	LOAD	{phasename}(S,address) (1) [,loadpoint](S,loadpoint) (0) [,LIST={listname}(S,listname) (r1)] [,SYS=YES] [,DE=YES] [,TXT=NO] [,MFG={area}(S,area) (r2)]	Loads specified phase; returns control to calling phase
[name]	LOCK	{name}(S,name) (r) [,FAIL={RETURN WAIT WAIT}]	Enqueues a resource access request with protection against disallowed usage
[name]	MAPBDY	[DSECT={NO YES}]	Generates a mapping DSECT for the EXTRACT ID=BDY macro
[name]	MAPPSID		Generates a mapping DSECT for the SUBSID macro

DATA MANAGEMENT AND SYSTEM CONTROL MACROS (. . . Cont'd)

System Control Macros (Cont'd)

Name	Operation	Operands	Description
[name]	MODDTL	ADDR={name1}(S,name1) (r1) [,CHANGE={ON OFF}] [,CONTROL={E S}] [,KEEP={NO YES}] [,LOCKOPT={1 2}] [,NAME={name2} (S,name2) (r2)] [,OWNER={TASK PARTITION}] [,SCOPE={INT EXT}]	Modifies a DTL (Define The Lock) control block
[name]	MVCOM	to,length,{from}(0)	Modifies communication region
[name]	PAGEIN	{{(listname)(1)} beginaddr, endaddr[,beginaddr,endaddr],...} [,FCB={ecbname}(0)]	Brings specified areas into real storage
[name]	PDUMP	{address}(r1),{address2}(r2) [,MFG={area}(S,area) (r3)]	Produces a snapshot hexadecimal dump; processing continues at next instruction
[name]	PFIX	{{(listname)(1)} beginaddr, endaddr[,beginaddr,endaddr],...}	Brings pages into real storage; fixes them
[name]	PFREE	{{(listname)(1)} beginaddr, endaddr[,beginaddr,endaddr],...}	Decrements a page's PFIIX counter by 1
[name]	POST	{ecbname}(1) [,SAVE={savearea}(0)]	Posts an ECB and removes a waiting task from the wait state
[name]	RCB		Generates a Resource Control Block
[name]	REALAD	{address}(1)	Returns a real storage address corresponding to a virtual address
[name]	RELEASE	(SYSnnn[,SYSnnn],...) [,savearea]	Releases programmer logical units
[name]	RELPAQ	{{(listname)(1)} beginaddr, endaddr[,beginaddr,endaddr],...}	Releases specified storage areas
[name]	RETURN	(r1[,r2])	Restores registers, returns control to calling program
[name]	RUNMODE		Returns mode information
[name]	SAVE	(r1[,r2])	Saves registers in savearea
[name]	SETIME	{timervalue}(1) [,tecbname[,r]],[,PREC]	Sets interval to specified value
[name]	SETPFA	[entryaddr](0)	Makes or breaks a linkage to a page fault appendage routine
[name]	SETT	{timervalue}(1)	Sets the task timer to the specified value
[name]	STXIT	{AB IT OC PC TT} [,rtnaddr](0) [,savearea](1) [,OPTION={DUMP NODUMP}]	Makes or breaks linkage from supervisor to your interrupt processing routine
[name]	SUBSID	INQUIRY ,NAME={name1}(S,name1) (r1) ,AREA={name2}(S,name2) (r2) ,LEN={length}(r3) [,LVLTEST={NO YES}] [,MFG={name4}(r4)]	Retrieves information about the supervisor
[name]	TECB		Generates a timer event control block
[name]	TESTT	[CANCEL]	Tests time elapsed from task timer set by SETT
[name]	TPIN		Deactivates partitions
[name]	TPOUT		Reactivates partitions
[name]	TTIMER	[CANCEL]	Tests time elapsed from interval timer set by SETIME

DATA MANAGEMENT AND SYSTEM CONTROL MACROS (. . .Cont'd)

System Control Macros (Cont'd)

Name	Operation	Operands	Description
[name]	UNLOCK	{(name (S,name) (r)) ALL}	Releases a resource that was enqueued by the LOCK macro
[name]	VIRTAD	{address}(1)	Returns virtual address corresponding to real address
[name]	WAIT	{ecbname}(1)	Sets a task into a wait state until an ECB is posted
[name]	WAITM	{ecb1,ecb2,... listname}(1)	Sets programs or tasks into wait state until ECBs are posted
[name]	XECBTAB	TYPE={DEFINE DELETE CHECK RESET DELETALL} ,XECB=xecbname [,XECBADR={xecbfield}(S,xecbfield) (r1)] [,ACCESS={XPOST XWAIT}] [,MFG={area (S,area) (r2)]	Defines or changes a cross-partition event control block
[name]	XPOST	XECB={xecbname}(1) ,POINTRG={14}	Posts a specified XECB
[name]	XWAIT	XECB={xecbname}(1) ,POINTRG={14}	Waits for a specified XECB to be posted

LIOCS MODULE NAME VERSUS OPTIONS

character # ➔	1	2	3	4	5	6	7	8
CDMOD	I	J	C	F RECFORM=FIXUNB (always for TYPEFLE=INPUT, TYPEFLE=CMBND or FUNC=I files) V RECFORM=VARUNB U RECFORM=UNDEF	A CTLCHR= ASA(not specified if CMBND) Y CTLCHR= YES C CONTROL= YES Z CTLCHR or CONTROL not specified	B RDNLY= YES and TYPEFLE= CMBND C TYPEFLE= CMBND H RDNLY= YES and TYPEFLE= INPUT I TYPEFLE= INPUT N RDNLY= YES and TYPEFLE= OUTPUT O TYPEFLE= OUTPUT	Z WORKA and IOAREA2 not specified W WORKA= YES I IOAREA2= YES B WORKA and IOAREA2 Z WORKA= YES not specified (CMBND file only)	0 DEVICE=2540,3881 1 DEVICE=1442,2596 2 DEVICE=2520 3 DEVICE=2501 4 DEVICE=2540 and CRDERR 5 DEVICE=2520 and CRDERR 6 DEVICE=3505 or 3504 7 DEVICE=3525 and FUNC=R/P or omitted 8 DEVICE=2560 and FUNC=R/P or omitted 9 DEVICE=5425 and FUNC=R/P or omitted A DEVICE=3525 and FUNC=RP B DEVICE=3525 and FUNC=RW C DEVICE=3525 and FUNC=PW D DEVICE=3525 and FUNC=I E DEVICE=3525 and FUNC=RPW F DEVICE=2560 and FUNC=RP

LIOCS MODULE NAME VERSUS OPTIONS (...Cont'd)

character # →	1	2	3	4	5	6	7	8
CDMOD (Cont'd)								G DEVICE=2560 and FUNC=RW H DEVICE=2560 and FUNC=PW I DEVICE=2560 and FUNC=I J DEVICE=2560 and FUNC=RPW K DEVICE=5425 and FUNC=RP L DEVICE=5425 and FUNC=RW M DEVICE=5425 and FUNC=PW N DEVICE=5425 and FUNC=I O DEVICE=5425 and FUNC=RPW
DIMOD	I	J	J	F always	C non-RPS version of module V RPS data set	B TYPEFLE=OUTPUT (processes both in put and output) I TYPEFLE=INPUT	I IOAREA2=YES Z IOAREA2=YES is not specified	C RDONLY=YES D RDONLY=YES is not specified
DRMOD	I	J	M	Z	S SETDEV=YES Z SETDEV=YES not specified	R RDONLY=YES Z RDONLY=YES not specified	D always	0 always
DUMOD	I	J	N	D always	I =DUMODFI O =DUMODFO	C ERROPT=YES and ERREXT=YES E ERROPT=YES Z neither is specified	Z always	Y RDONLY=YES Z RDONLY not specified

LIOCS MODULE NAME VERSUS OPTIONS (...Cont'd)

character # ➔	1	2	3	4	5	6	7	8
MRMOD	I	J	U	S Address=SINGLE D Address=DUAL	Z	Z	Z	Z
MTMOD (GET/PUT)	I	J	F	F RECFORM=FIXUNB (or FIXBLK) (EBCDIC mode) X RECFORM=FIXUNB (or FIXBLK) (ASCII mode) V RECFORM=VARUNB (or VARBLK) (EBCDIC mode) R RECFORM=VARUNB (or VARBLK) (ASCII mode) S RECFORM=SPNUNB (or SPNBLK) (spanned records) U RECFORM=UNDEF (EBCDIC code) N RECFORM=UNDEF (ASCII mode)	B READ=BACK Z READ=FORWARD or if READ is not speci fied	C CKPTREC=YES Z CKPTREC=YES is not specified	W WORKA=YES Z WORKA=YES is not specified	M ERREXT=YES and RDONLY=YES N ERREXT=YES Y RDONLY=YES Z ERREXT and RDON LY not specified
MTMOD (WORKFILE)	I	J	F	W always	E ERROPT=YES Z ERROPT is not specified	N NOTEPNT=YES S NOTEPNT=POINTS Z NOTEPNT is not specified	Z always	M ERREXT=YES and RDONLY=YES N ERREXT=YES Y RDONLY=YES Z ERREXT and RDON LY not specified

LIOCS MODULE NAME VERSUS OPTIONS (...Cont'd)

character # ➔	1	2	3	4	5	6	7	8
ORMOD	I	J	M	F RECFORM=FIXUNB X RECFORM=FIXBLK U RECFORM=UNDEF D RECFORM=UNDEF and BLKFA C=YES	C CONTROL=YES Z CONTROL=YES is not specified	I IOAREA2=YES W WORKA=YES B both are specified Z neither is specified	T device is in tape mode D device is in docu- ment mode	Z always
PRMOD	I	J	D	F RECFORM=FIXUNB V RECFORM=VARUNB U RECFORM=UNDEF	A CTLCHR=ASA Y CTLCHR=YES C CONTROL=YES S STLIST=YES Z none of these is spe- cified T DEVICE=3525 with 2-line printer U DEVICE=2560 V DEVICE=5425	B ERROPT=YES and PRINTOV=YES P PRINTOV=YES, DEVICE is not 3525 and ERROPT is not specified I PRINTOV=YES, DEVICE=3525 and FUNC=WET] or omitted F PRINTOV=YES, DEVICE=3525 and FUNC=RW[T] C PRINTOV=YES, DEVICE=3525 and FUNC=PW[T] D PRINTOV=YES, DEVICE=3525 and FUNC=RPW[T] Z PRINTOV=YES and ERROPT not speci- fied and DEVICE is not a 3525	I IOAREA2=YES Z IOAREA2=YES is not specified	V RDONLY=YES and WORKA=YES W WORKA=YES Y RDONLY=YES Z neither is specified

LIOCS MODULE NAME VERSUS OPTIONS. (...Cont'd)

character # ➔	1	2	3	4	5	6	7	8
PRMOD (Cont'd)						O PRINTOV=YES not specified, DEVICE=3525 and FUNCT=WCT] or omitted R PRINTOV=YES not specified, DEVICE=3525 and FUNCT=RWCT] S PRINTOV=YES not specified, DEVICE=3525 and FUNCT=PWCT] T PRINTOV=YES not specified, DEVICE=3525 and FUNCT=RPWCT] E ERROPT=YES and PRINTOV=YES is not specified U FUNC=W or omitted and DEVICE=2560 or 5425 V FUNC=RW and DEVICE=2560 or 5425 W FUNC=PW and DEVICE=2560 or 5425 X FUNC=RPW and DEVICE=2560 or 5425		

LIOCS MODULE NAME VERSUS OPTIONS (...Cont'd)

Character # →	1	2	3	4	5	6	7	8
PTMOD	I	J	E	S SCAN=YES Z SCAN=YES is not specified	T TRANS=YES (SCAN=YES is not specified) Z TRANS=YES is not specified	F RECFORM=FIXUNB and SCAN=YES U RECFORM=UNDEF and SCAN=YES Z SCAN=YES is not specified and/or DEVICE=1018	1 DEVICE=1017 2 DEVICE=1018 Z DEVICE=2671 or if this entry is omitted	Z always
ISMOD	I	J	H	A RECFORM=BOTH, IOROUT=ADD or ADDRTR B RECFORM=FIXBLK, IOROUT=ADD or ADDRTR U RECFORM=FIXUNB, IOROUT=ADD or ADDRTR Z RECFORM is not specified (IOROUT=LOAD or RETRVE)	A IOROUT=ADDRTR (non-RPS version of module) I IOROUT=ADD L IOROUT=LOAD (non-RPS version of module) R IOROUT=RETRVE V IOROUT=ADDRTR (RPS version of module) X IOROUT=LOAD (RPS version of module)	B TYPEFLE=РАНSEQ G IOAREA2=YES TYPEFLE=SEQNTL or IOROUT=LOAD R TYPEFLE=RANDOM S TYPEFLE=SEQNTL Z neither is specified (IOROUT=LOAD or ADD)	B CORINDX=YES and HOLD=YES C CORINDX=YES O HOLD=YES Z neither is specified	F CORDATA=YES, ERREXT=YES, RDONLY=YES G CORDATA=YES and ERREXT=YES O CORDATA=YES and RDONLY=YES P CORDATA=YES S ERREXT=YES and RDONLY=YES T ERREXT=YES Y RDONLY=YES Z neither is specified

DTFCD (Reader)

Bytes		Bits	Contents	Function
Dec	Hex			
0-15	00-0F			CCB
8	8			1=2501 double - CCW support
16	10	0		1=OMR ¹⁾ ; 0=Omitted
		1		1=ERROPT ²⁾ ; 0=Omitted
		2		COBOL open; ignore option
		3		1=GET issued ³⁾ ; 0=GET not issued ⁷⁾
		4		DTF table address constants relocated by OPENR
		5-7		File association: 000=READ only 010=READ/PRINT ⁴⁾ 101=READ/PUNCH/PRINT ⁵⁾ 001=READ/PUNCH ⁵⁾
17-19	11-13			Address of logic module
20	14		X'02'	DTF type
			X'05'	DTF type for 2560 or 5424/5425
21	15	0		1=Open; 0=Closed
		1		First time switch
		2		1=1442 or 2596; 0=Other
		3		1=2560, 3525 or 5424/5425; 0=Other
		4		1=3504, 3505; 0=Other
		5		1=2 I/O areas; 0=1 I/O area
		6		1=2520; 0=Other
		7		1=2540; 0=Other
22	16		B'SSF0X010'	Normal command code (not for 2560 or 5424/5425): SS: 00=pocket 1; 01=pocket 2; 10=pocket 3 ⁶⁾ F: 1=Column binary ³⁾ ; 0=EBCDIC X: 1=OMR or RCE ³⁾ ; 0=Neither
			B'H0B00010'	Read command code (2560): H: 0=hopper 1; 1=hopper 2 B: 0=EBCDIC; 1=column binary
			B'HMMM0011'	SS command code (5424/5425) H: 0=hopper 1; 1=hopper 2 MMM: 001=stacker 1; 010=stacker 2; 011=stacker 3; 100=stacker 4
23	17		B'H0B00010'	Control command code (not for 2560 or 5425)
			B'HMMM0011'	Read command code (2560) SS command code (5424/5425) H: 0=hopper 1; 1=hopper 2 MMM: 001=stacker 1; 010=stacker 2; 011=stacker 3; 100=stacker 4
24-27	18-1B			Address of IOAREA2. (If IOAREA2 is not specified, address of IOAREA1.)
28	1C	0		1=2560; 0=Other
		1		1=5424/5425; 0=Other
		2-7		Not used
29-31	1D-1F			Address of EOF routine
32-39	20-27			Read CCW (2560). Stacker select CCW (5424/5425).
Bytes 40-49 as used for all files except 2560 and 5424/5425 files				
40-43	28-2B		LA &IOREG, 0(14) NOP 0	Load user pointer register

DTFCD (Reader) (. . .Cont'd)

Bytes		Bits	Contents	Function
Dec	Hex			
44–49	2C–31		MVC 0 (&BLKSIZE,13), 0(14) NOP 0 DC X'0000'	Move IOAREA to WORKA
The following bytes (50–105) are used for 2501 double-CCW support.				
50–55	32–37			Unused CCB
56–71	38–47			
72	48	0 1 2 3 4 5–7		1=OMR ¹⁾ ; 0=omitted 1=ERROPT ²⁾ ; 0=omitted COBOL open; ignore option 1=GET issued ³⁾ ; 0=GET not issued ⁷⁾ DTF table address constants relocated by OPENR <u>File Association</u> 000=READ only 010=READ/PRINT ⁴⁾ 101=READ/PUNCH/PRINT ⁵⁾ 001=READ/PUNCH ⁵⁾
73–75	49–4B			Address of logic module
76	4C		X'02' X'05'	DTF type DTF type for 2560 or 5424/5425
77	4D	0 1 2 3 4 5 6 7		1=open; 0=closed First time switch 1=1442 or 2596; 0=other 1=2560, 3525, or 5424/5425; 0=Other 1=3504 or 3505; 0=Other 1=2 I/O areas; 0=1 I/O area 1=2520; 0=Other 1=2540; 0=Other
78	4E		B'SSFOX010' B'H0B00010'	Normal command code (not for 2560 or 5424/5425) SS: 00=pocket 1; 01=pocket 2; 10=pocket 3 ⁶⁾ F: 1=column binary ³⁾ ; 0=EBCDIC X: 1=OMR or RCE ³⁾ ; 0=Neither Read command code (2560, 5424/5425) H: 0=hopper 1; 1=hopper 2 B: 0=EBCDIC; 1=column binary
79	4F		B'H0B00010'	Control command code (not for 2560 or 5424/5425)
80–83	50–53		B'H0B00010'	Read command code (2560, 5424/5425)
84	54	0 1 2–7		Address of IOAREA2. (If IOAREA2 is not specified, address of IOAREA1.) 1=2560; 0=Other 1=5424/5425; 0=Other Not used
85–87	55–57			Address of EOF routine
88–95	58–5F			Read CCW

DTFCD (Reader) (. . . Cont'd)

Bytes		Bits	Contents	Function
Dec	Hex			
96-99	60-63		LA &IOREG, 0(14) NOP 0	Load user pointer register
100-103	64-67		MVC 0 (&BLKSIZE,13), 0(14) NOP 0	Move IOAREA to WORKA
104-105	68-69		DC X'0000'	
The following bytes (50-57) are used for 3504, 3505, and 3525 associated files				
50-53	32-35		DCA (name) B 16(15) B 20(15) DC F'0'	If ERROPT=name ²¹ If ERROPT=SKIP If ERROPT=IGNORE If ERROPT=omitted
54-57	36-39		DC A(ASOCFLE)	Address of associated DTF table ⁷¹ (3525 only)
Bytes 40 onward as used for 2560 and 5425 files				
40-47	28-2F			Stacker select CCW (2560 Read CCW (5424/5425)
48-51	30-33		LA &IOREG, 0(14) NOP 0	
52-57	34-39		MVC 0 (&BLKSIZE,13), 0(14) NOP 0 DC X'0000'	Move IOAREA to WORKA
58-63	3A-3F		CLC 0 (L,14), 64(1)	Test for end of file L=4 if MODE=C; L=2 in other cases
64-67	40-43		DC C/'* ' DC X'0C001022'	End-of-file indicator if MODE=E In other cases
68-71	44-47		DC A(name) B 16(15) B 20(15) DC F'0'	If ERROPT=name ²¹ If ERROPT=SKIP If ERROPT=IGNORE If ERROPT=omitted
72-75	48-4B		DC A(ASOCFLE)	Address of associated DTF table ⁷¹
76-81	4C-51		MVC 0 (&BLKSIZE,14), 82(1)	Move card image to IOAREA1
82	52		DC &BLKSIZE.C'	Buffer for card image

¹¹ OMR only for 3504 and 3505

²¹ ERROPT for 2560, 3504, 3505, 3525, or 5424/5425 READ FILE

³¹ 3504, 3505, and 3525 with or without CONTROL=YES specified

⁴¹ 2560, 3525, or 5424/5425 with or without CONTROL=YES specified

⁵¹ 2560, 3525, or 5424/5425 without CONTROL=YES specified

⁶¹ Defaults to pocket 2 for 3504, 3505, and 3525

⁷¹ Present only when 2560, 3525, or 5424/5425 associated files are specified for the input DTF

DTFCD (Punch)

Bytes		Bits	Contents	Function
Dec	Hex			
0–15	00–0F			CCB
16	10	0 1 2 3 4 5–7		Not used 1=ERROPT ³ ; 0=Omitted COBOL open; ignore option 1=PUT issued ² ; 0=PUT not issued DTF table address constants relocated by OPENR File Association: 000=PUNCH only 011=PUNCH/PRINT ³ 001=READ/PUNCH ³ 101=READ/PUNCH/PRINT ³ 100=PUNCH/INTERPRET ³
17–19	11–13			Address of logic module
20	14		X'04'	DTF type
21	15	0 1 2 3 4 5 6 7		1=Open; 0=Closed First time switch 1=CTLCHR 1=Fixed unblocked 1=Variable unblocked 1=2 I/O areas 1=Workarea 1=2 CCWs in table; 0=1 CCW in table
22	16		B'SSF00001'	Normal command code: SS: 00=pocket 1; 01=pocket 2; 10=pocket 3 ⁴ F: 1=column binary; 0=EBCDIC
			B'HSS0011'	Normal stacker select command code (2560 or 5424/5425) H: 0=hopper 1; 1=hopper 2 SSS: stacker information
23	17		B'HSS0011'	Control command code (not for 2560 or 5424/5425) Actual stacker select command code (2560 or 5424/5425)
24–27	18–1B		DC A (IOAREA1+x)	Address of data in IOAREA1
28–31	1C–1F			Bucket ¹
32–33	20–21		LR 12, (RECSIZE) NOPR 0	Undefined records only
34–37	22–25		LA &IOREG, 4(14) NOP 0	Load user pointer register
38	26	0–2 3 4 5 6 7		Not used 1=5424/5425 1=2560 1=3525 1=1442 or 2596 1=2520B1
39	27		DC C ' '	Blank for eject last card

DTFCD (Punch) (...Cont'd)

Bytes		Bits	Contents	Function
Dec	Hex			
For all files except 2560 and 5425 files:				
40-47	28-2F			Punch CCW
48-55	30-37			Eject CCW for last card if 2520
For 2540 files if CRDERR is specified				
48-55	30-37			Retry CCW
56-135	38-87		DC CL80' '	Save area card image
For 3525 PUNCH/INTERPRET files				
48-55	30-37			Load CCW
56-63	38-3F			Print CCW
64-127	40-7F		DC 64C' '	Print buffer
For 3525 Associated files				
48-51	30-33		DC A(ASOCFLE)	Pointer to associated file
For 2560 and 5424/5425 files				
40-47	28-2F		DC D'0'	Eject CCW If FUNC=RP or RPW
48-55	30-37			Stacker select CCW
56-63	38-3F			Punch and Feed CCW
For 2560 PUNCH/INTERPRET files				
64-71	40-47			Load print head buffer 1 CCW
72-79	48-4F			Load print head buffer 2 CCW
80-87	50-57			Print CCW
88-151	58-97		DC 64C' '	Save area for printing line 2
For 5424/5425 PUNCH/INTERPRET files				
64-71	40-47			Print CCW
For 2560 and 5424/5425 Associated files				
64-67	40-43		DC A(ASOCFLE)	If mode is EBCDIC If mode is Column Binary Buffer for card image
68	44		DC C' '	
69-	45-		DC X'00'	
			DC &BLKSIZE.C' '	

¹⁾ The bucket bytes handle undefined length records

²⁾ Valid for 2560, 3525 READ/PUNCH, PUNCH/PRINT, and READ/PUNCH/PRINT files

³⁾ Valid for 2560, 3525

⁴⁾ Defaults to pocket 2 for 3525

DTFCD (Combined Reader/Punch)

Bytes		Bits	Contents	Function
Dec	Hex			
0 -15	00-0F			CCB
16	10	0-1		Not used
		2		COBOL open; ignore option
		3		Not used
		4		OPENR relocates DTF address constants
		5-7		Not used
17-19	11-13			Address of logic module
20	14		X'00'	DTF type
21	15			Command code (X'02' for 1442, X'C2' for 2520, 2540)
22	16			Command code (X'01' for 1442, X'09' for 2520, 2540)
23	17			Command code (X'01' for 1442, X'09' for 2520, 2540)
24-31	18-1F			CCW
32-35	20-23			Input area address
36-39	24-27			Output area address
40-41	28-29			Input blocksize
42-43	2A-2B			Output blocksize
44-49	2C-31		MVC 0 (&BLKS, 13), 0(14)	
50-55	32-37		MVC 0 (&OUBL, 14), 0(13)	
56-59	38-3B			End-of-file address
60-67	3C-43			Save area
68-73	44-49		MVC 1 (&OUBL-1, 13), 0(13)	
74-77	4A-4D		MVI 0(13), X'40'	
78-79	4E-4F			Constant (blanks)
80-83	50-53			Constant address (bytes 78-79)

DTFPR

Bytes		Bits	Contents	Function
Dec	Hex			
0-15	00-0F			CCB. If 3800 extended buffering is selected, the CCW address is changed by OPEN to point to a DTF extension work area in the user virtual area. CLOSE restores it.
16	10	0 1 2 3 4 5-7		1=2-line printer ^(3,4) ; 0=Other 1=ERROPT ^(3,4) ; 0=Omitted COBOL open; ignore option 1=3525; 0=Other OPENR relocates DTF address constants 3525 Modes: 000=PRINT only 011=PUNCH/PRINT ⁽³⁾ 010=READ/PRINT ⁽³⁾ 101=READ/PUNCH/PRINT ⁽³⁾ 3800 Modes: (Bit 7 not used) 11 = TRC=YES specified on DTF ⁽⁷⁾ 01 = TRC=Y specified via SETPRT (set by OPEN) ⁽⁷⁾
17-19	11-13			Address of logic module. If 3800 extended buffering is selected, OPEN changes this address to point to extended buffering logic module IJDPR3 in system virtual area. CLOSE restores it.
20	14		X'08' X'07'	DTF type DTF type for 2560 and 5424/5425
21	15	0 1 2 3 4 5 6 7		1=Open; 0=Closed First time switch 1=Control character 1=Fixed unblocked records 1=Variable unblocked records 1=2 I/O areas 1=Workarea 1=Print overflow channel 9
For Printer and Card Punch devices				
22	16		X'09'	Normal command code ⁽⁵⁾
23	17		X'09'	Control command code ⁽⁵⁾
24-27	18-1B		DC A (IOAREA 1+x)	Address of data in IOAREA 1
28-31	1C-1F			Bucket ⁽¹⁾
32-33	20-21		LR 12, (RECSIZE) NOPR 0	For undefined records only
34-37	22-25		LA & IOREG, 4(14) NOP 0	Only if IOREG=(r)
38-39	26-27			Bucket ⁽²⁾
40-47	28-2F		11, *, X'60', 1 9, IOAREA, X'20', 121	CCW - Set up Selective Tape List Control ⁽⁶⁾ STLIST not specified
48-55	30-37		9, IOAREA, X'20', 121 A (Name) DC A (ASOCFLE)	CCW - STLIST specified ⁽⁶⁾ Address of user error routine (for all the 3211-compatible printers identified by device type code PRT1) If ASOCFLE=filename ⁽³⁾

DTFPR (. . . .Cont')

Bytes		Bits	Contents	Function
Dec	Hex			
For the 2560 and 5424/5425 Multi Function Card Machine				
22	16		X'00'	Not used
23	17		B'HHHHHH00'	Print head selection byte H=1 specifies the corresponding head
24-27	18-1B			Address of IOAREA 1
28-31	1C-1F			Bucket
32-33	20-21		LR 12, (RECSIZE) NOPR 0	For undefined records only
34-37	22-25		LA & IOREG, 4(14) NOP 0	Only if IOREG=(r)
38-39	26-27			Number of bytes to be printed by the last specified print head
40-43	28-2B		DC A (ASOCFLE) DC F'0'	If FUNC=RW, PW or RPW In all other cases
44	2C	0 1 3 4-7		1=2560 Not used 1=Print control switch for 2560 associated files Not used
45-47	2D-2F		DC 3X'00'	Reserved for future use
For 2560 simple files				
48-55	30-37			Eject CCW
56-63	38-3F			Load print head buffer CCW
64-71	40-47			Print CCW
For 2560 associated files				
48-55	30-37			Load print head buffer CCW
56-63	38-3F			Print CCW
For 5424/5425 files				
48-55	30-37			Print CCW

- 1) The bucket bytes handle undefined records. Bit 0 of byte 28 at open time determines the mode set of a printer with UCS. If bit 0=1, the mode is set so that data checks occur if an invalid character is printed. Otherwise, mode is set to suppress data checks. The use of the UCS parameter determines the setting of this bit. If STLST=YES, byte 31 saves the STLST control byte provided by the PUT macro.
- 2) The 2 byte bucket saves print overflow conditions if CTLCHR=ASA. If STLST=YES, byte 38 contains the current STLST control byte. Byte 39 is set by the PUT macro to indicate spacing or skipping. (X'00' no spacing, no skipping; X'01' spacing; X'02' skipping.)
- 3) Valid vor 3525 READ/PRINT, PUNCH/PRINT and READ/PUNCH/PRINT files.
- 4) Valid for 3525 PRINT only files.
- 5) X'05' for 3525; X'09' for other devices.
- 6) Valid for 1403 only.
- 7) Valid for 3800 only.

DTFCN

Bytes		Contents	Function
Dec	Hex		
0 - 15	00-0F		CCB
16	10	X'20' X'08'	COBOL open; ignore option DTF table address constants re-located by OPENR
17-19	11-13		Address of logic module: GET and PUT logic if TYPEFLE=INPUT; PUT logic if TYPEFLE=OUTPUT; GET, PUT and PUTR logic if TYPEFLE= CMBND
20	14	X'03'	DTF type
21-23	15-17		For input and output: not used For combined: byte 21 contains X'01' and bytes 22-23 contain INPSIZE
24-31	18-1F	X'09', IOAREA1, X'00', BLKSIZE	CCW
End of table if RECFORM=FIXUNB and WORKA not specified. The following bytes are added if WORKA is specified.			
32-35	20-23	DC A(IOAREA1)	Address of I/O area
36-39	24-27	DC F'0'	Register save area
40-43	28-2B	DC F'0'	Register save area
.End of table if RECFORM=FIXUNB. The following bytes are added if RECFORM=UNDEF			
		DC F'0'	Register save area
		DC F'0'	Register save area
		DC H'BLKSIZE'	I/O area size
		DC AL2(BLKSIZE-1)	For input files only
The following bytes are added to the table if TYPEFLE= CMBND			
32-35	20-23	DC A(IOAREA1+BLKSIZE)	I/O area address for input
36-37	24-25	DC H'BLKSIZE'	Blocksize

DTFDR

Bytes		Bits	Contents	Function
Dec	Hex			
0-15	00-0F			CCB
16	10	0-1		Not used
		2		COBOL open; ignore option
		3		Not used
		4		OPENR relocates DTF table addresses
		5-7		Not used
17-19	11-13			Address of logic module
20	14		X'CO'	DTF type
21	15			PIOCS switches:
		0		1=open; 0=closed
		1	B'1'	Input
		2-5	B'0000'	Not used
		6	B'1'	Device is 3886
		7	B'0'	Not used
22	16			Not used
23	17			LIOCS switches:
		0-4	B'00000'	Not used
		5		1=SETDEV
		6		1=Control passed to COREXIT
		7		1=FR loaded from disk
24-31	18-1F			FR phasename at open time
32-39	20-27			Phasename of currently used FR
40-43	28-2B		X'00000000'	Not used
44-47	2C-2F			Start address of FR area in DTF
48-51	30-33			Address of four-byte pointer at the end of the FR area in the DTF
52-55	34-37			EOF routine address
56-63	38-3F			Scan CCW
64-71	40-47			Read CCW
72-79	48-4F			Control CCW
80-87	50-57			Load format record CCW
88-91	58-5B			COREXIT routine address
92-95	5C-5F			IOAREA1 area address
96-99	60-63			Header area address
100-103	64-67			Exit indicator address
104	68			Start of DR area
105-107	69-6B			Header area address
108-111	6C-6F			Exit indicator address
112	70			Start of FR area

DTFOR

Bytes		Bits	Function
Dec	Hex		
0 -15	00-0F		Dummy CCB
16	10	0-1	Not used
		2	COBOL open; ignore option
		3	Not used
		4	DTF table address constants relocated by OPENR
		5-7	Not used
17-19	11-13		Address of logic module
20	14		DTF type, (X'09')
			DTF type, (X'0A' if HEADER= YES)
21	15		PIOCS switches:
		0	1= Open; 0= closed
		1	1= Input
		2	1= Control
		3	1= Device is 1287
		4	1= Header
		5	Reserved for future use
		6	1= RDLNE
7	Not used		
22	16		Not used
23	17	0-6	Not used
		7	1= LIOCS posts a hopper empty condition to DTF
24-39	18-27		CCB
40-47	28-2F		Sense CCW
48-51	30-33		Lost lines (equipment check)
52-55	34-37		After 9 retries for journal tape, or after 2 retries for documents
56-59	38-3B		Wrong length records
60-63	3C-3F		After 4 retries for journal tape, or after 2 retries for documents
64-67	40-43		Keyboard corrections
68-71	44-47		Count of data check errors
72-75	48-4B		Lines marked
76-79	4C-4F		Total lines read (CCW chains executed)
80	50		Error indicators:
		0	1= EOP
		1	1= Lost reference mark indicator
		2	1= Late stacker selection
		3	1= Non-recovery error
		4	1= Equipment check
		5	1= Wrong length record
		6	1= Hopper empty
7	1= Data check		
81	51		LIOCS switches:
		0	1= First time
	1	1= 2 I/O areas	

DTFOR (....Cont'd)

Bytes		Bits	Function
Dec	Hex		
81 (Cont'd)		2 3 4 5-7	1= WORKA= YES 1= RECFORM= FIXUNB 1= RECFORM= UNDEF Not used
82	52		Normal command code
83	53		Control command code
84-87	54-57		IOAREA2 address
88-95	58-5F		Read CCW
96-103	60-67		Go to next line CCW
104-111	68-6F		Control CCW
112-115	70-73		EOF address
116-119	74-77		Correction exit address
120-123	78-7B		IOAREA1 address
124-127	7C-7F		DC A(&BLKS-1)
128-129	80-81		SR 13, &RECS
130-131	82-83		LR &RECS, 13
132-133	84-85		LR &IOR, 13
134-135	86-87		Sense

DTFMR

Bytes		Bits	Function
Dec	Hex		
0-5	00-05		CCB indicators
6-7	06-07		Logical class and unit numbers (primary if DUAL addressing)
8	08		Zero
9-11	09-0B		CCW address
12-15	0C-0F		Zeros
16	10	0-1	Not used
		2	COBOL open; ignore option
		3	Not used
		4	DTF table address constants relocated by OPENR
		5-7	Not used
17-19	11-13		Address of logic module
20	14		DTF type= X'0B'
21	15	Logic module option switches:	
		0	User disengage 0= off; 1= on
		1	Program sort mode 0= no; 1= yes
		2	First time switch (after engage) 0= no; 1= yes
		3	Addressing= DUAL 0= no; 1= yes
		4	Waiting 0= no; 1= yes
		5	Read logic indicator 0= no; 1= yes
		6	Not used
7	Supervisor initial read (after open) 0= no; 1= yes		
22-29	16-1D		Symbolic filename
30	1E	0	Open/Close option switch:
			0= closed; 1= open
31-33	1F-21		Open/Close option switches
34-35	22-23		Logic module option switches
36-39	24-27		Error information status
40-41	28-29		Length of DTF table
42-43	2A-2B		Device type indicator
44-45	2C-2D		Record type
46-49	2E-31		Reserved for future use
50-51	32-33		I/O register
52-55	34-37		End-of-file address
56-59	38-3B		IOAREA2/1 address
60-63	3C-3F		Document buffer size
64-65	40-41		Blocking factor/Number of buffers
66-67	42-43		I/O area size
68-71	44-47		Record length
72-76	48-4C		Sense information

DTFMR (. . . Cont'd)

Bytes		Bits	Function
Dec	Hex		
77	4D		Supervisor switch
78-79	4E-4F		Logical class and unit numbers (secondary, for DUAL addressing only)
80-81	50-51		Register alignment bytes
82-83	52-53		Logical class and unit numbers (primary, for DUAL addressing)
84-87	54-57		Document buffer size
88	58		Command code (4C)
89-91	59-5B		Address of last byte of first document buffer
92	5C		Command code (4C)
93-95	5D-5F		Address of last byte of last document buffer
96-99	60-63		Stacker select routine address
100-103	64-67		Address of stacker select CCW chain
104-107	68-6B		Current buffer address pointer (Supervisor)
108-111	6C-6F		Supervisor count
112-113	70-71		Number of buffers minus 7
114-115	72-73		Message indicator
116-119	74-77		ERROPT routine address
120-121	78-79		Logical class and unit numbers (secondary, for DUAL addressing only)
122-123	7A-7B		Reserved for future use
124-127	7C-7F		Address of last buffer given to user
128-131	80-83		Address of first byte of last buffer
132-139	84-8B		Channel status word (CSW)
140-143	8C-8F		Address of active GET record
144-147	90-93		GET counter
148-159	94-9F		Reserved for future use
For single addressing			
160-167	A0-A7		CCW - Engage
168-175	A8-AF		CCW - Read
176-183	B0-B7		CCW - Sense
184-191	B8-BF		CCW - NOP
192-199	C0-C7		CCW - Stacker select
200-207	C8-CF		CCW - TIC
208-215	D0-D7		CCW - Control
216-223	D8-DF		CCW - BN

DTFMR (. . . .Cont'd)

Bytes		Bits	Function
Dec	Hex		
224-231	E0-E7		CCW - Read
232-239	E8-EF		CCW - Sense
240-247	F0-F7		CCW - Disengage
For DUAL Address Adapter			
160-167	A0-A7		CCW - Engage
168-175	A8-AF		CCW - Read buffer 1
176-183	B0-B7		CCW - Sense
184-191	B8-BF		CCW - NOP
192-199	C0-C7		CCW - Read buffer 2
200-207	CB-CF		CCW - MOD Sense
208-215	D0-D7		CCW - Read buffer 1
216-223	DB-DF		CCW - MOD Sense
224-231	E0-E7		CCW - TIC to NOP
232-239	E8-EF		CCW - NOP
240-247	F0-F7		CCW - MOD CTL
248-255	F8-FF		CCW - Stacker select
256-263	100-107		CCW - MOD Sense

DTFMT (Data Files)

Bytes		Bits	Contents*	Function	Record Format
Dec	Hex				
0 -15	00-0F			CCB	
8	08		Input: X'00'- X'63' Output: X'00'- X'04' (variable) X'00' (undefined)	Buffer offset length, ASCII	
16	10	0		First time entered MTMOD for a file	
		1		Not used	
		2		COBOL open; ignore option	
		3		American National Standard COBOL	
		4		DTF table address constants relocated by OPENR	
		5		1= spanned records	
		6		1= ASCII - 0= EBCDIC	V-V, S
		7		ASCII input: 1= Length check ASCII output: 1=Buffer (offset length=4)	V V
17-19	11-13			Address of logic module	
20	14		X'11' X'12' X'13' X'14'	Nonstandard or unlabeled Standard labeled, output Standard labeled, input, backwards Standard labeled, input, forwards	
21	15	0		First time switch: 1= not first-time entry 0= first-time entry	
		1		1= blocked 0= unblocked	
		2		1= 2 I/O area's 0= 1 I/O area	
		3		1= workarea 0= no workarea	F, U, V
		4		0= workarea, spanned 1= input 0= output	F, U, V
		5		1= backwards 0= forwards	S
		6		1= checkpoint 0= no checkpoint	
		7		1= TRUNC required during Close	
22-29	16-1D			Symbolic filename	
30	1E			Same as command code in CCW; (X'01', X'02' or X'0C')	
31	1F	0-4		Bits 0-4 are used as displacements by OPEN to determine the location of variable fields of the DTF.	

DTFMT (Data Files) (....Cont'd)

Bytes		Bits	Contents *	Function	Record Format
Dec	Hex				
31 (Cont'd)	1F		B'01110'	Input	F
			B'01100'	Output	F
			B'10001'	Input	V
			B'01111'	Output	V
			B'01101'	Input	U
			B'01011'	Output	U
			5	1= Tape label information included in DTF (see bytes 88-95) 0= Tape label information not included in DTF	
	6	Used by COBCL			
	7	1= Header label and EOF information wanted 0= No header label and EOF information wanted			
32	20	0	Standard labels: 1= yes; 0= no		
		1	Labels: 1= nonstandard; 0= unlabeled		
		2	Rewind unload: 1= yes; 0= no		
		3	Rewind option: 1= no rewind; 0= rewind		
		4	Drive direction: 1= backwards; 0= forwards		
		5	User label address: 1= yes; 0= no		
		6	Tapemark option: 1= no; 0= yes		
	7	EOF-EOV switch (used by IBM SORT): 1= yes; 0= no			
33-35	21-23		User label routine address		
36	24	0	DTFPH: 1= yes; 0= no		
		1	COBOL indicator: 1= yes; 0= no		
		2	File type: 1= input; 0= output		
		3	FEOV switch: 1= yes; 0= no		
		4	EOF-EOV switch (output): 1= EOF 0= EOV		
		5	Open indicator: 1= open; 0= closed		
		6	1= variable or spanned records		V, S
	7	1= undefined records		U	
37-39	25-27		EOF address		
40-43	28-2B		Block count		
44-47*	2C-2F		BXH 11, 12, 24(15)	Forward	F
			BXLE 11, 12 24(15)	Backward	F
			L &VARBLD, DEBLOCKER	If VARBLD parameter is used	V
			NOP 0(0)		S
			DC F'0'	DEBLOCKER1	U

DTFMT (Data Files) (...Cont'd)

Bytes		Bits	Contents*	Function	Record Format
Dec	Hex				
48-51	30-33		LA 14, 1(14) BCTR 14, 0 + NOPRO	Backward	F, V, S F, V, S
			L &RECSIZE, DEBLOCKER1 NOP 0(0)	If RECSIZE given For input if not NOP	U U
52-55	34-37		L &IOREG, DEBLOCKER1	If IOREG specified	F
			L &IOREG, DEBLOCKER5	If IOREG specified	V
			L &IOREG, DEBLOCKER2 NOP 0(0)	If IOREG specified If no IOREG	U S
			L &RECSIZE, IJFVSREC	If spanned input	S
			ST &RECSIZE, IJFVSREC	If spanned output	S
56-63	38-3F			CCW	
64-67	40-43		DC A(IOAREA1)	One I/O area	
			DC A(IOAREA1 +BLKSIZE-1)	One I/O area, read backward	
			DC A(IOAREA2)	Two I/O area's	
			DC A(IOAREA2 +BLKSIZE-1)	Two I/O area's, read backward	
68-71	44-47		DC F'0'	Input	F
			DC A(IOAREA1 +BLKSIZE- RECSIZE)	Input backward: DEBLOCKER1	F
			DC A(IOAREA1)	1 I/O area, output: DEBLOCKER1	F
			DC A(IOAREA2)	2 I/O area's, output: DEBLOCKER1	F
			DC A(BLKSIZE)	DEBLOCKER1: EBCDIC	V, S
			DC A(IOAREA1)	1 I/O area: DEBLOCKER2	U
			DC A(IOAREA2)	2 I/O area's: DEBLOCKER2	U
72-75	48-4B		DC F'RECSIZE'	Forward: DEBLOCKER2	F
			DC F'-RECSIZE'	Backward: DEBLOCKER2	F
			DC A(IOAREA1)	1 I/O area: DEBLOCKER2	V, S
			DC A(IOAREA2)	2 I/O area's: DEBLOCKER2	V, S
			LA 14, 1(14)	Forward	U
			BCTR 14, 0 + NOPRO	Backward	U
76-79	4C-4F		DC F'0'	Input forward: DEBLOCKER3	F
			DC A(IOAREA1 +BLKSIZE - RECSIZE)	Input backwards: DEBLOCKER3	F
			DC A(IOAREA1 +BLKSIZE-1)	Output, 1 I/O area: DEBLOCKER3	F
			DC A(IOAREA2 +BLKSIZE-1)	Output, 2 I/O area's: DEBLOCKER3	F

DTFMT (Data Files) (...Cont'd)

Bytes		Bits	Contents	Function	Record Format
Dec	Hex				
76-79 (Cont'd)			DC F'0' DC Y(BLKSIZE) DC Y(BLKSIZE -1)	DEBLOCKER3 (Bytes 76-77 only) (Bytes 78-79 only)	V, S U U
80-83	50-53		DC Y(BLKSIZE) + Y(BLKSIZE-1) DC &(BLKSIZE) + Y(BLKSIZE+1) DC F'0' LR 12, RECSIZE DC H'0'	Forward Backward DEBLOCKER4 (Bytes 80-81 only) (Bytes 82-83 only)	F F V, S U U
84-87	54-57		DC Y(RECSIZE -1) DC 2X'00' DC A(IOAREA1 +4) DC A(IOAREA2 +4) DC A(IOAREA1 +BLUOFF) DC A(IOAREA2 +BLUOFF) DC 2X'00' B 28(15) B 24(15) B 28(15) DC A(ERROPT)	(Bytes 84-85) (Bytes 86-87) Output, Standard labels 1 I/O area: DEBLOCKER 5, EBCDIC 2 I/O area's: DEBLOCKER 5, EBCDIC 1 I/O area: DEBLOCKER5, ASCII 2 I/O area's: DEBLOCKER5, ASCII (Bytes 84-85 output only) Standard labels; reserved for OPEN Input only, ERROPT= omitted Input only, ERROPT= SKIP Input only, ERROPT= IGNORE Input only, ERROPT= ADDRESS	F V, S V V F, U U U U
88-91	58-5B		DC A(WLRERR) B 24(15) B 28(15) DC 2X'00' DC A(ERROPT)	Input only, WLRERR= ADDRESS Input only, WLRERR omitted and ERROPT= SKIP Input only, WLRERR omitted and ERROPT= IGNORE or omitted Output only, standard labels (bytes 88-89), reserved for OPEN Input only, WLRERR omitted and ERROPT= ADDRESS	For fixed-length records only
90-95	5A-5F		DC 6X'00'	File serial number, Standard labels, Output only	
92-95	5C-5F		DC A(ERROPT) B 28(15) B 24(15) B 28(15)	Input only, ERROPT= ADDRESS Output, nonstandard labels only. ERROPT= ADDRESS Input only, ERROPT= omitted Input only, ERROPT= SKIP Input only, ERROPT= IGNORE	
96-99	60-63		DC 4X'00'	Volume sequence number, Standard labels, output only	
96-97	60-61		DC 2X'00'	Standard labels, input only, reserved for OPEN	

DTFMT (Data Files) (....Cont'd)

Bytes		Bits	Contents*	Function	Record Format
Dec	Hex				
98-103	62-67		DC 6X'00'	File serial number, Standard labels, Input only.	For fixed-length records only
100-103	64-67		DC 4X'00'	File sequence number, Standard labels, output only	
104-107	68-6B		DC 4X'00'	Volume sequence number, Standard labels, input only	
			DC A(ERROPT)	Output only, Standard labels only. ERROPT= ADDRESS	
108-111	6C-6F		DC 4X'00'	File sequence number, Standard label, input only	
88-91	58-5B		DC F'0'	DEBLOCKER6	V,S (V only) For variable-length and spanned records
92-95	5C-5F		DC A(ERROPT)	Output only, Nonstandard labels only. ERROPT= ADDRESS	
92-93	5C-5D		DC Y(BLKSIZE)	Input only	
			DC Y(BLKSIZE -4)	Output only: EBCDIC	
			DC Y(BLKSIZE -BUFOFF)	Output only: ASCII	
94-95	5E-5F		DC Y(BLKSIZE -1)		
96-97	60-61		DC Y(RECSIZE -1)		
98-99	62-63		DC H'0'	Input only: Residual count	
100-103	64-67		DC A(WLRERR)	Input only, WLRERR= ADDRESS	
			B 24(15)	Input only, WLRERR= omitted and ERROPT= SKIP	
			B 32(15)	Input only, WLRERR= omitted and ERROPT= IGNORE or omitted	
100-101	64-65		DC 2X'00'	Output only, Standard labels, reserved for OPEN	
104-107	68-6B		DC A(ERROPT)	Input only, ERROPT= ADDRESS	
			B 28(15)	Input only, ERROPT= omitted	
			B 24(15)	Input only, ERROPT= SKIP	
			B 28(15)	Input only, ERROPT= IGNORE	
			DC A(ERROPT)	Output, Nonstandard labels only (version 3 onward); ERROPT=ADDRESS	
108-111	6C-6F		DC 4X'00'	Volume sequence number; Standard labels, output only	
108-109	6C-6D		DC 2X'00'	Standard labels, input only; Reserved for OPEN	
110-115	6E-73		DC 6X'00'	File serial number; Standard labels, input only	
112-115	70-73		DC 4X'00'	File sequence number; Standard labels, output only	

DTFMT (Data Files) (...Cont'd)

Bytes		Bits	Contents*	Function	Record Format
Dec	Hex				
116-119	74-77		DC A(ERROPT)	Output only, ERROPT= ADDRESS, Standard labels only	For variable length and spanned records
116-119	74-77		DC 4X'00'	Volume sequence number; Standard labels, input only	
120-123	78-7B		DC 4X'00'	File sequence number; Standard labels, input only	
86-91	56-5B		DC 6X'00'	File serial number; Standard labels, output only	For undefined records only
88-91	58-5B		DC A(WLRERR)	Input only; WLRERR= ADDRESS	
			B 24(15)	Input only; WLRERR= omitted and ERROPT= SKIP	
			B 28(15)	Input only; WLRERR= omitted and ERROPT= IGNORE or omitted	
			DC A(ERROPT)	Input only; WLRERR= omitted and ERROPT= ADDRESS. Output only; nonstandard labels, ERROPT= ADDRESS	
92-95	5C-5F		DC 4X'00'	Volume sequence number; Standard labels, output only	
92-93	5C-5D		DC 2X'00'	Standard labels; input only, Reserved for OPEN	
94-99	5E-63		DC 6X'00'	File serial number; Standard labels, input only	
96-99	60-63		DC 4X'00'	File sequence number; Standard labels, output only	
100-103	64-67		DC 4X'00'	Volume sequence number; Standard labels, input only	
100-103	64-67		DC A(ERROPT)	Output only; Standard labels only, ERROPT= ADDRESS	
100-103	64-67		DC 4X'00'	Volume sequence number; Standard labels, output only	
104-107	68-6B		DC 4X'00'	File sequence number; Standard labels, input only	
100-103	64-67		DC A(WLRERR)	Input only; WLRERR= ADDRESS	For spanned records only
			B 24(15)	Input only; WLRERR= omitted and ERROPT= SKIP	
			B 32(15)	Input only; WLRERR= omitted and ERROPT= IGNORE or omitted	
100-101	64-65		DC 2X'00'	Output only; Standard labels, reserved for OPEN	
102-107	66-6B		File serial number	Standard labels, output only	
100-103	64-67		DC 4X'00'	Output only; ERROPT= ADDRESS Nonstandard labels only	

DTFMT (Data Files) (...Cont'd)

Bytes		Bits	Contents*	Function	Record Format
Dec	Hex				
100-123	64-7B		DC 24X'00'	Output only; ERROPT= omitted, nonstandard labels	For spanned records only
104-107	68-6B		DC A(ERROPT) B 24(15) B 24(15) B 28(15)	Input only; ERROPT= ADDRESS Input only; ERROPT= omitted Input only; ERROPT= SKIP Input only; ERROPT= IGNORE	
104-107	68-6B		DC A(ERROPT)	Output only; ERROPT= ADDRESS, nonstandard labels	
108-123	6C-7B		DC 16X'00'	Output only; ERROPT= ADDRESS, nonstandard labels	
108-111	6C-6F		Volume sequence number	Standard labels, output only	
112-115	70-73		File sequence number	Standard labels, output only	
116-119	74-77		DC A(ERROPT)	Output only, ERROPT= ADDRESS, standard labels	
120-123	78-7B		DC 4X'00'	Output only, ERROPT= ADDRESS, standard labels	
108-123	6C-7B		DC 16X'00'	Input only, nonstandard labels	
108-109	6C-6D		DC 2X'00'	Standard labels, input only, reserved for OPEN	
110-115	6E-73		File serial number	Standard labels, input only	
116-119	74-77		Volume sequence number	Standard labels, input only	
120-123	78-7B		File sequence number	Standard labels, input only	
124-127	7C-7F		DC F'0'	Full word for loading and storing USER RECSIZE: IJFVSREC	
128	80	0	DC X'00'	IJFVSFLG	
		1		Sign bit, not used	
		2		Skip to first segment	
		3		First segment	
		4		Segment out of sequence, input only	
		5		Read back for EOF, output only File reversed for logical spacing; Input CNTRL only; TRUNC issued, output only	
		6		User TRUNC issued, output only	
		7		Multi segment, output only; Skip Get segment, input CNTRL only	
129-131	81-83		DC 3X'00'	Pointer within WORKA	

See Notes on next page

DTFMT (Data Files) (...Cont'd)

- The format of the tape data file DTF is different starting at byte 44.
The location indicated by the numbers in the left hand column can contain only one of the factors listed under Contents .
The factor used for any given DTF table is determined by whether the file record format is fixed, variable or undefined, and by other DTF parameters as indicated.
A blank in the record column indicates that the contents apply to all record types.

- Record Format explanation

F = Fixed Record
V = Variable
U = Undefined
S = Spanned (variable format superset)

The deblockers are scratch areas used by the modules to save data from one GET/PUT macro instruction to another. In the text and listings, they are referred to by the names DEBLOCKER1 to 6. These are not labels; they are comments used to make it easier to follow the listings.

DTFMT (Workfiles)

Bytes		Bits	Function
Dec	Hex		
0 -15	00-0F		CCB
16	10	0-1	Not used
		2	COBOL open; ignore option
		3	1= VOL1 label is at user specified density
		4	1= DTF table address constants relocated by OPENR
		5-7	Not used
17-19	11-13		Address of logic module
20	14		DTF type= X'10'
21	15	0	1= No rewind
		1	1= Rewind unload
		2	1= Workfile
		3	1= Read backward
		4	1= Write
		5	1= POINTW
		6	Not used
7	1= Forward-space file before next operation		
22-23	16-17		Not used
24-25	18-19		Record length
26-27	1A-1B		Maximum BLKSIZE
28	1C		Read command code (X'02' for read forward; X'0C' for read backward)
29-31	1D-1F		EOF address
32-39	20-27		CCW
40-43	28-2B		Block count, initialized 00000000 for read forward, 00400000 for read backward
44	2C	0	1= Error routine
		1	1= Ignore
		2	Not used
		3	1= Record fixed unblocked
4-7		Not used	
45-47	2D-2F		DC A(ERROPT) Address of error routine

DTFSD (Data Files)

DTF Assembly Label	Bytes		Bits	Function	
	Dec	Hex			
&Filename	0-15	00-0F		Command Control Block (CCB)	
	16	10	0	1=Dequeue old volume extents	
			1	1=Dummy OPEN to obtain extents from label track	
			2	1=File assigned 'IGN' (COBOL)	
			3	1=Track hold option specified	
			4	1=DTF relocated by OPENR	
			5	1=Input trailer labels to be processed at close time (COBOL only)	
			6	1=Spanned processing	
			7	1=COBOL end-of-extent option specified	
		17-19	11-13		Address of logic module
		20	14		DTF type for OPEN/CLOSE (X'20'=sequential access DASD files)
		21	15	0	1=Not used
				1	1=Blocked file
				2	1=Work file
				3	1=Workarea specified
				4	1=Not a Version 1 type table
				5	1=Open; 0=closed
				6	1=Input; 0=output
				7	1=User labels specified
		22-28	16-1C		Filename (DTF name)
		29	1D		Device type code: X'00'=2311 X'01'=2314,2319 X'04'=3330-1,-2 X'05'=3330-11 X'07'=3350 X'08'=3340 general X'09'=3340 35MB X'0A'=3340 70MB X'90'=FBA device
					Note: In previous versions, last byte of filename contains device type code
		30-35	1E-23		Address of Format 1 label in VTOC (BCCHHR or PBN)
		36-37	24-25		Volume sequence number
		38	26		Open communication byte:
					<u>Input file</u>
				0	1=No more extents
				1	1=Update file
				2	1=Process trailer labels
				3	1=Exit to user's EOF routine
				4	1=Next extent on new volume
				5	1=Return to close routine
				6	1=Process header labels
				7	1=Extent switch
					<u>Output file</u>
				0	1=No more extents
				1	1=Extents needed at close time
				2	1=Process trailer labels
			3	1=Process header labels	
			4	1=Next extent on new volume	
			5	1=Extents entered via console	
			6	1=Process trailer labels at close	
			7	1=Check extent for minimum of 2 tracks	

DTFSD (Data Files) (. . . Cont'd)

DTF Assembly Label	Bytes		Bits	Function	
	Dec	Hex			
&Filename.S	39	27	0	1=Extent bypassed before file is opened (input only)	
			1	1=FEOVD has been issued (input only)	
			0-7	Sequence number of current extent opened (output only)	
	40	28		Sequence number of last extent opened	
	41-43	29-2B		Address of user's label routine	
	44	2C	0	Not used	
			1	1=Device supports RPS	
			2	1=Version 3 DTF	
			3-7	Not used	
	45-47	2D-2F		Address of IOAREA 1	
	48-51	30-33		Address of user's label track (X'8000000')	
				CCHH for CKD and device address for FBA	
	52-53	34-35		Lower head limit (HH), zero for FBA	
	54-57	36-39	Fx	Extent upper limit (CCHH) for CKD, device address for FBA	
	58-59	3A-3B		Seek address (BB): X'0000' if a disk device, zero for FBA	
	60-63	3C-3F		Search argument (CCHH), physical block number for FBA	
	64	40		Record number: FBA=0; CKD=0 for output, 1 for input	
	65-67	41-43		EOF address if input file; Key length and data length if output file	
	68-71	44-47		CCHH control field: CCHH=X'00C80009' if 2311 - type 1 CCHH=X'00C80013' if 2314 or 2319 - type 1 CCHH=X'01940012' if 3330 - type 1 CCHH=X'03280012' if 3330-11 - type 1 CCHH=X'015C000B' if 3340 35 MB CCHH=X'02B8000B' if 3340 70MB CCHH=X'022B001D' if 3350 - type 1 PBN=maximum block number if FBA	
			72	48	Number of records per track (input) or number of records per track - <u>minus one (output)</u> , fixed length records only
73			49		Switch byte used by the logic modules for various switching purposes. Functions indicated are for the ON condition (1) of the respective bit.
					<u>Fixed length Record Modules</u>
				0	Not first entry after Open (INPUT and UPDATE) Not first write after Open (OUTPUT)
		1	Short record (INPUT and UPDATE without truncation		
		2	Partial block written (OUTPUT)		
		3	ERROPT=SKIP (INPUT); TRUNC=YES (OUTPUT)		
		4	End-of-file record written (OUTPUT)		
			End of extent (UPDATE)		
		5	Truncation not specified (used by OPEN routines)		
		6	Write block of records (UPDATE)		
		7	End of file (UPDATE)		

DTFSD (Data Files) (. . .Cont'd)

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
73 (Cont'd)			0	<u>Variable length Record Modules</u> Not first entry after OPEN (INPUT and UPDATE) Write record (OUTPUT)
			1	Wrong length record (INPUT); TRUNC=YES (OUTPUT); Second GET operation performed (UPDATE)
			2	Return to close routine (OUTPUT) Update specified (UPDATE)
			3	Not first entry after OPEN (OUTPUT)
			4	New extent required by CLOSE
			5	Capacity of I/O area exceeded (OUTPUT) Second GET required (UPDATE)
			6	Not first read (INPUT) Second GET issued (UPDATE)
			7	Unnecessary to read (INPUT) Track capacity exceeded (OUTPUT) Save record count (UPDATE)
			0	<u>Undefined length Record Modules</u> Not first entry after OPEN (ALL modules)
			1	Save record count (UPDATE)
			2	Return to close routine (OUTPUT)
			3	Second GET issued (UPDATE)
			4	Not used
			5	PUT command issued (UPDATE)
	6	End of file reached (UPDATE)		
	74-75	4A-4B		Block size minus 1
	76-80	4C-50		Extent lower limit and record number. Initialize with the current PBN/track address: CCHRR for CKD, track address for FBA.
	81	51	1	1=FEOVD has been issued (output only)
	81-83	51-53		Address of user wrong-length record routine if input file: Track capacity counter if output file.
	84-87	54-57		Instruction to load user's register IOREG. (Note: This field is a NOP unless blocked records are processed in one I/O area, or two I/O areas are specified and records are processed in the I/O areas)
	88-91	58-5B		Address of current available input/output area
	92-95	5C-5F		Logical record size
	96-99	60-63		Address of end of input/output area
	100	64		Logical indicators: 0=1=ERROPT=address 1=ERROPT=IGNORE 2=1=ERROPT=SKIP 3=1=VERIFY=YES 4=1=2 I/O areas 5=1=WLRERR=addr. (fixed length + variable records) 6=1=Output file (undefined length records) 7=1=Fixed-length records 0=Variable or undefined length records Control parameter specified
	101-103	65-67		Address of user's read error routine

This is the end of the common portion of the DTFSD table. The following sections are a added depending on the parameters specified in the operand of the DTFSD macro instruction.

DTFSD (Data Files) (. . . Cont'd)

The following section is added to the DTFSD table for fixed-length record output files.

DTF Assembly Label	Bytes*	Bits	Function
	If CONTROL is not specified:		
	160–163 (A0–A3)		End-of-extent routine address (primarily used by COBOL compiler).
	If CONTROL=YES:		
	184–187 (B8–BB)		End-of-extent routine address (primarily used by COBOL compiler).

The following section is added to the DTFSD table for variable-length record, undefined length record, and spanned record input files.

DTF Assembly Label	Bytes*	Bits	Function
	If UPDATE is not specified:		
	If CONTROL=YES: ¹		
	176–179 (B0–B3)		Logical record length
	180–183 (B4–B7)		RX type instruction
	184 (BB)	0	Not used
		1	1=Skip segment
		2	1=Spanned first time
		3	Not used
		4	Not used
		5	Not used
		6	Not used
		7	Not used
	185–187 (B9–BB)		Pointer in logical record

¹ These bytes are always generated when spanned processing is specified.

The following section is added to the DTFSD table for variable-length spanned record update files.

DTF Assembly Label	Bytes	Bits	Function
	216–219 (DB–DB)		Logical record length
	220–223 (DC–DF)		RX type instruction. Load record size in register.
	224 (E0)	0	Not used
		1	1=Skip segment
		2	1=Spanned first time
		3	1=Null segment
		4	1=Spanned PUT return
		5	Not used
		6	Not used
		7	1=No update
	225–227 (E1–E3)		Pointer in logical record
	228–235 (E4–EB)		Not used
	236–239 (EC–EF)		Extent status save area

DTFSD (Data Files) (. . . Cont'd)

The following section is added to the DTFSD table for variable-length spanned record output files.

DTF Assembly Label	Bytes*	Bits	Function
	160–163 (A0–A3)		Space remaining in output area
	164–165 (A4–A5)		Track capacity
	166–169 (A6–A9)		Instruction to load user's register VARBLD. (If VARBLD is not specified, instruction is NO-OP.)
	If CONTROL=YES: ¹		
	170–172 (AA–AC)		Not used
	173–175 (AD–AF)		End-of-extent routine address (primarily used by COBOL compiler)

¹ These bytes are always generated when spanned processing is specified.

The following section is added to the DTFSD table for variable-length spanned record output files.

DTF Assembly Label	Bytes*	Bits	Function
	200–203 (CB–CB)		Logical record length
	204–207 (CC–CF)		RX type instruction. Store record size.
	208 (D0)	0	Not used
		1	Not used
		2	1=Leading segment
		3	1=Output block truncated
		4	1=End of track
		5	1=Track truncated
		6	1=Save count
		7	1=Volumes spanned
	209–211 (D1–D3)		Pointer in logical record
	212–219 (D4–DB)		Not used
	220–223 (DC–DF)		Extent status save area

The following section is added to the DTFSD table for undefined length record output files.

DTF Assembly Label	Bytes*	Bits	Function
	160–161 (A0–A1)		Track capacity
	If CONTROL=YES:		
	162–164 (A2–A4)		Not used
	164–167 (A4–A7)		End-of-extent routine address (primarily used by COBOL compiler).

*Numbers in parentheses are displacements in hexadecimal notation.

DTFSD (Workfiles)

DTF Assembly Label	Bytes		Bits	Function	
	Dec	Hex			
&Filename	0–15	00–0F		Command Control Block (CCB). Note: The CCW address in byte 9–11 is changed by OPEN to point to the DTF Extension. CLOSE restores it.	
	16	10	0–1	Not used	
			2	1=File assigned 'IGN' (COBOL)	
			3	1=Track hold option specified	
			4	1=DTF relocated by OPENR	
			5–7	Not used	
	17–19	11–13		Address of logic module. OPEN changes to point to the logic module in SVA. CLOSE restores it.	
	20	14		DTF type for OPEN/CLOSE (X'20' = sequential access DASD files)	
	21	15	0	0=Disk device	
			1	1=CLOSE macro is not to delete Format 1 and Format 3 file labels	
			2	1=Work file	
			3	Type of open: 1=Point; 0=Normal	
			4	1=Routine entered from close routine	
			5	1=File opened; 0=File closed	
			6–7	Not used	
	22–28	16–1C		Filename (DTF name)	
	29	1D		Device type Code: X'00'=2311 X'01'=2314,2319 X'04'=3330-1,-2 X'05'=3330-11 X'07'=3350 X'08'=3340 general X'09'=3340 35MB X'0A'=3340 70MB X'90'=FBA device Note: In previous versions, last byte of filename contains device type code	
30–31			1E–1F	Track capacity counter	
32–35			20–23	Address of Format 1 label in VTOC (CCHHR for CKD, PNB for FBA)	
36			24	Extent sequence number	
37			25		Open communication byte
				0	Not used
				1	1=Device supports RPS
				2	1=Version 3 DTF
				3	1=symbolic unit in DTF
				4	1=next extent on new volume
	5	1=extent opened			
6–7	Not used				
38	26		Lower head limit for CKD, zero for FBA		
39	27		Upper head limit for CKD, zero for FBA		
&Filename.L	40–41	28–29		Record length	
	42–45	2A–2D		Initial extent lower limit	
	46–49	2E–31		Current extent lower limit	
	50–53	32–35		Extent upper limit	

DTFSD (Workfiles) (. . . Cont'd)

DTF Assembly Label	Bytes		Bits	Function	
	Dec	Hex			
&Filename.S	54–55	36–37		Seek address (BB=X'0000'), not used for FBA	
	56–59	38–3B		Search address (CCHH) for CKD, PBN for FBA	
	60	3C		Record number for CKD, zero for FBA	
	61	3D		Switch byte used by logic module	
			0	1=First write entry indicator	
			1	1=Write update indicator	
			2	1=POINTS macro issued	
			3	Not first record of a track (RECFORM=UNDEF)	
			4	1=Track upper limit reached	
			5	Not used	
			6	1=Check after read/write	
			7	Not used	
		62–63	3E–3F		Maximum record length
		64	40		Not used
		65–67	41–43		Address of user's EOF routine
		68	44		Logical indicators
			0		1=ERROPT=address
			1		1=ERROPT=IGNORE
			2		1=Fixed-length unblocked records
			3		1=Verify specified
		4		1=ERROPT=SKIP	
		5		1=Re-read after read error	
		6–7		Not used	
	69–71	45–47		Address of user read/write error routine	

DTFDA

DTF Assembly Label	Module DSECT Label	Bytes		Bits	Function		
		Dec	Hex				
&Filename	IJICCB	0-15	00-0F	0 1 2 3 4 5 6 7	Command Control Block (CCB) 1= Trailer labels Used by FREE macro 1= COBOL Open/Ignore option 1= Track hold option specified 1= DTF relocated by OPENR Not used 1= SPNUNB Used by CNTRL macro		
	IJIMOD	16	10				
	IJISWI	17-19	11-13			0 1 2 3 4 5 6 7	Address of logic module DTF type for OPEN/CLOSE (X'22'= direct access files) 1= Output; 0= Input 1= Verify option specified 1= Search multiple track (SRCHM) specified 1= WRITE AFTER or WRITE RZERO macro used 1= IDLOC specified 1= Undefined; 0 = FIXUNB, VARUNB or SPNUNB 1= RELTYPE= DEC 1= End of file
		20	14				
		21	15				
		22-28	16-1C				
		29	1D				
	IJIFNM	22-28	16-1C	0 1 2-6 7	Filename (DTF name) Device type code: X'05'=3330-11 X'00'=2311 X'07'=3350 X'01'=2314, 2319 X'08'=3340 general X'09'=3340 35MB X'04'=3330-1, -2 X'0A'=3340 70MB		
	IJIDVTP	29	1D				
	IJIUNT	30-31	1E-1F				
	IJIRPS	32	20				
						0	Not used 1=Device supports RPS, RPS=YES in FOPT macro Not used 1=Extended DTF for RPS
1							
2-6							
IJIULB	33-35	21-23	Address of user's label routine Address of user's routine for processing EXTENT information Pointer to relative address area <u>&Filename.P - &Filename</u> 2 Address of a 2-byte field in which IOCS can store the error condition or status codes Macro code switch for internal use: X'0000'= READ ID X'0001'= READ KEY X'0002'= WRITE ID X'0003'= WRITE KEY X'0004'= WRITE RZERO X'0005'= WRITE AFTER				
IJIUXT	36-39	24-27					
IJIRELPT	40	28					
IJIERC	41-43	29-2B					
						2	
IJITST	44-45	2C-2D					

DTFDA (....Cont'd)

DTF Assembly Label	Module DSECT Label	Bytes		Bits	Function
		Dec	Hex		
&Filename.Z	IJIBPT	46-47	2E-2F		Pointer to channel program build area (&Filename.B) minus 32
	IJICB2	48-63	30-3F		Control seek CCB
	IJICCW	64-71	40-47		Control Seek CCW for overlap seek routine
	IJIXMD	72-75	48-4B		Channel program builder instruction: XI 36(2),C'0'
	IJIMSZ	76-77	4C-4D		Maximum data length for FIXUNB or UNDEF records; BLKSIZE for VARUNB or SPUNB records
	IJISPT	78	4E		Pointer to READ ID string (File name.0); X'00' if no READ ID issued
		79	4F		Pointer to READ KEY string (File name.1); X'00' if no READ KEY issued
		80	50		Pointer to WRITE ID string (File name.2); X'00' if no WRITE ID issued
		81	51		Pointer to WRITE KEY string (File name.3); X'00' if no WRITE KEY issued
		82	52		Pointer to WRITE RZERO string (Filename.4); X'00' if no WRITE RZERO issued
	IJITRK	83	53		Pointer to WRITE AFTER string (Filename.5); X'00' if no WRITE AFTER issued
84-85		54-55		Track constant: 2311: H'0' if key length=0 H'20' if key length≠0 2314/2319: H'0' if key length=0 H'45' if key length≠0 3330: H'135' if key length=0 H'191' if key length≠0 3340: H'167' if key length=0 H'242' if key length≠0 3350: H'185' if key length=0 H'267' if key length≠0	
IJIRIC		86-87	56-57		2311: H'61' 2314/2319: H'101' 3330: H'135' 3340: H'167' 3350: H'185'
		IJILAT	88	58	0 Not used 1 1= Wrong-length record 2 1= non data transfer error 3 Not used 4 1= no room found

DTFDA (. . . . Cont'd)

DTF Assembly Label	Module DSECT Label	Bytes		Bits	Function
		Dec	Hex		
	IJILAT (Cont'd)	88	58	5-6 7	Not used 1= Record out of extent area
		89	59	0 1 2 3 4 5 6 7	1= Data check in count area 1= Track overrun 1= End of cylinder 1= Data check when reading key or data 1= No record found 1= End of file 1= End of volume Not used
	IJILBTK	90-95	5A-5F		Label track address, XBCCHH, where X is the volume sequence number of the device on which the label track is located.
The following section is included if UNDEF, AFTER or RZERO is specified					
&Filename.L	IJILST	96-143	60-8F		Basic CCW's to build channel program
		144-183	90-87		Basic CCW's for undefined length or formatting macros
	IJIVIT	184-185	88-89		Instruction to give record length to user if record length is undefined (NOPR 0 if no RECSIZE specified)
	IJIFRU	186-187	8A-8B		Instruction to get record length from user if record length is undefined. (NOPR 0 if no RECSIZE specified)
&Filename.F	IJIFLD	188-192	8C-C0		Work area (used for R0 address - CCHH0)
&Filename.K	IJICNT	193-200	C1-C8		Work area (used for R0 data field)
&Filename.C	IJICTS	201-208	C9-D0		Work area (included only for spanned or variable records for record count field)
The channel program builder strings are generated following the DTFDA table and preceding the channel program building area					
&Filename.0			Variable		Channel program builder string for READ ID macro. If READ ID is not specified, the string is not generated
&Filename.1			Variable		Channel program builder string for READ KEY macro. If READ KEY is not specified, the string is not generated
&Filename.2			Variable		Channel program builder string for WRITE ID macro. If WRITE ID is not specified, the string is not generated

DTFDA (...Cont'd)

DTF Assembly Label	Module DSECT Label	Bytes		Bits	Function
		Dec	Hex		
&Filename.3		Variable			Channel program builder string for WRITE KEY macro. If WRITE KEY is not specified, the string is not generated
&Filename.4		Variable			Channel program builder string for WRITE RZERO macro. If WRITE RZERO or WRITE AFTER is not specified, the string is not generated
&Filename.5		Variable			Channel program builder string for WRITE AFTER macro. If WRITE RZERO or WRITE AFTER is not specified, the string is not generated
The following section contains the channel program build areas and varies in size					
&Filename.B		0-7	00-07		Seek CCW that is generated at program assembly time and used by all channel programs
		Variable			<p>Area to build:</p> <ol style="list-style-type: none"> Eight CCW's if AFTER is not specified Eight CCW's if spanned or variable length records and AFTER= YES is specified Seven CCW's if undefined or fixed records and AFTER= YES is specified
		Variable			<p>Area to build:</p> <ol style="list-style-type: none"> Eight CCW's if AFTER is not specified and VERIFY= YES is specified Eight CCW's if spanned or variable length records and AFTER= YES and VERIFY= YES are specified Five CCW's if undefined or fixed records and AFTER= YES and VERIFY= YES are specified
The following section is added for spanned records only					
		8 bytes			Count save area
		8 bytes			SEEKADR save area
		1 byte		0	1= Relative addressing
				1	1= IJIGET switch on
				2	1= Ignore hold switch on
				3	Reserved for use by DAMODV
				4	1= New volume SEEKADR
				5-7	Not used

DTFDA (...Cont'd)

DTF Assembly Label	Module DSECT Label	Bytes		Bits	Function
		Dec	Hex		
		1 byte			Reserved
		2 bytes			Record size
		12 bytes			Work area
		8 bytes			Control word save area
The following section is added to the DTFDA table if DSKXTNT (relative addressing) is specified					
&Filename.P		3 bytes			3X'00' for padding
&Filename.I		5 bytes			IDLOC record area (bucket used by module)
&Filename.S		8 bytes			SEEKADR in the form: M,B1,B2,C1,C2,H1,H2,R
		4 bytes			DC A(&SEEKADR)
		4 bytes			DC A(&IDLOC)
		8 bytes			Work area for RELTYPE= DEC
&Filename.X		4 bytes			Save area for CCHH portion of actual DASD address
		4 bytes			Alteration factor for C1 in SEEK ADR (see bytes 112-119) 2311 : X'00000001' 2314/2319 : X'00000001' 3330 : X'00001300' 3340 : X'00000C00' 3350 : X'00001E00'
		4 bytes			Alteration factor for C2 in SEEK ADR (see bytes 112-119) 2311 : X'0000000A' 2314/2319 : X'00000014' 3330 : X'00000013' 3340 : X'0000000C' 3350 : X'0000001E'
		4 bytes			Alteration factor for H1 in SEEK ADR (see bytes 112-119) 2311 : X'00000001' 2314/2319 : X'00000001' 3330 : X'00000001' 3340 : X'00000001' 3350 : X'00000001'
		Variable to end of DTF table			DSKXTNT table composed of a variable number of 8-byte entries containing extent information in the following format:
		Bytes 0-2	TTT2 - cumulative number of tracks in the DSKXTNT table entries up to and including the current entry		
		3	M- volume sequence number		
		4	B - bin number (0 for disk devices)		
		5-7	TTT1 - relative track number of lower limit of this entry		
			A 2-byte end-of-table indicator containing X'FFFF' follows the last entry in the DSKXTNT table		

DTF Extension for DTFDA

DTF Assembly Label	Module DSECT Label	Bytes		Bits	Function
		Dec	Hex		
	IJIXBLD	0	0		CCW build area
	IJIXSPTR	176	B0		Address of original channel program
	IJIXSVMP	180	B4		Address of original logic module
	IJISAVA	184	B8		Save area
		266	100		Not used
	IJISECV0	267	101		Sector work byte
	IJISECV1	268	102		Sector work byte
	IJISECV2	269	103		Sector work byte
	IJIXSEC	270	104		RPS CCW
	IJIXSS0	278	10C		RPS CCW
	IJIXSSX	286	114		RPS CCW
	IJIXSSNF	294	11C		RPS CCW
	IJIXSTRG	302	124		PESC byte string area
	IJIXSPT	382	174		Displacement to strings
	IJIXMCYL	390	186		Maximum cylinders per volume
	IJIXTFAC	392	188		Tolerance factor
	IJIFLG1	394	18A		Flag byte
	IJIXUSTF	395	18B		Indicator needed to use tolerance factor
	IJIFLG2	396	18C		Flag byte

DTFIS (Load)

DTF Assembly Label	Bytes		Bits	Function	
	Dec	Hex			
&Filename	0-15	00-0F		Command Control Block (CCB)	
	16	10	0-1	Not used	
			2	1=COBOL open; ignore option	
			3	Not used	
			4	1=DTF table address constants relocated by OPENR	
			5	Not used	
			6	1=Data set security	
			7	1=Wrong blocksize error during file extension	
		17-19	11-13		Address of logic module
		20	14		File type for OPEN/CLOSE (X'24'=LOAD)
		21	15		Option byte:
	&Filename.C			0-1	Not used
			2	1=Cylinder overflow option	
			3	Not used	
			4	1=Blocked records (used by previous versions)	
			5	1=Verify	
			6	Not used	
			7	1=2 I/O areas present	
		22-28	16-1C		File name
		29	1D		Prime data device type indicator: X'00'=2311; X'01'=2314/2319; X'04'=3330; X'08'=3340 general; X'09'=3340 35MB X'0A'=3340 70MB
		30	1E		Status byte:
			0	1=Uncorrectable DASD error (except WLR Error)	
			1	1=WLR error	
		2	1=Prime data area full		
		3	1=Cylinder index area not large enough to reference prime data area. Set on only if error detected at SETFL time.		
		4	1=Master index not large enough to reference prime data area. Set on only if error detected at SETFL time.		
		5	1=Duplicate record		
		6	1=Sequence error		
		7	1=No EOF record written in prime data area		
	31	1F		High level index device type indicator: X'00'=2311; X'01'=2314/2319; X'04'=3330; X'08'=3340 general; X'09'=3340 35MB; X'0A'=3340 70MB	
	32	20		Relative position of the DSKXTN (logical unit, cell number) table (in words). This value is the length of the DTF table divided by 4.	

DTFIS (Load) (...Cont'd)

DTF Assembly Label	Bytes		Bits	Function	
	Dec	Hex			
&Filename.H	33-34	21-22		First prime track in cylinder (HH)	
	35	23		First prime data record in cylinder (R)	
	36-37	24-25		Last prime track in cylinder (HH)	
	38	26		High record on master index/cylinder index track (R)	
	39	27		High record on prime data track (R)	
	40	28		High record on overflow track (R)	
	41	29		High record on last track index track in cylinder (whether shared or unshared)	
	42	2A		High record on track index track other than last in cylinder. If only one track index track in cylinder, it is equal to byte 41	
	43	2B		Condition code :	
				0	1= WLR checks requested (for extension)
				1	1= First record in file
				2	1= Prime data extent full
				3	1= Master index/cylinder index extent too small
				4	1= Prime data upper limit has been increased (for extension)
				5	1= Extension
				6-7	Not used
		44-50		2C-32	Prime data lower limit (MBBCCHH)
		51-57		33-39	Cylinder index lower limit (MBBCCHH)
		58-64		3A-40	Master index lower limit (MBBCCHH)
		65		41	Switches
				0-3	Not used
				4	1= RPS type device (data)
				5	1= RPS type DTF
				6	1= Master index
				7	1= RPS type device (index)
		66-73		42-29	Address of last prime data record (MBBCCCHR)
	74-75	4A-48	Logical record length		
	76-77	4C-4D	Key length		
	78-79	4E-4F	Block length (logical record length times number of records)		
	80-81	50-51	Overflow record length (logical record length plus 10)		
	82-83	52-53	Blocking factor (number of logical records)		
	84-85	54-55	Index entry length (key length plus 10)		
	86-87	56-57	Prime data record length (key length plus physical record length)		
	88-89	58-59	Overflow record length with key (key length plus logical record length plus 10)		
	90-91	5A-5B	Prime data record format length (key length plus physical record length plus 8)		

DTFIS (Load) (....Cont'd)

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
	92-93	5C-5D		Overflow record format length (key length plus logical record length plus 18)
	94-95	5E-5F		Key location (in blocked records)
This is the end of the common DTF area. The format of the remainder of the table is variable and is generated according to the parameters specified in the DTFIS macro instruction				
&Filename.S	96-103	60-67		Seek/search address area (MBBCCHHR)
&Filename.P	104-105	68-69		Logical record counter (for blocking)
	106-107	6A-6B		Number of bytes for high level index
	108-111	6C-6F		Prime data record counter (logical records)
	112	70		Status indicators:
			0-1	Not used
			2	1= File closed
			3-5	Not used
			6	1= Last prime data track full
			7	1= Last block full
	113-117	71-75		Last track index normal entry address (CCHHR)
	118-122	76-7A		Last cylinder index entry address (CCHHR)
	123-127	7B-7F		Last master index entry address (CCHHR)
&Filename.B				CCW build area. See description of SETFL macro, phase 1 - \$\$BSETFL
	128-135	80-87		Seek CCW
	136-143	88-8F		Search ID Equal CCW
	144-151	90-97		TIC CCW
	152-159	98-9F		Read/Write CCW
	160-167	A0-A7		Search ID Equal CCW
	168-175	A8-AF		TIC CCW
	176-183	B0-B7		Verify CCW
&Filename.M	184-187	B8-BB		Address of IOAREAL
	188-191	BC-BF		Address of data in WORKL. (FIXBLK= address of WORKL; FIXUNB= address of WORKL plus key).
	192-195	C0-C3		Address of key in WORKL. (FIXBLK= address of WORKL plus KEYLOC minus 1; FIXUNB= address of WORKL.)
	196-199	C4-C7		Block position indicator (address of logical record in IOAREAL)
	200	C8		Master index, extension indicator:
			0-2	Not used
			3	1= Extending file; 0= Creating file
			4-6	Not used
			7	1= Master index being used; 0= No master index being used

DTFIS (Load) (....Cont'd)

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
	201-204	C9-CC		Cylinder index upper limit (CCHH)
	205-208	CD-D0		Master index upper limit (CCHH)
	209-215	D1-D7		Prime data upper limit (old upper limit if extension) (MBBCCHH)
	216-222	D8-DE		Prime data new upper limit (for extension) (MBBCCHH)
	223	DF		Last prime data track in cylinder minus 1
	224-225	E0-E1		Key length minus one
	226-227	E2-E3		Logical record length minus 1
	228-229	E4-E5		Address of track index dummy record (HR)
	230-231	E6-E7		Address of record before first prime data record in cylinder (HR)
	232	EB		Number of records on master index/cylinder index track minus 1
	233-236	E9-EC		Master index/cylinder index DASD address control field (CCHH): 2311 = X'00C70009' 2314/2319= X'00C70013' 3330 = X'01FF0012' 3340 = X'01FF000C'
	237-239	ED-EF		Prime data address control field (CCH): 2311 = X'00C700' 2314/2319= X'00C700' 3330 = X'01FF00' 3340 = X'01FF00'
	240-242	F0-F2		Prime data beginning of volume (CCH): 2311 = X'000100' 2314/2319= X'000100' 3330 = X'000100' 3340 = X'000100'
	243-245	F3-F5		Prime data end of volume (CCH): 2311 = X'00C700' 2314/2319= X'00C700' 3330 = X'019300' 3340 = X'015800'(35MB), X'02B700'(70MB)
	246-247	F6-F7		Used for alignment
&Filename.E	248-251 ¹⁾	F8-FB		First entry in DSKXTN table (logical unit, cell number)
	256-259 ²⁾	100-103		X'FFFFFFF'= End of DSKXTN table
	260-263	104-107		Address of IOAREA2
	264-267	108-10B		Address used to relocate IOAREA2

1) Each entry in the DSKXTN table is 4 bytes long. The minimum number of entries is two. There is one entry per extent.

2) Location of the end-of-table indicator depends on length of DSKXTN table

DTFIS (Add) - part 1

DTF Assembly Label	Bytes		Bits	Function	
	Dec	Hex			
&Filename	0 -15	00-0F		CCB	
	16	10	0	Not used	
			1	Not used	
			2	1= COBOL open; ignore option	
			3	1= Track hold specified	
			4	1= DTF table address constants relocated by OPENR	
			5	Not used	
			6	1= Data set security	
			7	1= Wrong blocksize error during addition to file	
		17-19	11-13		Logic module address
		20	14		File type for OPEN/CLOSE (X'25'= ADD)
		21	15		Option byte:
				0	Not used
				1	1= Prime data in core
				2	1= Cylinder overflow
				3	1= Cylinder index in core
				4	1= Blocked records
				5	1= Verify
				6-7	Not used
		22-28	16-1C		DTF file name
	29	1D		Prime data device type indicator: X'00'= 2311 X'01'= 2314/2319 X'04'=3330 X'08'= 3340 general X'09'= 3340 (35MB) X'0A'= 3340 (70MB)	
&Filename.C	30	1E		Status byte:	
			0	1= Uncorrectable DASD error (except WLR)	
			1	1= WLR error	
			2	1= EOF (sequential)	
			3	1= No record found	
			4	1= Illegal ID specified	
			5	1= Duplicate record sensed	
			6	1= Overflow area full	
			7	1= Record retrieved from overflow area	
		31	1F		Highest level index device type: X'00'= 2311 X'01'= 2314/2319 X'04'=3330 X'08'= 3340 general X'09'= 3340 (35MB) X'0A'= 3340 (70MB)
	32	20		Relative position of the DSKXTN (logical unit, cell number) table (in words). This value is the length of the DTF table divided by 4	
	33-35	21-23		First prime data record in cylinder (HHR)	
	36-37	24-25		Last prime data track in cylinder (HH)	
	38	26		High record number on master index/cylinder index track (R)	

DTFIS (Add) - part 1 (...Cont'd)

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
39	27			High record number on prime data track (R)
40	28			High record number on overflow track (R)
41	29			High record number on shared track (R)
42	2A			High record number on track index (TI) track (R)
43	2B			Retrieval byte :
			0	1= WORKR area specified
			1	1= WORKS area specified
			2	Overflow switch
			3	1= Read
			4	Not used
			5	1= Output
			6	1= Write key
			7	1= PUT macro issued
44-50	2C-32			Prime data lower limit (MBBCCHH)
51-57	33-39			Cylinder index lower limit (MBBCCHH)
58-64	3A-40			Master index lower limit (MBBCCHH)
65	41			Switches
			0	1= From WAITF routine
			1	1= WAITF seek check bit
			2-3	Not used
			4	1= RPS type device (data)
			5	1= RPS type DTF
			6	1= Master index
			7	1= RPS type device (index)
66-73	42-49			Last prime data record address (MBBCCHR)
74-75	4A-4B			Logical record length (RECSIZE)
76-77	4C-4D			Key length (KEYLEN)
78-79	4E-4F			Block size (logical record length times number of records)
80-81	50-51			Overflow record length (logical record length plus 10)
82-83	52-53			Blocking factor (number of logical records in block (NRECD5))
84-85	54-55			Index entry length (key length plus 10)
86-87	56-57			Prime data record length (key length plus physical record length (block size))
88-89	58-59			Overflow record length plus key (key length plus logical record length plus 10)
90-91	5A-5B			Prime data record format length (key length plus blocksize plus 8)
92-93	5C-5D			Overflow record format length (key length plus logical record length plus 18)
94-95	5E-5F			Key location (KEYLOC) for blocked records
96-97	60-61			Constant = 5
98-99	62-63			Constant = 10

DTFIS (Add) - part 1 (...Cont'd)

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
	100-101	64-65		Displacement of part 2 of the DTFIS table from start of part 1
	102-103	66-67		Displacement of part 3 of the DTFIS table from start of part 1
&Filename.S	104-113	68-71		Seek/search address area (MBBCCHRFP)
&Filename.W	114-123	72-7B		Random/sequential retrieval work area
&Filename.P	124-127	7C-7F		Prime data record count
	128	80		Status indicators:
			0-1	Not used
			2	1= File closed
			3-5	Not used
			6	1= Last prime data track full
			7	1= Block complete
	129-133	81-85		Last track index normal entry address (CCHHR)
	134-138	86-8A		Last cylinder index entry address (CCHHR)
	139-143	8B-8F		Last master index entry address (CCHHR)
	144-151	90-97		Last independent overflow record address (MBBCCHR)
&Filename.I	152-153	98-99		Number of independent overflow tracks
&Filename.A	154-155	9A-9B		Number of full cylinder overflow areas
&Filename.O	156-157	9C-9D		Overflow record count
	158-164	9E-A4		Independent overflow area lower limit (MBBCCHH)
	165-171	A5-AB		Independent overflow area upper limit (MBBCCHH)
	172-175	AC-AF		A(&Filename.D) - Address of work area for cylinder overflow control record (COCR)
	176-179	B0-B3		A(&Filename.D+8) - Address of workarea for the current track index normal entry count field
	180-183	B4-B7		A(&Filename.D+16) - Address of work area for current track index overflow entry count field
	184-187	B8-BB		A(&Filename.D+24) - Address of workarea for current prime data record count field
	188-191	BC-BF		A(&Filename.D+32) - Address of work area for current overflow record count field
	192-195	C0-C3		A(&Filename.D+40) - Address of work area for track index normal entry data field
	196-199	C4-C7		A(&Filename.D+50) - Address of work area for current overflow record linkage field
	200-203	C8-CB		A(&IOAREAL) - Address of IOAREAL, the I/O area used for adding records to a file

DTFIS (Add) – part 1 (...Cont'd)

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
	204-207	CC-CF		A(&WORKL) – Address of WORKL, workarea containing user data records to be added to the file
	208-211	D0-D3		A(&Filename.K) – Address of the ADD key area
	212-215	D4-D7		A(&IOAREAL+8) – Address of key position in IOAREAL
	216-219	D8-DB		A(&IOAREAL+8+&KEYLEN) – Address of data position in IOAREAL

DTFIS (Add) – part 2

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
&Filename.2	0 -3	00-03		A(&Filename.S+3) – Address of the seek/search address area plus 3
	4	04	0 1-5 6 7	1= Seek check indicated Not used 1= Over/under seek has occurred 1= An error has been found, but a seek check is indicated
	5 -7	05-07		A(&Filename.W) – Address of random/sequential retrieval work area

The following information is generated if the cylinder index in core option is specified

	12-15	0C-0F		A(&INDAREA) – Starting address of main storage area specified for cylinder index
	16-17	10-11		AL2(&INDSIZE) – Number of bytes in main storage available for cylinder index
	18-25	12-19		Next cylinder index entry to be read (MBBCCCHR)
	26-30	1B-1E		Last cylinder index entry (CCHHR)
	31	1F		Core index byte:
			0	1= First time through B-transient, \$\$\$INDEX
			1	1= End of cylinder index reached
			2	1= Index skip option specified
			3	1= Suppress in-core option and read cylinder index
			4-7	Not used
	32-35	1D-23		Pointer to key (stored by module)

DTFIS (Add) – part 2 (...Cont'd)

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
The following information is generated if the prime data in core add function is specified This information is aligned on a double word boundary				
	36-37	24-25	0 1-7	Size of IOAREAL
	38-39	26-27		Maximum number of prime data records in main storage
	40-43	28-2B		Address of write CCW's
	44-47	2C-2F		Address of read CCW's
	48	30		Switch byte: 1= EOF Not used
	49	31		Reserved.
	50-51	32-33		Work field for I/O Module.

DTFIS (Add) – part 3

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
&Filename.B	0 -7	00-07		CCW X'07', &Filename.S+1, X'40', 6 - Long seek CCW with command chaining
	8 -127	08-7F		Channel program build area.
&Filename.D	128-135	80-87		Cylinder overflow control record (COCR)
	136-143	88-8F		Current track index normal entry count field address
	144-151	90-97		Current track index overflow entry count field address
	152-159	98-9F		Current prime data record count field address
	160-167	A0-A7		Current overflow record count field address
	168-177	A8-B1		Track index normal entry data field
	178-187	B2-BB		Current overflow record sequence link field
	188-197	BC-B5		Current track index overflow entry data field
	198	C6		X'01' - Add to EOF X'02' - Add to independent overflow area
	199-201	C7-C9		Overflow control bytes (CCH)
	202-203	CA-CB		High HR on overflow track
	204-211	CC-D3		Volume upper limit for prime data records (MBBCCCHR)
	212-217	D4-D9		CLC 0 (&KEYLEN, 13), 0 (6) - Unblocked CLC 0 (&KEYLEN, 13), &KEYLOC-1 (6) - Blocked Utility CLC for key

DTFIS (Add) – part 3 (...Cont'd)

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
	218-223	DA-DF		MVC 0 (&KEYLEN, 13), 0 (12) – Unblocked MVC 0 (&KEYLEN, 13), &KEYLEN-1 (12) – Blocked Utility MVC for key
&Filename.E	224-227 ¹⁾	E0-E3		First entry in DSKXTN table (logical unit, cell number)
	232-235 ²⁾	E8-EB		4X'FF' – End of DSKXTN table
&Filename.K	236 +	EC-end		Key area for ADD only. Number of bytes depends on key length, KEYLEN

- 1) Each entry in the DSKXTN table is four bytes long. The minimum number of entries is two. There is one entry per extent.
- 2) Location of the end-of-table indicator depends on length of DSKXTN table.

DTFIS (RETRVE,RANDOM) – part 1

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
&Filename	0 -15	00-0F		Command Control Block (CCB)
	16	10	0	Not used
			1	1= GET issued
			2	1= COBOL open; ignore option
			3	1= HOLD option specified
			4	1= DTF table address constants relocated by OPENR
			5-6	Not used
			7	1= Different blocksize in format-1 label than in DTFIS.
	17-19	11-13		Address of logic module
	20	14		File type for OPEN/CLOSE (X'26'= RETRVE)
	21	15		Option byte:
			0	Not used
			1	1= Prime data in core
			2	1= Cylinder overflow option
			3	1= Cylinder index in core option
			4	1= Blocked records
			5	1= Verify
			6-7	Not used
	22-28	16-1C		File name (DTF name)
	29	1D		Prime data device type: X'00'= 2311 X'01'= 2314/2319 X'04'= 3330 X'08'= 3340 general X'09'= 3340 (35MB) X'0A'= 3340 (70MB)
&Filename.C	30	1E		Status byte:
			0	1= Uncorrectable DASD error (except WLR error)
			1	1= WLR error
			2	1= EOF (sequential)
			3	1= No record found
			4	1= Illegal ID specified
			5	1= Duplicate record sensed
			6	1= Overflow area full
			7	1= Record retrieved from overflow area
	31	1F		High level index device type: X'00'= 2311 X'01'=2314/2319 X'04'= 3330 X'08'= 3340 general X'09'= 3340 (35MB) X'0A'= 3340 (70MB)
32	20		Relative position of the DSKXTN (logical unit, cell number) table (in words). This value is the length of the DTF table divided by 4	
33-35	21-23		First prime data record in cylinder (HHR)	
36-37	24-25		Last prime data track in cylinder (HH)	
38	26		High record number on master index/cylinder index track (R)	
39	27		High record number on prime data track (R)	

DTFIS (RETRVE, RANDOM) - part 1 (....Cont'd)

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
40	28			High record number on overflow track (R)
41	29			High record number on shared track (R)
42	2A			High record number on track index track (R)
43	2B			Retrieval byte :
			0	1= WORKR specified
			1	1= WORKS specified
			2	Overflow switch
			3	1= Read key
			4	Not used
			5	1= Output
			6	1= Write key
			7	1= PUT macro issued
44-50	2C-32			Prime data lower limit (MBBCCHH)
51-57	33-39			Cylinder index lower limit (MBBCCHH)
58-64	3A-40			Master index lower limit (MBBCCHH)
65	41			Switches
			0	1= From WAITF routine
			1	1= Seek check from WAITF
			2	1= Index track held
			3	1= Data track held
			4	1= RPS type device (data)
			5	1= RPS type DTF
			6	1= Master index
			7	1= RPS type device (index)
66-73	42-49			Last prime data record address (MBBCCHHR)
74-75	4A-4B			Logical record length
76-77	4C-4D			Key length
78-79	4E-4F			Block size (logical record length times number of records)
80-81	50-51			Overflow record length (logical record length plus 10)
82-83	52-53			Blocking factor
84-85	54-55			Index entry length (key length plus 10)
86-87	56-57			Prime data record length (key length plus physical record length)
88-89	58-59			Overflow record length with key (key length plus logical record length plus 10)
90-91	5A-5B			Prime data record format length (key length plus physical record length plus 8)
92-93	5C-5D			Overflow record format length (key length plus logical record length plus 18)
94-95	5E-5F			Key location (blocked records)

DTFIS (RETRVE,RANDOM) - part 1 (...Cont'd)

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
	96-97	60-61		Constant= 5
	98-99	62-63		Constant= 10
	100-101	64-65		Displacement of part 2 of the DTFIS table from part 1
	102-103	66-67		Displacement of part 3 of the DTFIS table from part 1
&Filename.S	104-113	68-71		Seek/search address area (MBBCCHHRFP)
&Filename.W	114-123	72-7B		Random/sequential retrieval work area

DTFIS (RETRVE,RANDOM) - part 2

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
&Filename.2	0 -3 4	00-03 04	0 1-5 6 7	Address of seek/search address area plus 3 1= Seek check indicated Not used 1= Over/under seek has occurred 1= An error has been found, but a seek check is indicated
	5 -7	05-07		Address of random/sequential retrieval work area
	8 -11	08-0B		Address of IOAREAS
	12-15	0C-0F		Address of IOAREAR
	16-19	10-13		Address of KEYARG
	20-23	14-17		Address of WORKR
	24-27	18-1B		Current sequential I/O area address
	28-31	1C-1F		4-byte NO-OP instruction, or L IOREG, * - 4 if IOREG specified.
	32	20		X'00'= No verify; X'40'= Verify
	33	21		X'08'= Unblocked; X'00'= Blocked
	34	22		R= First prime data record on shared track
	35-39	23-27		Upper limit for sequential retrieval (CCHHR)
	40-41	28-29		H'0'= Blocked records H'2'= Overflow record H'8'= Unblocked records
	42	2A		X'C7'= 2311, 2314 or 2319 X'FF'= 3330, 3340
	&Filename.H	43-47	2B-2F	Initial values for sequential retrieval
	48-55	30-37	Current DASD address for sequential (MBBCCCHR)	
	56-63	38-3F	Current overflow DASD address for sequential (MBBCCCHR).	

DTFIS (RETRVE,RANDOM) – part 2 (...Cont'd)

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
&Filename.T	64-65	40-41		Sequential record counter
	66-67	42-43		Current track index entry for sequential (HR)
	68-69	44-45		Number of records tagged for deletion
	70-71	46-47		Load IOREG for random retrieval
&Filename.G	72-79	48-4F		DASD address save area (MBBCCHHR)
	80-83	50-53		Record pointer within I/O area for write operation
&Filename.R	84-87	54-57		Nonfirst overflow record count
The following information is generated when the cylinder index in core option is specified				
	92-95	5C-5F		A(&INDAREA) – Starting address of main storage area specified for cylinder index
	96-97	60-61		AL2(&INDSIZE) – Number of bytes in main storage available for cylinder index
	98-105	62-69		Next cylinder index entry to be read (MBBCCHHR) (Initialized by \$\$\$INDEX to cylinder index starting address)
	106-110	6A-6E		Last cylinder index entry
	111	6F		Core index byte:
			0	1= First time through transient
			1	1= End of index reached
			2	1= Index skip option
			3-7	Not used
	112-115	70-73		Pointer to key (stored by the module)
	116-131	74-83		Reserved

DTFIS (RETRVE,RANDOM) – part 3

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
&Filename.B	0 -7	00-07		X'07', &Filename.S+1, X'40', 6 - Long seek CCW with command chaining
	8 -63	08-3F		Area to build CCW-string
&Filename.E	64-67 ¹⁾	40-43		First entry in DSKXTN table (logical unit, cell number)
	72-75 ²⁾	48-4B		4X'FF' End of DSKXTN table

- 1) The length of one entry is the four bytes shown here. The minimum number of entries is 2. There is one entry per extent.
- 2) The location of the end-of-table indicator depends on the length of DSKXTN table.

DTFIS (RETRVE,SEQNTL) – part 1

DTF Assembly Label	Bytes		Bits	Function	
	Dec	Hex			
&Filename	0 -15	00-0F		Command Control Block (CCB)	
	16	10	0	Not used	
			1	1= GET issued	
			2	1= COBOL open; ignore option	
			3	1= Track Hold specified	
			4	1= DTF table address constants relocated by OPENR	
			5	1= EOF on sequential retrieve	
			6	1= Data set security	
			7	1= Different blocksize in format 1 label than in DTFIS	
		17-19	11-13		Address of logic module
		20	14		File type for OPEN/CLOSE (X'26'= RETRVE)
	&Filename.C	21	15		Option byte:
			0	Not used	
			1	1= Prime data in core	
			2	1= Cylinder overflow option	
			3	1= Cylinder index in core option	
			4	1= Blocked records	
			5	1= Verify	
			6	1= IOAREAS just used; 0= IOAREA2 just used	
			7	1= 2 I/O areas present	
		22-28	16-1C		File name (DTF name)
		29	1D		Prime data device type: X'00'= 2311 X'01'= 2314/2319 X'04'= 3330 X'08'= 3340 general X'09'= 3340 (35MB) X'0A'= 3340 (70MB)
		30	1E		Status byte:
			0	1= Uncorrectable DASD error (except WLR error)	
			1	1= WLR error	
			2	1= EOF (sequential)	
		3	1= No record found		
		4	1= Illegal ID specified		
		5	1= Duplicate record sensed		
		6	1= Overflow area full		
		7	1= Record retrieved from overflow area		
	31	1F		High level index device type: X'00'= 2311 X'01'= 2314/2319 X'04'= 3330 X'08'= 3340 general X'09'= 3340 (35MB) X'0A'= 3340 (70MB)	
	32	20		Relative position of the DSKXTN (logical unit, cell number) table (in words). This value is the length of the DTF table divided by 4)	
	33-35	21-23		First prime data record in cylinder (HHR)	
	36-37	24-25		Last prime data track in cylinder (HH)	

DTFIS (RETRVE, SEQNTL) – part 1 (...Cont'd)

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
	38	26		High record number on master index/cylinder index track (R)
	39	27		High record number on prime data track (R)
	40	28		High record number on overflow track (R)
	41	29		High record number on shared track (R)
	42	2A		High record number on track index track (R)
	43	2B		Retrieval byte :
			0	1= WORKR specified
			1	1= WORKS specified
			2	Overflow switch
			3	1= Read key
			4	1= First record being processed (after issuing SETL macro)
			5	1= Output
			6	1= Write key
			7	1= PUT macro issued
	44-50	2C-32		Prime data lower limit (MBBCCHH)
	51-57	33-39		Cylinder index lower limit (MBBCCHH)
	58-64	3A-40		Master index lower limit (MBBCCHH)
	65	41		Switches:
			0	1= From WAITF routine
			1	1= WAITF seek check bit
			2-3	Not used
			4	1= RPS type device (data)
			5	1= RPS type DTF
			6	1= Master index
			7	1= RPS type device (index)
	66-73	42-49		Last prime data record address (MBBCCCHR)
	74-75	4A-4B		Logical record length
	76-77	4C-4D		Key length
	78-79	4E-4F		Block size (logical record length times number of records)
	80-81	50-51		Overflow record length (logical record length plus 10)
	82-83	52-53		Blocking factor
	84-85	54-55		Index entry length (key length plus 10)
	86-87	56-57		Prime data record length (key length plus physical record length)
	88-89	58-59		Overflow record length with key (key length plus logical record length plus 10)
	90-91	5A-5B		Prime data record format length (key length plus physical record length plus 8)
	92-93	5C-5D		Overflow record format length (key length plus logical record length plus 18)
	94-95	5E-5F		Key location (blocked records)

DTFIS (RETRVE, SEQNTL) – part 1 (....Cont'd)

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
	96-97	60-61		Constant= 5
	98-99	62-63		Constant= 10
	100-101	64-65		Displacement of part 2 of the DTFIS table from part 1
	102-103	66-67		Displacement of part 3 of the DTFIS table from part 1
&Filename.S	104-113	68-71		Seek/search address area (MBBCCHRFP)
&Filename.W	114-123	72-7B		Random/sequential retrieval work area

DTFIS (RETRVE, SEQNTL) – part 2

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
&Filename.2	0 -3	00-03		Address of seek/search address area plus 3
	4	04	0	1= Seek check indicated
			1-5	Not used
			6	1= Over/under seek has occurred
			7	1= An error has been found, but a seek check is indicated
	5 -7	05-07		Address of random/sequential retrieval work area
	8 -11	08-0B		Address of IOAREAS
	12-15	0C-0F		Address of IOAREA2
	16-19	10-13		Address of KEYARG
	20-23	14-17		Address of WORKR
	24-27	18-1B		Current sequential I/O area address
	28-31	1C-1F		L IOREG,*-4 - Lead IOREG or a 4 byte NO-OP instruction
	32	20		X'00'= No verify; X'40'= Verify
	33	21		X'08'= Unblocked records; X'00'= Blocked rec'ds
34	22		R= First prime data record on shared track	
35-39	23-27		Upper limit for sequential retrieval (CCHHR)	
40-41	28-29		H'0'= Blocked records H'2'= Overflow record H'8'= Unblocked records	
42	2A		X'C7'= 2311, 2314 or 2319; X'FF'= 3330, 3340	
43-47	2B-2F		Initial values for sequential (CCHHR)	
&Filename.H	48-55	30-37		Current DASD address for sequential retrieval (MBBCCHR)
	56-63	38-3F		Current overflow DASD address (MBBCCHR)

DTFIS (RETRVE,SEQNTL) – part 2 (...Cont'd)

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
&Filename.T	64-65	40-41		Sequential record counter
	66-67	42-43		Current track index entry (HR)
	68-69	44-45		Number of records tagged for deletion.
	70-75	46-4B		For boundary alignment.
	76-91	4C-5E		Reserved.

DTFIS (RETRVE,SEQNTL) – part 3

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
&Filename.B	0 -7	00-07		X'07', &Filename.S+1, X'40',6 - Long seek CCW with command chaining
&Filename.E	8 -63	08-3F		Area to build CCW-string
	64-67 ¹⁾	40-43		First entry in DSKXTN table (logical unit, cell number)
	72-75 ²⁾	48-4B		4X'FF' - End of DSKXTN table

1) The length of one entry is the four bytes shown here. The minimum number of entries is 2. There is one entry per extent.

2) The location of the end-of-table indicator depends on the length of DSKXTN table.

DTFIS (ADDRTR) – part 1

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
&Filename	0 -15	00-0F		Command Control Block (CCB)
	16	10	0	Not used
			1	1= GET issued
			2	COBOL open; ignore option
			3	1= Track hold option specified
			4	1= DTF table address constants relocated by OPENR
			5	EOF switch
			6	1= Data set security
			7	1= Wrong blocksize error during addition to file
	17-19	11-13		Logic module address
20	14		File type for OPEN/CLOSE (X'27'= ADDRTR)	
21	15		Option byte:	
		0	Not used	
		1	1= Prime data in core	
		2	1= Cylinder overflow	
		3	1= Cylinder index in core	
		4	1= Blocked records	

DTFIS (ADDRTR) - part 1 (...Cont'd)

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
&filename.C	21 (Cont'd)		5 6 7	1= Verify 1= IOAREAS just used; 0= IOAREA2 just used 1= 2 I/O areas present
	22-28	16-1C		DTF file name
	29	1D		Prime data device type indicator: X'00'= 2311 X'01'= 2314/2319 X'04'= 3330 X'08'= 3340 general X'09'= 3340 (35MB) X'0A'= 3340 (70MB)
	30	1E	0 1 2 3 4 5 6 7	Status byte: 1= Uncorrectable DASD error (except WLR error) 1= WLR error 1= EOF (sequential) 1= No record found 1= Illegal ID specified 1= Duplicate record sensed 1= Overflow area full 1= Record retrieved from overflow area
	31	1F		Highest level index device type: X'00'= 2311 X'01'= 2314/2319 X'04'= 3330 X'08'= 3340 general X'09'= 3340 (35MB) X'0A'= 3340 (70MB)
	32	20		Relative position of the DSKXTN (logical unit, cell number) table (in words). This value is the length of the DTF table divided by 4.
	33-35	21-23		First prime data record in cylinder (HHR)
	36-37	24-25		Last prime data track in cylinder (HH)
	38	26		High record number on master index/cylinder index track (R)
	39	27		High record number on prime data track (R)
	40	28		High record number on overflow track (R)
	41	29		High record number on shared track (R)
	42	2A		High record number on track index (TI) track (R)
	43	2B	0 1 2 3 4 5 6 7	Retrieval byte: 1= WORKR area specified 1= WORKS area specified 2= Overflow switch 1= Read 1= First record being processed (after issuing SETL macro) 1= Output 1= Write key 1= PUT macro issued
	44-50	2C-32		Prime data lower limit (MBBCCHH)

DTFIS (ADDRTR) - part 1 (. . .Cont'd)

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
&Filename.H	51-57	33-39	0 1 2 3 4 5 6 7	Cylinder index lower limit (MBBCCHH)
	58-64	3A-40		Master index lower limit (MBBCCHH)
	65	41		Switches:
				1=From WAITF routine
				1=Seek check from WAITF
				1=Data track held
				1=Index track held
			1=RPS type device (data)	
			1=RPS type DTF	
			1=Master index; 0=Cylinder index	
			1=RPS type device (index)	
	66-73	42-49		Last prime data record address (MBBCCHHR)
	74-75	4A-4B		Logical record length (RECSIZE)
	76-77	4C-4D		Key length (KEYLEN)
	78-79	4E-4F		Block size (logical record length times number of records)
	80-81	50-51		Overflow record length (logical record length plus 10)
	82-83	52-53		Blocking factor (number of logical records in block (NRECS))
	84-85	54-55		Index entry length (key length plus 10)
	86-87	56-57		Prime data record length (key length plus physical record length (block size))
	88-89	58-59		Overflow record length with key (key length plus logical record length plus 10)
90-91	5A-5B		Prime data record format length (key length plus block size plus 8)	
92-93	5C-5D		Overflow record format length (key length plus logical record length plus 18)	
94-95	5E-5F		Key location (KEYLOC) for blocked records	
96-97	60-61		Constant = 5	
98-99	62-63		Constant = 10	
100-101	64-65		Displacement of part 2 of the DTFIS table from start of part 1	
102-103	66-67		Displacement of part 3 of the DTFIS table from start of part 1	
&Filename.S	104-113	68-71		Seek/search address area
&Filename.W	114-123	72-7B		Random/sequential retrieval work area
&Filename.P	124-127	7C-7F		Prime data record count
	128	80	0-1 2 3-5 6 7	Status indicators: Not used 1=File closed Not used 1=Last prime data track full 1=Block complete

DTFIS (ADDRTR) - part 1 (...Cont'd)

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
	129-133	81-85		Last track index normal entry address (CCHHR)
	134-138	86-8A		Last cylinder index entry address (CCHHR)
	139-143	8B-8F		Last master index entry address (CCHHR)
	144-151	90-97		Last independent overflow record address (MBBCCCHR)
&Filename.I	152-153	98-99		Number of independent overflow tracks
&Filename.A	154-155	9A-9B		Number of full cylinder overflow areas
&Filename.O	156-157	9C-9D		Overflow record count
	158-164	9E-A4		Independent overflow area lower limit (MBBCCHH)
	165-171	A5-AB		Independent overflow area upper limit (MBBCCHH)
	172-175	AC-AF		A(&Filename.D) - Address of work area for cylinder overflow control record (COCR)
	176-179	B0-B3		A(&Filename.D+8) - Address of work area for the current track index normal entry count field
	180-183	B4-B7		A(&Filename.D+16) - Address of work area for current track index overflow entry count field
	184-187	B8-BB		A(&Filename.D+24) - Address of work area for current prime data record count field
	188-191	BC-BF		A(&Filename.D+32) - Address of work area for current overflow record count field
	192-195	C0-C3		A(&Filename.D+40) - Address of work area for track index normal entry data field
	196-199	C4-C7		A(&Filename.D+50) - Address of work area for current overflow record sequence-link field
	200-203	C8-CB		A(&IOAREAL) - Address of IOAREAL, the I/O area used for adding records to a file
	204-207	CC-CF		A(&WORKL) - Address of WORKL, work area containing user data records to be added to a file
	208-211	D0-D3		A(&Filename.K) - Address of the ADD key area
	212-215	D4-D7		A(&IOAREAL+8) - Address of key position in IOAREAL
	216-219	D8-DB		A(&IOAREAL+8+&KEYLEN) - Address of data position in IOAREAL

DTFIS (ADDRTR) – part 2

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
&Filename.2	0 -3	00-03		A(&Filename.S+3) – Address of the seek/search address area plus 3
	4	04	0	1= Seek check indicated
			1-5	Not used
			6	1= Over/under seek has occurred
			7	1= An error has been found, but a seek check is indicated
	5 -7	05-07		A(&Filename.W) – Address of the random/sequential retrieval work area
	8 -11	08-0B		Address of IOAREAS, I/O area used for sequential retrieval
	12-15	0C-0F		Address of IOAREAR, I/O area used for random retrieval or address of IOAREA2 (if specified) for sequential retrieval
	16-19	10-13		Address of KEYARG, field containing user supplied key used for random READ/WRITE operations and sequential retrieval initiated by key
	20-23	14-17		Address of WORKR, work area used for random retrieval
	24-27	18-1B		Current sequential I/O area address
	28-31	1C-1F		1) L IOREG, *-4 – Load I/O register for sequential or 2) 4- byte NO-OP instruction for random
	32	20		X'00'= No verify; X'40'= Verify
	33	21		X'00'= Blocked; X'08'= Unblocked
	34	22		R= First prime data record on shared track
	35-39	23-27		Limits for sequential (CCHHR)
40-41	28-29		H'0'= Blocked records H'2'= Overflow records H'8'= Unblocked records	
42	2A		X'C7'= 2311, 2314 or 2319; X'FF'= 3330, 3340	
43-47	2B-2F		Initial values for sequential	
&Filename.H	48-55	30-37		Current sequential DASD address (MBBCCHHR)
	56-63	38-3F		Current overflow DASD address (MBBCCHHR)
	64-65	40-41		Sequential record count
	66-67	42-43		Current track index entry for sequential (HR)
&Filename.T	68-69	44-45		Number of records tagged for deletion
	70-71	46-47		LR &IOREG, 0 for random (or 2-byte NO-OP for sequential)
&Filename.G	72-79	48-4F		DASD address save area for random retrieval (MBBCCHHR)

DTFIS (ADDRTR) - part 2 (...Cont'd)

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
&Filename.R	80-83	50-53		Record pointer within I/O area for write (for random retrieval)
	84-87	54-57		Non-first overflow record count
The following information is generated if the cylinder index in core option is specified. Bytes 88-91 (58-5B) are not used.				
	92-95	5C-5F		A(&INDAREA) - Starting address of main storage area specified for cylinder index
	96-97	60-61		AL2(&INDSIZE) - Number of bytes in main storage available for cylinder index
	98-105	62-69		Next cylinder index entry to be read (MBBCCHR)
	106-110	6A-6E		Last cylinder index entry (CCHHR)
	111	6F		Core index byte:
			0	1= First time through B-transient, \$\$BINDEX
			1	1= End of cylinder index reached
			2	1= Index skip option specified
			3	1= Suppress index in-core option and read cylinder index
			4-7	Not used
	112-115	70-73		Pointer to key (stored by module)
The following information is generated if the prime data in core add function is specified. This information is aligned on a double word boundary. If both cylinder index in core and prime data in core add functions are specified, the following information is found in bytes (116-131) (74-83).				
	116-117	74-75		Size of IOAREAL
	118-119	76-77		Maximum number of prime data records in main storage
	120-123	78-7B		Address of write CCW's
	124-127	7C-7F		Address of read CCW's
	128	80		Switch byte:
			0	1= EOF
			1-7	Not used
	129	81		Reserved.
	130-131	82-83		Work field for I/O module.

DTFIS (ADDRTR) - part 3

DTF Assembly Label	Bytes		Bits	Function
	Dec	Hex		
&Filename.B	0 -7	00-07		X'07', &Filename.St+1, X'40', 6 - Long seek CCW with command chaining
	8 -63	08-3F		Channel program build area
	64-127	40-7F		Channel progr.build area for add function only
&Filename.D	128-135	80-87		Cylinder overflow control record (COCR)
	136-143	88-8F		Current track index normal entry count field
	144-151	90-97		Current track index overflow entry count field
	152-159	98-9F		Current prime data record count field
	160-167	A0-A7		Current overflow record count field
	168-177	A8-B1		Track index normal entry data field
	178-187	B2-BB		Current overflow record sequence-link field
	188-197	BC-C5		Current track index overflow entry data field
	198	C6		X'01' - Add to EOF X'02' - Add to independent overflow area
	199-201	C7-C9		Overflow control bytes (CCH)
	202-203	CA-CB		High HR on overflow track
	204-211	CC-D3		Volume upper limit for prime data records (MBBCCHHR)
	212-217	D4-D9		CLC 0(&KEYLEN, 13),0(6) - Unblocked CLC 0(&KEYLEN, 13), &KEYLOC-1(6) - Blocked Utility CLC for key
	218-223	DA-DF		MVC 0(&KEYLEN, 13),0(12) - Unblocked MVC 0(&KEYLEN, 13), &KEYLOC-1(12) - Blocked Utility MVC for key
	&Filename.E	224-227 ¹⁾	E0-E3	
232-235 ²⁾		E8-EB		4X'FF' - End of DSKXTN table
&Filename.K	236 ⁺	EC-end		Key area for add only. Number of bytes depends on key length, KEYLEN

- 1) Each entry in the DSKXTN table is four bytes long. The minimum number of entries is 2. There is one entry per extent.
- 2) Location of the end-of-table indicator depends on length of DSKXTN table.

DTFDU

Bytes		Bits	Contents	Function
Dec	Hex			
0–15	0–F			Command Control Block (CCB)
16	10	0–3	B'0000'	Not used
		4		1=DTF relocated by OPENR
		5–7	B'000'	Not used
17–19	11–13			Address of logic module
20	14		X'1A'	DTF type for OPEN/CLOSE
			X'21'	(X'1A'=diskette file) (X'21'=DTFPH)
21	15	0		1=Command chained file
		1–2	B'00'	Not used
		3		1=Work area specified
		4	B'0'	Not used
		5		1=Open; 0=Close
		6		1=Input; 0=Output
		7		Not used
22–28	16–1C			Filename
29	1D		X'06'	Device type code (X'06'=3540)
30–35	1E–23		C'00CHR00'	Address of HDR1 label in VTOC
36–37	24–25			Volume sequence number
38	26			Open communications byte
				<u>Input File</u>
		0		1=No more extents
		1–2	B'00'	Not used
		3		1=Exit for user's EOF routine
		4		1=Next extent on new volume
		5–6		Not used
		7		1=Extent switch
				<u>Output File</u>
		0		1=No more extents
		1		1=Extents needed at Close time
		2–3	B'00'	Not used
		4		1=Next extent on new volume
		5		1=Extent entered via console
		6–7		Not used
39	27	0		1=Extent bypassed before file opened (input)
		0–7		Sequence number of current extent opened (output)
40	28			Sequence number of last extent opened
41–43	29–2B		X'000000'	Reserved
44–47	2C–2F			Address of IOAREA1
48–51	30–33			Address of last Read/Write CCW in chain
52–53	34–35		X'0001'	Lower record limit
54–57	36–39		X'00CC00RR'	End-of-data seek address (last record + 1)
58–59	3A–3B			Number of records in I/O area (used in short chain processing)
60–53	3C–3F		X'00FF0001'	Seek argument (OCHR)
64–67	40–43			End-of-file routine address (input); 4X'00' (output)
68–71	44–47		X'0049001A'	Seek argument control field
72	48			Command chaining factor

DTFDU (...Continued)

Bytes		Bits	Contents	Function
Dec	Hex			
73	49	0	B'0'	Switch byte 1.
		1		1=Not first entry after open.
		2		Not used.
		3		1=In close routine (output).
		4		1=Error chain to be skipped.
74-75	4A-4B	5-7	B'000'	1=End of extent. Not used.
76-80	4C-50		X'FFFFFFFF'	(record size multiplied by command chain factor)-1.
81-83	51-53		X'000000'	Seek argument bucket.
84-87	54-57			Reserved.
88-91	58-5B			Instruction to load user's I/O register (or NOP).
92-95	5C-5F			Address of current I/O area.
96-99	60-63			Logical record size.
100	64			Address of last byte of the I/O area.
		0		Logical indicators.
		1		1: ERROPT=address.
		2		1: ERROPT=IGNORE.
		3		1: ERROPT=SKIP.
		4		Not used.
		5-7		1=Two I/O areas. Not used.
101-103	65-67			Address of user's error handling routine.
104	68			CCW count (write command only).
105	69			Allowed operations
		0		1=Allow read commands.
		1		1=Allow write commands.
		2		1=Suppress unit check on C4/C6.
		3-7	B'00000'	Not used.
106	6A		X'00'	Sector factor (X'00'=128).
107	6B		X'00'	Reserved.
108	6C	0		1=Write protect.
		1		1=No feed at EOF.
		2		1=Check multivolume sequence.
		3		1=Multivolume file.
		4		1=Verify requested.
		5		1=C6s written (update ERMAP)
		6		1=Read/Write security.
		7	B'0'	Not used.
109-111	6D-6F		X'000000'	Not used.
112-119	70-77			Feed CCW.
120-127	78-7F			Define ops CCW (output); 8X'00' (input).
128-135	80-87			Seek CCW.
136-143	88-8F			TIC CCW.
144-X	90-Y		X=143+8*(# of CCWs)	Read/Write data CCWs, 1, 2, 13, or 26.
			Y=8F+8*(# of CCWs)	Read/Write CCWs.
X+1	Y+1			NOP CCW (output only).

DTFPH (Magnetic Tape)

Bytes		Bits	Contents	Function
Dec	Hex			
0 - 15	00-0F			CCB
16	10	0-1		Not used
		2		COBOL open; ignore option
		3		Not used
		4		DTF Table address; constants relocated by OPENR
		5		Not used
		6		1= ASCII 0= EBCDIC
		7		Not used
17-19	11-13		3X'00'	
20	14		X'12'	Standard labeled, output
			X'14'	Standard labeled, input, forward
21	15	0-3		Not used
		4		1= input; 0= output
		5-7		Not used
22-29	16-1D			Symbolic filename
30	1E			Not used
31	1F	0-4	B'01100'	Used as displacement by OPEN
		5		
		6-7		Reserved
32	20	0		1= Standard labels
		1-2		Not used
		3		1= No rewind
		4		Not used
		5		User label address; 1= yes, 0= no
		6-7		Not used
33-35	21-23			User label routine address
36	24	0		1= DTFPH table
		1		Not used
		2		File switch: 1= input, 0= output
		3		Not used
		4		1= EOF switch
		5-7		Not used
37-39	25-27			User label exit
40-43	28-2B		DC F'0'	Reserved for OPEN
44-87	2C-57			EOV routine
88-89	58-59		DC 2X'00'	Reserved for OPEN
90-95	5A-5F		DC 6X'00'	File serial number
96-99	60-63		DC 4X'00'	Volume sequence number
100-103	64-67		DC 4X'00'	File sequence number

DTFPH (Sequential Disk)

Bytes		Bits	Function
Dec	Hex		
0-15	00-0F		CCB
16	10	0	1=Dequeue old volume extents
		1	Not used
		2	1=File assigned 'IGN' (COBOL)
		3	Not used
		4	1=DTF relocated by OPENR
		5-7	Not used
17-19	11-13		3X'00'
20	14		DTF type (X'21')
21	15		Open/Close indicators
		0	Not used
		1	1=Blocked files
		2	1=Work file
		3	1=Work area
		4	1=Not version 1 table type
		5	1=Open; 0=Closed
		6	1=Input; 0=Output
		7	1=User labels specified
22-28	16-1C		Filename (see byte 29)
29	1D		Device type code: X'00'=2311 X'01'=2314,2319 X'04'=3330-1,-2 X'05'=3330-11 X'07'=3350 X'08'=3340 general X'09'=3340 35MB X'0A'=3340 70MB X'90'=FBA device
30	1E		C'F'=EOF indicator for DTFPH
30-35	1E-23		(BCCHHR) Address of F1 label in VTOC (output) (BCCHHR) Address of next DLBL-EXTENT record (input)
36-37	24-25		Volume sequence number
38	26		Open communication byte: <u>Output</u>
		0	1=No more EXTENTS
		1	1=EXTENTS for LIOCS at close
		2	1=Process trailer labels
		3	1=Process header labels
		4	1=New extent on next volume
		5	1=EXTENTS entered via console
		6	1=Process trailer labels at close
		7	1=Check EXTENT for minimum of 2 tracks
			<u>Input</u>
		0	1=No more EXTENTS
		1	Not used
		2	1=No F1 label, process EXTENTS only
		3	Not used
		4	1=New volume on next EXTENT
		5	Not used
		6	1=Process header labels
		7	Not used
39	27		Sequence number of current EXTENT being opened

DTFPH (Sequential Disk) (. . . Cont'd)

Bytes		Bits	Function
Dec	Hex		
40	28		Sequence number of last EXTENT opened (not a console EXTENT entry)
41-43	29-2B		Address of user's label routine
44	2C	2	1=Version 3 DTF
45-47	2D-2F		Not used
48-51	30-33		CCHH address of user's label track. Initially X'80000000'
52-53	34-35		Lower head limit (HH) X'0000' if type 1; X'00nn' if type 128 (n=head limit)
54-57	36-39		EXTENT upper limit (CCHH)
58-59	3A-3B		BB seek address: X'0000' if disk device
60-63	3C-3F		EXTENT lower limit (CCHH)
64	40		Record number: 1=Input; 0=Output
65-67	41-43		Not used
68-71	44-47		CCHH control bucket CCHH=X'00C80009' if 2311 - type 1 CCHH=X'00C80013' if 2314 or 2319 - type 1 CCHH=X'01940012' if 3330 - type 1 CCHH=X'03280012' if 3330-11 - type 1 CCHH=X'015C000B' if 3340 35MB CCHH=X'02B8000B' if 3340 70 MB CCHH=X'022B001D' if 3350 - type 1 PBN=Maximum block size if FBA device
72	48		Record number
73	49		Not used
74-75	4A-4B		Not used
76-80	4C-50		CCHHR bucket=extent lower limit and record number
81-83	51-53		Not used

Note: Where nn = current upper head number

DTFPH (DAM FILES)

Bytes		Bits	Function
Dec	Hex		
0–15	0–F		CCB
16	10		X'08' indicates DTF relocated by OPENR
17–19	11–13		3X'00'
20	14		DTF type (X'23')
21	15		Option codes
		0	1=Output; 0=Input
		1–7	Not used
22–28	16–1C		Filename
29	1D		Device type code: X'00'=2311 X'01'=2314, 2319 X'04'=3330-1, -2 X'05'=3330-11 X'07'=3350 X'08'=3340 general X'09'=3340 35MB X'0A'=3340 70MB
30–31	1E–1F		Logical unit address of first volume containing the file
32	20		Not used
		1	1=Device supports RPS
		2	1=Version 3 DTF
		3–7	Reserved for future use
33–35	21–23		Address of user label routine
36–39	24–27		Address of user routine to process EXTENT information

DTFPH (DISKETTE)

Bytes		Bits	Function
Dec	Hex		
0-15	0-F		CCB
16	10	0	1=Dequeue old volume extents
		1-3	Not used
		4	1=DTF relocated by OPENR
		5-7	Not used
17-19	11-13		3X'00'
20	14		DTF type (X'21')
21	15		Open/close indicators
		0-2	Not used
		3	1=Work area
		4	1=Not version 1 DTF table type
		5	1=Open; 0=Closed
		6	1=Input; 0=Output
		7	Not used
22-28	16-1C		Filename (see byte 29)
29	1D		Device type code (3540=X'06')
30	1E		C'F'=EOF indicator for DTFPH
30-35	1E-23		(0CHR00) Address of HDR1 label in VTOC (output)
36-37	24-25		Volume sequence number
38	26		Open communications byte
			<u>Input</u>
		0	1=No more extents
		1-3	Not used
		4	1=New volume or new extent
		5-7	Not used
			<u>Output</u>
		0	1=No more extents
		1	1=Extents for LIOCS at close
		2-3	Not used
		4	1=New volume on next extent
		5	1=Extents entered via console
		6	Not used
		7	1=Check extent for minimum of 2 tracks
39	27		Sequence number of current extent being opened
40	28		Sequence number of last extent opened (not a console extent entry)
41-43	29-2B		Not used
44-47	2C-2F		Address of IOAREA1
48-51	30-33		Not used
52-53	34-35		X'0000'
54-57	36-39		Extent upper limit (0CHR)
58-59	3A-3B		Not used
60-63	3C-3F		Extent lower limit (0CHR)
64	40		Record number
			1=Input; 0=Output
65-67	41-43		Not used

DTFPH (DISKETTE) (. . . Cont'd)

Bytes		Bits	Function
Dec	Hex		
68–71	44–47		OCHR control bucket OCHR=X'0049001A' for 3540 (output only)
72	48		Record number
73	49		X'10' - multivolume file (input) X'40' - last volume on multivolume file (input) X'80' - verify requested
74	4A		Record size (maximum of 128)
75	4B		Not used
76–80	4C–50		OCHR bucket = extent lower limit and record number (output)
81–83	51–53		Not used

DTFDI

Bytes		Bits	Function
Dec	Hex		
0-15	00-0F		CCB. If the file is on a DASD, the CCW address in bytes 9-11 (09-0B) is changed by OPEN to point to the DTF extension an RPS CCW string in the user virtual area. CLOSE restores it. If 3800 extended buffering is selected, the CCW address is changed by OPEN to point to a DTF extension work area in the user virtual area. CLOSE restores it.
16	10	0-1 2 3 4 5-7	Not used COBOL open; ignore option Not used DTF table address constants relocated by OPEN Not used
17-19	11-13		Address of logic module. If the file is on a DASD, OPEN changes this address to point to the logic module in the system virtual area. CLOSE restores it. If 3800 extended buffering is selected, OPEN changes the address to point to the extended buffering logic module IJDP3 in the system virtual area. CLOSE restores it.
20	14		DTF Type=X'33'
21	15	0	Open/Close indicators - X'82'=Input; X'80'=Output Always set on for no rewind
22-28	16-1C		Symbolic filename
29	1D		DASD or diskette device indicators X'00'=2311; X'01'=2314, 2319; X'04'=3330-1, -2 X'05'=3330-11; X'07'=3350; X'08'=3340 general X'09'=3340 35MB; X'0A'=3340 70MB; X'90'=FBA device
30-35	1E-23		DASD address of format 1 label
36-37	24-25		DASD or diskette volume sequence number
38	26	0 1-3 4 5-7	Open communications switch 1=No more extents - diskettes Not used Always 1 Not used
39	27		Sequence number of current extent
40	28		Sequence number of last extent, or X'80' for 1442 reader punch
41	29		Open indicator = X'20'
42	2A	0 1 2 3 4 5 6 7	Device type indicators: Unused 1=DTF has been extended into the partition GETVIS area 2=DASD 3=tape 4=printer 5=punch 6=reader 7=RPS supported
43	2B		Logic module device indicators: X'F3' = DASD or diskette device X'F1' = reader or tape device X'F0' = other type devices

DTFDI (. . . Cont'd)

Bytes		Bits	Function
Dec	Hex		
44	2C	0	Logic module option switches
		1	1=Input; 0=Output
		2	1=eject for RDR-PCH; 0=no eject
		3	1=not first pass; 0=first pass
		4	1=two I/O areas; 0=one I/O area
		5	1=2540 Punch
		6	1=SYSLST/SYSPCH
		7	1=Tape SYSLST/SYSPCH
45-47	2D-2F		Alternate I/O area address
48	30	0-1	Reserved for future use
		2	1=Version 3 DTF
		3-4	Reserved
		5	1=TRC=YES specified on DTF
		6	1=TRC in effect
		7	1=3800 printer
49-51	31-33		Reserved
52-53	34-35		Extent lower head limit
54-57	36-39		Extent upper head limit
58-64	3A-40		DASD seek address. Diskette seek address at byte 60 (3C).
65-67	41-43		Users EOF address
68-72	44-48		Control bucket CCHHR. Byte 72 (48) always X'01' for diskettes.
73	49		Logic module switches
			X'01'=Input; X'00'=Output;
			X'00'=both input and output on diskettes
74-75	4A-4B		Logic module constants
			X'0020' DASD output
			X'0018' DASD input
			X'0008' Diskette devices
			X'0000' Non-DASD devices
76-80	4C-50		Count field CCHHR (0CHR0 for diskettes); not used for FBA DASD
81	51		Key length
82-83	52-53		Data length
84-87	54-57		Instruction to load IOREG with correct I/O area address
88-103	58-67		Seek, Search CCWs; not used for FBA DASD
			Seek, Read/Write CCW for diskette files
104-111	68-6F		TIC CCW
			NOP CCW for diskette output files; unused for diskette input files
112-119	70-77		Input/output CCW
120-127	78-7F		Second output CCW
128-151	80-97		Verify CCWs for output
152-159	98-9F		Error CCW1
160-167	A0-A7		Error CCW2
168-231	A8-E7		Save area (64 bytes)
232-235	E8-EB		DC A(WLRERR) if WLRERR=Address
			B 28(15) if ERROPT=omitted
			B 25(15) if ERROPT=SKIP
			B 28(15) if ERROPT=IGNORE
236-239	EC-EF		DC A(ERROPT) if ERROPT=Address
			B 0(15) if ERROPT=omitted
			B 24(15) if ERROPT=SKIP
			B 28(15) if ERROPT=IGNORE

DTFCP (DISK=YES)

Bytes		Bits	Function
Dec	Hex		
0-15	00-05		CCB. If the file is on a DASD device, the CCW address in bytes 9-11 (09-0B) is changed by OPEN to point to a DTF extension in the user virtual save area. CLOSE restores it. If 380J extended buffering is selected, the CCW address is changed by OPEN to point to a DTF extension work area in the user virtual area. CLOSE restores it.
16	10	0	Not used
		1	Set by Maint; indicates that LIOCS must retrieve extents from the VTOC instead of the label cylinder.
		2	COBOL open; ignore option
		3	X'10' indicates an unlabeled FORTRAN tape
		4	DTF table address constants relocated by OPENR
		5	Used by FORTRAN (Sequential Disk Backspace and Rewind)
		6	1=ASCII; 0=EBCDIC
17-19	11-13	7	FORTRAN is calling DTFCP
			Logic module address. If the file is on a DASD device, OPEN changes this address to point to the logic module residing in the system virtual save area. CLOSE restores it. If 380J extended buffering is selected, OPEN changes this address to point to the extended buffering logic module IJDP3 in the system virtual area. CLOSE restores it.
		20	DTF type X'32' except in the case of disk assigned to units other than SYSLNK. In this case, DTFCP open changes it to X'20'.
		21	Open indicators: X'02' input, X'00' output, except for tapes assigned to SYS000 to SYSnnn when X'00'=input and X'08' is output
			X'08' DISK=YES indicator
			1=no rewind; 0=rewind
			0
22-28	16-1C		Device type code:
29	1D		X'00'=2311
			X'01'=2314, 2319
			X'04'=3330-1, -2
			X'05'=3330-11
			X'07'=3350
			X'08'=3340 general
			X'09'=3340 35MB
			X'0A'=3340 70 MB
			X'45'=3800 with TRC
			X'90'=FBA device
30-35	1E-23		File address for disk; block count if bit 7 of byte 16 is on
36-37	24-25		Volume sequence number or work area
38	26		Open switch
39	27		Sequence number of current extent
40	28		Sequence number of last extent, or X'80' if 1442 punch
41	29		X'80' indicates request for standard label tape OPEN
42	2A		X'80' device is a 2560
			X'40' DTF has been extended into the user virtual save area
			X'20' device is a DASD
			X'10' device is a tape
			X'08' device is a printer
			X'04' device is a punch
			X'02' device is a reader
			X'01' RPS is supported

DTFCP (DISK=YES) (. . . Cont'd)

Bytes		Bits	Function
Dec	Hex		
43	2B		X'F3' device is a DASD X'F1' device is a reader X'F0' device is other type
44	2C	0	1=input; 0=output
		1	1=eject needed for a reader punch; 0=no eject
		2	0=first pass; 1=not first pass
		3	1=two I/O areas; 0=one I/O area
		4	1=2540 punch
		5	1=SYSLST or SYSPCH
		6	1=SYSLST or SYSPCH on output tape
		7	1=TLBL is present and type is labeled
45-47	2D-2F		IOAREA2 address
48	30	0	1=Always on
		1	Reserved for future use
		2	1=Version 3 DTF
		3-7	Reserved for future use
49-51	31-33		Reserved for future use
52-53	34-35		Lower head limit
54-57	36-39		Extent upper limit
58-64	3A-40		BBCCHHR seek address or physical block number for FBA-DASD
65-67	41-43		EOF address
68-71	44-47		Control bucket CCHH; not used for FBA DASD
72	48		Number of record per track for output, number of record per track + 1 for input
73	49		X'00' for output, X'01' for input
74-75	4A-4B		X'0020' for output;
			X'0018' for input for DASD
			X'0008' for 2560 and 5424/5425 output
			X'0000' for nondisk device
76-80	4C-50		CCHHR for count field; not used for FBA DASD
81	51		Key length
82-83	52-53		Data length
84-87	54-57		Instruction to load user I/O area address to I/O register
88-111	58-6F		Seek, search, TIC CCWs; not used for FBA DASD
112-119	70-76		CCW for DASD input and first CCW for DASD output; not used for FBA DASD. This CCW can be used for other device if unit is not a DASD.
End-of-table if DTF is defined for an input file			
120-127	77-7F		Second CCW for output
128-151	80-97		Verify CCWs for output
End-of-table if DTF is defined for output file and DEVADDR does not equal SYSPCH			
152-159	98-9F		2540 punch error recovery CCW1
160-167	A0-A7		2540 punch error recovery CCW2
168-231	A8-E7		Reserved
When the CP open initializes the table and determines that the device is a 2540 punch, the following bytes in the table are changed:			
30	1F		X'FF' indicator to DTFCP open phases and logic module
32-35	20-23		Instruction to load user I/O area to I/O register
48-55	30-37		CCW

DTFCP (DISK=YES) (. . .Cont'd)

Bytes		Bits	Function
Dec	Hex		
56-63	38-3F		2540 punch error recovery CCW 1
64-71	40-47		2540 punch error recovery CCW 2
72-151	48-97		80-byte card image, savearea 1
152-231	98-E7		80-byte card image, savearea 2
When the CP open initializes the table and determines that the device is a 2560 or 5424/5425, the following bytes in the table are changed:			
32-35	20-23		Instruction to load user I/O area to I/O register
48-55	30-37		First output CCW
56-63	38-3F		Second output CCW
64	40		Stacker select character V for ASCII
65	41		Stacker select character W for EBCDIC

DTFCP (DISK=NO)

Bytes		Bits	Function
Dec	Hex		
0-15	00-0F	0-1 2 3 4 5 6 7	CCB.
16	10		Not used.
			COBOL open; ignore option.
			Not used.
			DTF table address constants relocated by OPENR.
			Not used.
			1=ASCII (used only if DISK=YES), 0=EBCDIC (used only if DISK=YES).
17-19	11-13		FORTTRAN is calling DTFCP.
20	14		Logic module address.
			DTF type X'32' except in the case of tape assigned to units SYS000 to SYSnnn. In this case, a DTFCP open phase changes it to X'10'.
21	15		Open indicators X'02' input, X'00' output (except for tapes assigned to SYS000 to SYSnnn when it is X'00' input, X'08' output).
22-28	16-1C		Filename (see byte 29).
29	1D		Device type code: X'45'=3800 with TRC
30	1E		Indicator to DTFCP open phase and logic module. X'FF' for input files. X'00' for output files.
31	1F		Reserved for future use.
32-35	20-23		Instruction to load user's I/O area address into I/O register.
36-37	24-25		Volume sequence number or work area.
38	26		Open switch.
39	27		Sequence number of current extent.
40	28		Sequence number of last extent, or X'80' if 1442 punch.
41	29		X'20'.
42	2A		X'80' device is a 2560. X'40' device is a 5424/5425. X'10' device is a tape. X'08' device is a printer. X'04' device is a punch. X'02' device is a reader.
43	2B		X'F1' device is a reader or tape. X'F0' device is other type.
44	2C	0	1=input, 0=output.
		1	1=eject needed for a reader-punch, 0= no eject.
		2	1=not first pass, 0=first pass.
		3	1=two I/O areas, 0=one I/O area.
		4	1=2540 punch.
		5	1=SYSLST or SYSPCH.
		6	1=SYSLST or SYSPCH on output tape.
		7	Reserved for future use.
45-47	2D-2F		IOAREA2 address.
48-55	30-37		CCW.

End-of-table if DTF is defined as output file and DEVADDR is not equal to SYSPCH.

DTFCP (DISK=NO) (. . .Cont'd)

Bytes		Bits	Function
Dec	Hex		
End-of-table if DTF is defined as output file and DEVADDR is not equal to SYSPCH			
56-63	38-3F		2540 punch error recovery CCW 1
64-71	40-47		2540 punch error recovery CCW 2
65-67	41-43		EOF address, input only
End-of-table if DTF is defined as input file			
72-151	48-97		80-byte card image, save area 1
152-231	98-E7		80-byte card image, save area 2
If the device is a 2560 or 5424/5425, bytes 56 onward contain the following information			
56-63	38-3F		Second output CCW
64	40		Stacker select character V for ASCII
65	41		Stacker select character W for EBCDIC
66-75	42-4B		Reserved for future use
76-235	4C-EB		First I/O area
236-237	EC-ED		Reserved
238-317	EF-13D		Second I/O area
318-319	13E-13F		Reserved

DTFCP (DISK=PARAMETER OMITTED)

Bytes		Bits	Function
Dec	Hex		
0–15	00–0F		CCB
16	10	0–1	Not used
		2	COBOL open; ignore option
		3	Not used
		4	DTF table address constants relocated by OPENR
		5	Not used
		6	1=ASCII (used only if DISK=YES); 0=EBCDIC (used only if DISK=YES)
		7	Used by FORTRAN
17–19	11–13		Logic module address
20	14		DTF type X'31' except in the case of tape assigned to units SYS000 to SYSnnn. In this case DTFCP open phase changes it to X'10'.
21	15		Open indicators X'02' input, X'00' output (except for tapes assigned to SYS000 to SYSnnn when it is X'00' input, X'08' output).
22–28	16–1C		Filename
29	1D		Device type code: X'45'=3800 with TRC
30	1E		X'00' indicator to DTFCP open phases and logic module
31	1F	0	1=input; 0=output
		1	1=eject needed for a read punch; 0=no eject
		2	1=not first pass; 0=first pass
		3	1=two I/O areas; 0=one I/O area
		4	1=2540 punch
		5	1=SYSLST or SYSPCH
		6	1=SYSLST or SYSPCH on output tape
		7	1=TLBL specified and tape is labeled
32	20		Open indicators
33–35	21–23		IOAREA2 address
36–39	24–27		Instruction to load user's I/O area address into I/O register
40–47	28–2F		CCW
End of table if DTF is defined as output file and DEVADDR is not equal to SYSPCH			
48–55	30–37		2540 punch error recovery CCW 1
56–63	38–3F		2540 punch error recovery CCW 2
57–59	39–3B		EOF address, input only
End of table if DTF is defined as input file			
64–143	40–8F		80-byte card image, save area 1
144–223	90–13F		80-byte card image, save area 2
For 2560 and 5424/5425, bytes 48 onwards contain the following information:			
48–207	30–CF		IOAREA1
208–209	D0–D1		Reserved
210–369	D2–171		IOAREA2
370–371	172–173		Reserved
372–451	174–1C3		Compare area

DTF - Table Types


DTF Type Code (Byte 20) of DTF Table	DTF	Description
X'00'	DTFCD	Combined files
X'01'	DTFPT	Paper tape files
X'02'	DTFCD	Reader and 3881 Optical Mark Reader files
X'03'	DTFCN	Console
X'04'	DTFCD	Punch files
X'05'	DTFCD	Reader files on 2560, 5424/5425
X'07'	DTFPR	Printer files on 2560
X'08'	DTFPR	Printer files
X'09'	DTFOR	Optical Reader files except 3881 and 3886 files
X'0A'	DTFOR	Optical Reader files (HEADER=YES)
X'0B'	DTFMR	Magnetic Ink Character Recognition (MICR) and Optical Reader/Sorter files
X'0C'	DTFDR	3886 Optical Character Reader files
X'10'	DTFMT	Magnetic tape workfiles
	DTFCP	Magnetic tape workfiles (compiler). (Note 1)
X'11'	DTFMT	Nonstandard or unlabeled tape files
X'12'	DTFMT	Standard labeled, output tape files
	DTFPH	Standard labeled, output tape files (physical IOCS)
X'13'	DTFMT	Standard labeled, input tape files (read backward)
X'14'	DTFMT	Standard labeled, input tape files (read forward)
X'1A'	DTFDU	Diskette Input/Output Unit files
X'20'	DTFSD	Sequential DASD workfiles and data files
	DTFCP	DASD workfiles (compiler)
X'21'	DTFPH	Sequential DASD files, MOUNTED=SINGLE (physical IOCS)
X'22'	DTFDA	Direct access files
X'23'	DTFPH	Direct access files, MOUNTED=ALL (physical IOCS)
X'24'	DTFIS	Indexed sequential, LOAD file
X'25'	DTFIS	Indexed sequential, ADD file
X'26'	DTFIS	Indexed sequential, RETRVE file
X'27'	DTFIS	Indexed sequential, ADDRTR file
X'28'	ACB	Access Method Control Block for VSAM
X'30'	DTFCP	Compiler file for DOS Version 1 (Note 1)
X'31'	DTFCP	Compiler file for DOS Versions 2 onward
X'32'	DTFCP	Compiler file for DOS Versions 2 onward (Note 2)
X'33'	DTFDI	Device independent system unit files
X'40'	DTFBT	Basic Telecommunication Access Method (BTAM) file (Note 3)
X'60'–X'67'		

Notes


- DTF type is X'30' except for tape or DASD assigned to units SYS000 to SYSnnn. In this case, the DTFCP open phases change the DTF type to X'10' for tape workfiles, or X'20' for DASD workfiles.
- DTF type is X'32' except for DASD assigned to units SYS000 to SYSnnn. In this case, the DTFCP open phases change the DTF type to X'20' for DASD workfiles.
- The following control unit codes are ORed into the low-order 4 bits of the DTF type code.

Control Unit	Code
7770	1
2848	3
2701	4
2702	5
2703	6

RPS DTF/MODULE RELATIONSHIP



RPS DTF or DAM DASD Device Independent Extension



CHAPTER IV
VSE/AF2 SUPERVISOR CONTROL BLOCKS AND AREAS



SUPERVISOR STORAGE ALLOCATION

Generation Macro	Macros Called	Generated Code	Base Registers Used	
IOTAB	SGEND	DSECTS, EQUATES.		
	SGLOWC	Hardware/Software Interface (PSW's, Logout Areas, etc.).	R0	
	SGNUC	Interrupt Handler, Job Accounting In-Line Routine.	R13	
	SGSVC	Various SVC Routines		R13
		Various Constants and Tables must be below 8K. CRTGEN, PIB Tables, Exit Tables, I/O Tables, Foreground Communication Regions etc., having Y-Type Address Pointer in Low Storage, must be below 32 K.		R0
	SMICR	(DTSVADLID) ICCF pseudo partition validation		R0
		External Interrupt Handler		R14
	SGEFCH	C-Transient, B-Transient, and A-Transient Area		–
		FTTAB and SSLD Initialization.		R9
	DISP	Task Selection.		R6
		(DTS VALID) ICCF interactive part. validation.		R0
	SGAFCH	Fetch Data Section (CCWs, Control Blocks).		–
	SGDFCH	Fetch Overall Logic and Directory Search		R9
	SGCCWT	CCW Translation for 370 Mode.		R8, R9
		(DTSVALID CALL=CCWT) ICCF interactive partition validation.		R8, R9
	SGCCWF	CCW Analysis and Fixing Routine for ECPS:VSE Mode.		R8, R9
		(DTSVALID CALL=CCWT) ICCF interactive partition validation.		R8, R9
	SGPCK	Program Check Handler		R13
		(DTSMCIC) ICCF Monitor Call intercept routine.		R14
	SGPMR	Page Manager.		R9
		(SGPLLEV) Load Leveller.		R15
		(SGPFIX) Fixing Routines.		R9
		(SGPOPT) Page in SVCs.		R9
		(SGPDATA) Data for Page Manager.		R8
	ASYCODE	Asynchronous operator communication routine.		R9
	SGSVCX	Various SVC Routines.		R13
	MCRAS	Machine/Channel Check Handler, RTA.		R15
	SGSCVRT	RPS Convert Routine.		R9
	SGIOS	SVC0 (EXCP) and SVC 15 (SYSIO) Routines.		R13
		(SGSCHED) Channel Scheduler Routine.		R13
		(IOINTER) I/O Interrupt Handler.		R9
		(SGDSK) Disk Error Recovery Routine.		R13
		(SGSERI) Service Task Interface and Data.		R12
SGCFCH	Fetch SVC Routines.		R13	
SGERP	Interface to ERP Transients.		R13	
SGAP	Asynchronous processing SVC routines.		R13	
SGTINF	Tasking Interface routines.		–	
DTSSVCIC	ICCF SVC intercept routine.		R14	
DTSSVCIN	ICCF SVC routine.		R14	
SGRM	Resource Management SVC Routines.		R13	
	Tasking Control Blocks.		–	
SGLOCK	LOCK, UNLOCK Routines.		R13	

Note:

Other generation macros like PIOCS, FOPT, etc. only set globals but do not generate code.

SUPERVISOR STORAGE ALLOCATION (Cont'd)

Generation Macro	Macros Called	Generated Code	Base Registers Used
IOTAB (Cont'd)	SGAM	CDLOAD, GETVIS, and FREEVIS Routines.	R14
	SGBFCH	IDRA Area and Program Fetch.	R9
	SGSM	Allocate and Setlimit SVC Routines.	R13
	SGPREAL	Get/Free Real Storage for 370.	R9
	SGSER	AVR Task and SVC Routines.	R13
		SGSLDUP, SLD update routine, DASD sharing only.	R14
	SGXECB	Cross Partition Common SVC Routines.	R13
	SGACCT	GETJA SVC Routine.	R13
	SGINF	Logical SV/PP Common SVC Routines.	R12
	SGATAB	Tables having A-Type Address Pointers in low Storage (CRTSAV, SDAGDT, ISTAVT, DTSVECTB, SCYVECTB)	—
IPL Initialization Routine. CCW Translation Copy Buffers.		R7, R9	

Note:

Other generation macros like PIOCS, FOPT, etc. only set globals but do not generate code.

SUPERVISOR CALLS

SVC		Macro supported	Function
Dec	Hex		
0	0	EXCP	Execute Channel Program.
1	1	FETCH	Fetch any phase, except a transient phase.
2	2		Fetch a logical transient (B-transient).
3	3		Quiesce I/O
4	4	LOAD	Load any phase.
5	5	MVCOM	Modify partition communication region (if issued by MVCOM macro). Fetch another physical transient (if issued by a physical transient).
6	6	CANCEL	Cancel a problem program or task.
7	7	WAIT	Wait for a CCB (or IORB) or TECB.
8	8		Transfer control to the problem program from a logical transient (B-transient).
9	9	LBRET	Return to a logical transient (B-transient) from the problem program after an SVC 8.
10	A	SETIME	Set timer interval.
11	B		Return from a logical transient (B-transient).
12	C		Reset Switches in Part. COMREG
13	D		Set Switches in Part. COMREG
14	E	EOJ	Cancel job and go to job control for end of job step.
15	F	SYSIO	Headqueue I/O request and execute channel program.
16	10	STXIT(PC)	Provide supervisor with linkage to user's PC routine for program check interrupts.
17	11	EXIT(PC)	Return from user's PC routine.
18	12	STXIT(IT)	Provide supervisor with linkage to user's IT routine for interval timer interrupts.
19	13	EXIT(IT)	Return from user's IT routine.
20	14	STXIT(OC)	Provide supervisor with linkage to user's OC routine, for external or attention interrupts (operator comm.).
21	15	EXIT(OC)	Return from user's OC routine.
22	16		Seize/Release system; Enable/disable external and I/O interrupts; Set key in user's PSW.
23	17		Store the load address of a phase at a defined user address.
24	18	SETIME	Set timer interval and provide supervisor with linkage to user's TECB, if any.
25	19		Issue HALT I/O on a teleprocessing device, or HALT I/O on any device if issued by OLTEP. Dequeued an unstarted OLTEP I/O request to a shared device.
26	1A		Validate address limits.
27	1B		Issue an HIO for a telecommunication device without dequeuing the CCB.
28	1C	EXIT(MR)	Return from user's stacker select routine (MICR type devices only).
29	1D	WAITM	Provide support from multiple wait macro WAITM.
33	21	COMRG	<ul style="list-style-type: none"> Force task select for system tasks.
34	22	GETIME	Provides Time-of-Day and updates the DATE field.
35	23		Hold a track for use by the requesting task only.
36	24	FREE	Free a track held by the task issuing the FREE.

SUPERVISOR CALLS (. . . Cont'd)

SVC		Macro supported	Function
Dec	Hex		
37	25	STXIT(AB)	Provide supervisor with linkage to user's AB routine for abnormal termination of a task.
38	26	ATTACH	Initialize a subtask and establish its priority.
39	27	DETACH	Perform normal termination of a subtask. It includes calling the FREE routine to free any tracks held by the subtask.
40	28	POST	Inform the system of the termination of an event and ready any waiting tasks.
41	29	DEQ	Inform the system that a previously enqueued resource is now available.
42	2A	ENQ	Prevent tasks from simultaneous manipulation of a shared data area (resource).
44	2C		Support the creation of unit check records from outside the A- or R-transient area.
45	2D		Reserved.
46	2E		Provide OLTEP with the facility to operate in supervisor state.
47	2F	WAITF	Provide support for multiple wait macro WAITF for MICR type devices.
48	30		Fetch a CRT transient.
49	31		Used by ACF/VTAM to initialize execution of channel program.
50	32		Used by LIOCS to cancel user indicating illegal SVC.
51	33		Make directory entry information for a phase available to the requesting task.
		HIPROG	Calculate the highest address of an overstructure of phase and store it in the COMREG.
52	34	TTIMER	Return the remaining time interval, or cancel a time interval.
53	35		Used by ACF/VTAM to schedule user exit in application program.
54	36		Release page frames to selection pool. (Applies only to 370 mode of operation.)
55	37		Allow SDAID to acquire processor storage needed for program initialization (applies only 370 mode of operation).
56	38		Support the VSE/POWER-CP interface when DOS/VSE operates under VM/370.
57	39	GETPRTY SETPRTY	Return partition priorities to the requesting task. Change partition priorities as specified.
58	3A	INVPART	Initialize partition.
59	3B	INVPAGE	Initialize tables or invalidate pages.
60	3C	GETADR	Provide virtual address of location within I/O areas for ERP and CRT routines.
61	3D	GETVIS	Request allocation of storage within the same partition or within the SVA.
62	3E	FREEVIS	Free storage requested through a GETVIS macro.
63	3F	USE	Use a system resource.
64	40	RELEASE	Release a system resource.
65	41	CDLOAD	Load a phase in the requesting partition's GETVIS area unless that phase is already in the SVA.
66	42	RUNMODE	Return mode which program is running.
67	43	PFIX	Fix page(s) in processor storage.

SUPERVISOR CALLS (. . . Cont'd)

SVC		Macro supported	Function
Dec	Hex		
68	44	PFREE	Free page(s) in partition storage.
69	45	REALAD	Return real address corresponding to a given virtual address.
70	46	VIRTAD	Return virtual address corresponding to a given real address.
71	47	SETPFA	Establish or terminate the linkage between the supervisor and a user page-fault appendage routine.
72	48	GETCBUF/FREECBUF	Get or free copy buffer for IDAL or tape ERP.
73	49	SETAPP	Allow linkage to channel and appendage routines.
74	4A	PFXREST	Fix page(s) in processor storage for restart.
		PFXCHPT	Build parameter list for PFXREST during checkpointing.
75	4B	SECTVAL	Calculate a sector value (disk dev.with RPS feature).
76	4C		Initiate recording on SYSREC file.
77	4D	TRANSCSW	Return the virtual address of an ERP CCW address copied from the pertinent CSW.
78	4E	CHAP	Change the processing priority of requesting task.
79	4F	SYNCH	Give control to synchronous exit.
80	50	SETT	Set task time interval.
81	51	TESTT	Return the remaining task time interval or cancel a time interval.
82	52		Set monitor call and/or branch, for ICCF.
83	53	ALLOCATE	Allocate real or virtual partitions.
84	54	SETLIMIT	Set partition sizes.
85	55	RELPAG	Release contents of one or more pages.
86	56	FCEPGOUT	Force a page-out operation for one or more pages.
87	57	PAGEIN	Page-in operation for one or more pages.
88	58	TPIN	Start TP Balancing.
89	59	TPOUT	Stop TP Balancing.
90	5A	PUTACCT	Provide interface with VSE/POWER for additional account information (by user).
91	5B		Provide interface with VSE/POWER for standard account information.
92	5C	XECBTAB	Define, delete, or check an entry in the cross partition ECB table.
93	5D	XPOST	Set the traffic bit in a cross-partition ECB and ready any waiting tasks.
94	5E	XWAIT	Wait for a cross-partition ECB to be posted.
95	5F	EXIT AB	Return from a user's abnormal termination routine.
96	60	EXIT(TT)	Return from user's task timer exit.
97	61	STXIT(TT)	Provide supervisor with linkage to user's task timer exit routine for task time interval end.
98	62	EXTRACT MODCTB	Extract system control information. Modify a PUB2 table entry.
99	63	GETVCE	Return a specific volume characteristics table entry.
100	64	PFX PFREE	Fix or free a page in the system GETVIS area.
101	65	MODVCE	Update the volume characteristics table.
102	66	GETJA	Update the fields in the requesting partition's job accounting table.
103	67		Execute I/O operations for SYSFIL on a FBA device.

SUPERVISOR CALLS (. . . Cont'd)

SVC Code *)		Imperative macro that issues the SVC	Generation option to be specified **)	Function
Dec	Hex			
104	68	EXTENT		Build, return, or delete DASD extent information.
105	69	SUBSID		Accept, return, and delete subsystem identification information.
106	6A			Set the storage key for a specific area to the value in Register 0 (ICCF).
107	6B	GETFLD MODFLD TREADY TPOST	none none none	Retrieve task-related information. Modify task-related information. Post or cancel a task. Deactivate current task or partition.
108	6C	SECHECK	none	Check user's authority for accessing the specified resource.
109	6D	PAGESTAT	none	Return status of a page or a set of pages.
110	6E	LOCK/ UNLOCK	none	Protect a serially re-usable resource against concurrent accessing by two or more tasks.

COMMAND CONTROL BLOCK (CCB)

Count	Transmission Information	CSW Status Bits	Type Code and logical Unit	Reserved for logical IOCS or 3895 PIOCS	CCW Address	Reserved for physical IOCS	CCW Address in CSW	Optional Sense CCW
0	1	2	3	4	5	6	7	8
9	10	11	12	13	14	15	16	17
18	19	20	21	22	23	24	25	26

Bytes	Description																		
0-1	Used for residual Count. Used by BTAM to indicate the number of copy blocks needed at channel end appendage time (370 mode only).																		
2-3	Transmitting information between Physical IOCS & Problem Program																		
	<table border="1"> <thead> <tr> <th>Byte 2</th> <th>Set on by:</th> </tr> </thead> <tbody> <tr> <td>Bit 0: Traffic Bit (Wait) (Note 5)</td> <td>PIOCS *</td> </tr> <tr> <td>Bit 1: End of File (/ * or / &) PRT1 UCSB Parity Check (Line Complete) (Note 2)</td> <td>PIOCS</td> </tr> <tr> <td>Bit 2: Irrecoverable I/O error</td> <td>PIOCS</td> </tr> <tr> <td>Bit 3: Accept irrecoverable I/O error</td> <td>Pr. Pr.**</td> </tr> <tr> <td>Bit 4: Return DASD Data Checks Diskette Data Checks, 2671 errors, or 1017/1018 errors to the user; indicate actiontype messages for DOC; Return 5424/5425 not ready.</td> <td>Pr. Pr.</td> </tr> <tr> <td>Bit 5: Post at Device End (Note 5)</td> <td>Pr. Pr.</td> </tr> <tr> <td>Bit 6: Return Tape Read Data Check; 1018 or 2560 Data Check; 2520, 2540, 2560, 3881 or 5424/5425 Equipment Check; Accept 3504, 3505 or 3525 Perm. Error; DASD Data Checks on Read or Verfiy Command on 3203, PRT1, or 5203 Pass-back Requested. (Notes 3, 6, 8 and 10)</td> <td>Pr. Pr.</td> </tr> <tr> <td>Bit 7: User Error Routine (Note 9)</td> <td>Pr. Pr.</td> </tr> </tbody> </table>	Byte 2	Set on by:	Bit 0: Traffic Bit (Wait) (Note 5)	PIOCS *	Bit 1: End of File (/ * or / &) PRT1 UCSB Parity Check (Line Complete) (Note 2)	PIOCS	Bit 2: Irrecoverable I/O error	PIOCS	Bit 3: Accept irrecoverable I/O error	Pr. Pr.**	Bit 4: Return DASD Data Checks Diskette Data Checks, 2671 errors, or 1017/1018 errors to the user; indicate actiontype messages for DOC; Return 5424/5425 not ready.	Pr. Pr.	Bit 5: Post at Device End (Note 5)	Pr. Pr.	Bit 6: Return Tape Read Data Check; 1018 or 2560 Data Check; 2520, 2540, 2560, 3881 or 5424/5425 Equipment Check; Accept 3504, 3505 or 3525 Perm. Error; DASD Data Checks on Read or Verfiy Command on 3203, PRT1, or 5203 Pass-back Requested. (Notes 3, 6, 8 and 10)	Pr. Pr.	Bit 7: User Error Routine (Note 9)	Pr. Pr.
Byte 2	Set on by:																		
Bit 0: Traffic Bit (Wait) (Note 5)	PIOCS *																		
Bit 1: End of File (/ * or / &) PRT1 UCSB Parity Check (Line Complete) (Note 2)	PIOCS																		
Bit 2: Irrecoverable I/O error	PIOCS																		
Bit 3: Accept irrecoverable I/O error	Pr. Pr.**																		
Bit 4: Return DASD Data Checks Diskette Data Checks, 2671 errors, or 1017/1018 errors to the user; indicate actiontype messages for DOC; Return 5424/5425 not ready.	Pr. Pr.																		
Bit 5: Post at Device End (Note 5)	Pr. Pr.																		
Bit 6: Return Tape Read Data Check; 1018 or 2560 Data Check; 2520, 2540, 2560, 3881 or 5424/5425 Equipment Check; Accept 3504, 3505 or 3525 Perm. Error; DASD Data Checks on Read or Verfiy Command on 3203, PRT1, or 5203 Pass-back Requested. (Notes 3, 6, 8 and 10)	Pr. Pr.																		
Bit 7: User Error Routine (Note 9)	Pr. Pr.																		
	<table border="1"> <thead> <tr> <th>Byte 3</th> <th>Set on by:</th> </tr> </thead> <tbody> <tr> <td>Bit 0: DASD Data Check in Count Area; Permanent Error for 3330, 3340 or 3350 MICR-SCU Not Operational; 1287/1288 Data Check; 3203, PRT1, or 5203 Print Check/Equipment Check; 3540 Special Record Transferred.</td> <td>PIOCS</td> </tr> <tr> <td>Bit 1: DASD Track Overrun; MICR Intervention required; 1287-Keybord Correction in Journal Tape Mode; 1017-Broken Tape PRT1-Print Quality/Equipment Check.</td> <td>PIOCS</td> </tr> <tr> <td>Bit 2: DASD End of Cylinder; MICR- (Note 4) 1287/1288-Hopper Empty in Document Mode. PRT1/2245 Line Position Error. (Note 7)</td> <td>PIOCS</td> </tr> <tr> <td>Bit 3: 2520, 2540, 3881-Equipment Check; 2560 3203, 5203, 5424/5425 Data Check/Equipment Check; Tape Read Data Check; DASD-Any Data Check; 1287-Equipment Check; 1017/1018 Data Check; PRT1-Print Check/Data Check; 3504, 3505, 3525 Perm. Error (Note 8); Diskette Data Check.</td> <td>PIOCS</td> </tr> <tr> <td>Bit 4: Non-Recovery Questionable Condition: Card-Unusual Command Sequence; DASD-No Record Found; 1287/1288-Documnt Jam or Torn Tape; PRT1-UCSB Parity Check (Command retry); 5424/5425 Not Ready.</td> <td>PIOCS</td> </tr> <tr> <td>Bit 5: No Record Found Condition (Retry on Disk Devices).</td> <td>Pr. Pr.</td> </tr> </tbody> </table>	Byte 3	Set on by:	Bit 0: DASD Data Check in Count Area; Permanent Error for 3330, 3340 or 3350 MICR-SCU Not Operational; 1287/1288 Data Check; 3203, PRT1, or 5203 Print Check/Equipment Check; 3540 Special Record Transferred.	PIOCS	Bit 1: DASD Track Overrun; MICR Intervention required; 1287-Keybord Correction in Journal Tape Mode; 1017-Broken Tape PRT1-Print Quality/Equipment Check.	PIOCS	Bit 2: DASD End of Cylinder; MICR- (Note 4) 1287/1288-Hopper Empty in Document Mode. PRT1/2245 Line Position Error. (Note 7)	PIOCS	Bit 3: 2520, 2540, 3881-Equipment Check; 2560 3203, 5203, 5424/5425 Data Check/Equipment Check; Tape Read Data Check; DASD-Any Data Check; 1287-Equipment Check; 1017/1018 Data Check; PRT1-Print Check/Data Check; 3504, 3505, 3525 Perm. Error (Note 8); Diskette Data Check.	PIOCS	Bit 4: Non-Recovery Questionable Condition: Card-Unusual Command Sequence; DASD-No Record Found; 1287/1288-Documnt Jam or Torn Tape; PRT1-UCSB Parity Check (Command retry); 5424/5425 Not Ready.	PIOCS	Bit 5: No Record Found Condition (Retry on Disk Devices).	Pr. Pr.				
Byte 3	Set on by:																		
Bit 0: DASD Data Check in Count Area; Permanent Error for 3330, 3340 or 3350 MICR-SCU Not Operational; 1287/1288 Data Check; 3203, PRT1, or 5203 Print Check/Equipment Check; 3540 Special Record Transferred.	PIOCS																		
Bit 1: DASD Track Overrun; MICR Intervention required; 1287-Keybord Correction in Journal Tape Mode; 1017-Broken Tape PRT1-Print Quality/Equipment Check.	PIOCS																		
Bit 2: DASD End of Cylinder; MICR- (Note 4) 1287/1288-Hopper Empty in Document Mode. PRT1/2245 Line Position Error. (Note 7)	PIOCS																		
Bit 3: 2520, 2540, 3881-Equipment Check; 2560 3203, 5203, 5424/5425 Data Check/Equipment Check; Tape Read Data Check; DASD-Any Data Check; 1287-Equipment Check; 1017/1018 Data Check; PRT1-Print Check/Data Check; 3504, 3505, 3525 Perm. Error (Note 8); Diskette Data Check.	PIOCS																		
Bit 4: Non-Recovery Questionable Condition: Card-Unusual Command Sequence; DASD-No Record Found; 1287/1288-Documnt Jam or Torn Tape; PRT1-UCSB Parity Check (Command retry); 5424/5425 Not Ready.	PIOCS																		
Bit 5: No Record Found Condition (Retry on Disk Devices).	Pr. Pr.																		

- * Physical IOCS
- ** Problem Program

COMMAND CONTROL BLOCK (CCB) (. . . Cont'd)

Count	Trans- mission infor- mation	CSW Status Bits	Type Code and logical Unit	Reserved for logical IOCS or 3895 PIOCS	CCW Address	Reserved for physical IOCS	CCW Address in CSW	Optional Sense CCW
0	1	2	3	4	5	6	7	8
9	10	11	12	13	14	15	16	17
18	19	20	21	22	23	24	25	26

Byte(s)	Description
2-3 (. . . Cont'd)	<p>Byte 3 (Cont'd)</p> <p>Bit 6: Carriage Channel 9 Overflow or Verify Error for DASD; 1287-Documt Mode-Late, Stacker Select; 1288-End of Page. PIOCS</p> <p>Bit 7: Command Chaining, Retry from the next CCW to be executed. Pr. Pr.</p>
4-5 CSW Status Bits	<p>Byte 4 (Note 1)</p> <p>Bit 0: Attention 1: Status Modifier 2: Control Unit End 3: Busy 4: Channel End 5: Device End 6: Unit Check 7: Unit Exception</p> <p>Byte 5</p> <p>Bit 0: Program Controlled Interruption 1: Incorrect Length 2: Program Check 3: Protection Check 4: Channel Data Check 5: Channel Control Check 6: Interf. Control Check 7: Chaining Check</p>
6-7 Type Code and Logical Unit	<p>Byte 6</p> <p>1x00x00x = User-translated CCB x1x0x00x = BTAM CCB 0x10x00x = System-translated CCB xxx0100x = CCB for physical unit xxx0x001 = CCB for program logical unit xxx0x000 = CCB for system logical unit</p> <p>Byte 7</p> <p>Hexadecimal representation of SYSnnn: SYSRDR = 00 SYSREC = 0A SYSIPT = 01 SYSCLB = 0B SYSPCH = 02 SYSDMP = 0C SYSLSLST = 03 SYSCAT = 0D SYSLOG = 04 SYS000 = 00 SYSLINK = 05 SYS001 = 01 SYSRES = 06 SYS002 = 02 SYSRLB = 07 : SYSRLB = 08 : SYSUSE = 09 SYS254 = FE</p>
8 Reserved for Logical IOCS or 3895 PIOCS (Note 10)	<p>Buffer Offset:</p> <p>ASCII Input Tapes X'00'–X'63'</p> <p>ASCII Output Tapes Fixed X'00'</p> <p>Variable X'00' or X'04'</p> <p>Undefined X'00'</p> <p>2501 Double CCW-Support X'80' (2501 Double-CCW Support is active)</p> <p>SNS Task I/O Request X'80' (I/O Error on Alternate Channel)</p>
9-11 CCW Address	<p>Virtual or real address of CCW associated with this CCB depending on byte 6:</p> <p>Real address if byte 6 bit 0 is ON</p> <p>Virtual address if byte 6 bit 0 is OFF</p>

COMMAND CONTROL BLOCK (CCB) (. . . Cont'd)

Count	Trans- mission Informa- tion	CSW Status Bits	Type Code and logical	Reserved for logical IOCS or 3895 PIOCS	CCW Address	Reserved for physical IOCS	CCW Address in CSW	Optional Sense CCW																
0	1	2	3	4	5	6	Unit	7	8	9	10	11	12	13	14	15	16	17	18	19	20	21	22	23

Byte(s)	Description
12	Reserved for Physical IOCS X'80' CCB being used by ERP X'40' Channel Appendage Routine present for TP Device, VSAM or VSE/POWER X'20' Sense Information desired (Note 9) X'10' Reserved X'08' EU Tape Error X'04' OLTEP Appendage available X'02' Tape ERP Read Opposite Recovery X'01' Reserved
13–15	CCW Address in CSW Virtual Address of CCW pointed to by CSW at Channel End (if byte 6, bit 0 is on, it is the real address) or address of the Channel End Appendage Routine.
16–23	Optional Sense CCW 8 bytes appended to the CCB when Sense Information is desired.

- Note 1: Bytes 4 and 5 contain the status bytes of the Channel Status Word (Bits 32–47). If byte 2, bit 5 is on and device end results as a separate interrupt, device end will be OR-ed into CCB byte 4.
- Note 2: Indicates / * or / & statement on SYSRDR or SYSIPT. Byte 4, bit 7 (unit exception) is also on.
- Note 3: DASD data checks on count not returned.
- Note 4: For 1255/1259/1270/1275/1419, disengage. For 1275/1419D, I/O Error is external interrupt routine (Channel data check or bus-out check).
- Note 5: The traffic bit (Byte 2, bit 0) is normally set on at channel end to signify that the I/O was completed. If byte 2, bit 5 has been set on, the traffic bit and bits 2 and 6 in byte 3 will be set on at device end. Also see Note 1.
- Note 6: 1018 ERP does not support the Error Correction Function.
- Note 7: This error occurs an equipment check, data check or FCB parity check. For 2245, this error occurs as a data check or FCB parity check.
- Note 8: For 3504, 3505, 3525 input or output files using ERRCP, byte 3, bit 3 is set on if a permanent error occurs. Byte 2, bit 6 is set on to allow you to accept permanent errors.
- Note 9: If user error routine is specified and the user needs the sense information to further process the error, byte 12, bit 2 must also be set. Otherwise, the supervisor error routine will clear off the status on return and the sense information is not available.
- Note 10: 3895 error codes are returned in CCB Byte 8. Refer to 3895 document reader/inscriber machine and programming description for information on these error codes.

INPUT/OUTPUT REQUEST BLOCK (IORB)

Count	Transmission Information	CSW Status Bits	Type Code and Logical Unit	Reserved for Logical IOCS	CCW Address	Reserved for Physical IOCS
0	2	4	6	8	9	12

CCW Address in CSW	Fix Flag	Address of Fixlist	Version ID	Special Processing Flags	Optional Extension	
13	16	17	20	22	ID	Address
					24	25


Input/Output Request Block (IORB)

Byte(s)	Description
0–1	Used for residual count
2–3	<p>Byte 2: For transmitting information between physical IOCS and problem program. Set by the physical IOCS: Bit 0: Traffic bit, wait (Note 3) Bit 1: End-of-File /* or /& (Note 2) Bit 2: Irrecoverable I/O error</p> <p>Set by the Problem Program: Bit 3: Accept irrecoverable I/O error Bit 4: Reserved Bit 5: Post at device end (Note 3). Bit 6: Reserved Bit 7: Skip system error recovery</p> <p>Byte 3: Reserved für ERP return information.</p>
4–5	<p>Byte 4 (Note 1): Bit 0 (32): Attention Bit 1 (33): Status modifier Bit 2 (34): Control unit end Bit 3 (35): Busy Bit 4 (36): Channel end Bit 5 (37): Device end Bit 6 (38): Unit check Bit 7 (39): Unit exception</p> <p>Byte 5: Bit 0 (40): Program controlled interruption Bit 1 (41): Incorrect length Bit 2 (42): Program check Bit 3 (43): Protection check Bit 4 (44): Channel data check Bit 5 (45): Channel control check Bit 6 (46): Interface control check Bit 7 (47): Chaining check</p>
6–7	<p>Byte 6 (Class byte): Bit 0: Reserved Bit 1: Reserved Bit 2: 1 = Copied IORB (370 mode only) Bit 3: Reserved Bit 4: 1 = Physical addressing Bit 5: 1 = IORB ID Bit 6: Reserved Bit 7: 1 = Programmer logical unit; 0 = System logical unit</p> <p>Byte 7 (Addressing byte) Hexadecimal representation of SYSnnn: SYSRDR = 00 SYSREC = 0A SYSIPT = 01 SYSCLB = 0B SYSPCH = 02 SYSDMP = 0C SYSLIST = 03 SYSCAT = 0D SYSLOG = 04 SYSLUB = 0E–FF SYSLINK = 05 SYS000 = 00 SYSRES = 06 SYS001 = 01 SYSSLB = 07 SYS002 = 02 SYSRLB = 08 : SYSUSE = 09 SYS254 = FE</p>

INPUT/OUTPUT REQUEST BLOCK (IORB) (. . . Cont'd)

Byte(s)	Description
8	Reserved for Logical IOCS
9–11	Address for the CCW associated with this IORB.
12	Reserved for physical IOCS: Bit 0: IORB is used by ERP Bit 1: Reserved Bit 2: IORB has an extension Bit 3: Reserved Bit 4: EU tape error Bit 5: Reserved Bit 6: Tape ERP read opposite recovery Bit 7: Reserved
13–15	Virtual address of CCW pointed to by CSW at Channel End.
16	Fix Flag (ignored in 370 mode): Bit 0 = 1 Compressed: The system needs not to compress the fixlist. Each page to the fixed for the channel program is covered only once by the fixlist. = 0 Not compressed: The system must compress the fixlist. Bit 1 = 1 Fixed: No fixlist is provided by the user. The user has fixed all areas. = 0 Not fixed: The user has provided a fixlist. Bit 2–7 Reserved
17–19	Address of the fixlist (ignored in 370 mode): Each fixlist area is contiguous and consists of one or more 8-Byte fixlist entries. Each entry contains a begin and an end address describing a storage area that has to be fixed for the I/O request (an area containing the channel program or an input/output area).
20–21	Version identification code.
22–23	Special processing flags (set by LIOCS): Bit 0: SYSFIL request for FBA device. Bits 1–15: Reserved
Begin of optional parameters (set by the problem program).	
24	Optional parameter ID: Bit 0: Last parameter Bits 1–7: ID code (00 = ECB)
25–27	Address portion of optional parameter
Note 1:	Bytes 4 and 5 contain the status bytes of CSW (Bits 32–47). If byte 2, bit 5, is on, the accumulated interrupt information will be stored in byte 4 and 5 of the IORB.
Note 2:	Indicates /* or /& statement on SYSRDR or SYSIPT. Byte 4, bit 7, (unit exception) is forced on.
Note 3:	The traffic bit (byte 2, bit 0) is normally set on at channel end to signify that the data transfer is completed. If byte 2, bit 5, has been set on, the traffic bit is set on at device end. See also Note 1.

STORAGE MANAGEMENT CONTROL BLOCK (SMCB) FOR A MULTI PARTITION SYSTEM



Bytes 220–223 (X'DC'–X'DF') of the system communication region (SYSCOM) contain the address of the storage management control block (SMCB). Label SMCB identifies the first byte of the table.

SYSCOM

Displacement	0	4	8	0C	10	18			
	0	4	8	12	16	24			
Hex Dec	Address of Error Block	Hard Wait Code	Address of Operator Option Cancel Exit	Address of SYSRES PUB	Reserved	Reserved			
	xxxx	xxxx	xxxx	xxxx	xxxxxxxx	xxxx			
	1C 28	20 32	24 36	25 37	28 40	2A 42	2C 44	2E 46	30 48
	Address of Logical Transient Area	Address of 1st byte of Problem Program Area	Free List Pointer	Address of Channel Queue	Number of Channel Queue Entries	Length of One Error Queue Entry	Number of Partitions	Flags and Switches (see expansion)	Reserved
	xxxx	xxxx	x	xxx	xx	xx	xx	xx	xxxx
	34 52	35 53	38 56	40 64	44 68	46 70	48 72	4C 76	
	Configuration Byte (see expansion)	Address of CRT Table	Reserved	Flags and Switches (see expansion)*	Reserved	Reserved	Reserved	Reserved	TH Free List Pointer
	x	xxx	xxxxxxxx	xxxx	xx	xx	xxxx	xxxx	x

* See end of tables for further explanation.

Note: The address of SYSCOM can be found at fixed location X'80'-X'83'.

4D 77	50 80	54 84	58 88	5A 90	5C 92	60 96	64 100	68 104
Address of TH Table	Reserved	Reserved	Key of Task owing LTA (LIK)	Key of Task running (TIK)	Address of VSE/POWER Table	Address of VTAM Address Vector Table	Address of RF Table	Reserved
xxx	xxxx	xxxx	xx	xx	xxxx	xxxx	xxxx	xxxx

6C 108	70 112	74 116	78 120	7C 124	80 128	84 132	88 136
Address of OLTEP bucket	Address of RAS Linkage Area	Address of ASCII Translate Table	Address of PUB Ownership Table	Address of Job Accounting Common Table	Reserved	Used by SDAID	Address of SDAID Comm. Area
xxxx	xxxx	xxxx	xxxx	xxxx	xxxx	xxxx	xxxx

8C 140	90 144	94 148	98 152	to AF 175	80 176	BC 188	BE 190	C0 192	CB 203	CC 204
Address of Line Mode Table	Input buffer for Attention	Address of PTA	Reserved		Address of Task Timer Table	TP Balancing Parameter	Key of Partition owning Task Timer	Repositioning Information for 2560/5424/5425 ERP	Number of Error Queue Entries	Length of PUB Table in bytes
xxxx	xxxx	xxxx	xxxx		xxxx	xx	xx	xxxxxxxxxxxx	x	xx

CE 206	D0 208	D4 212	DC 220	E0 224	E4 228	E6 230	E8 232
Number of Active Partitions	Address of Segment Table (370 mode)	Reserved	Address of Storage Management Control Block	Address of DPD Table	Address of System Operator Console	Number of Subtasks	Reserved
xx	xxxx	xxxxxxxx	xxxx	xxxx	xx	xx	xxxx

EC 236	F0 240	F4 244	F5 245	F8 248	FC 252	100 256	104 260	108 264
Address of End of Real Storage in 370 mode	Address of Fetch Table	SVA Flags (see expansion)	Address of SVA	Address of System GETVIS area	Address of RPS Local Directory List*	Address of RPS Sector Calculation Routine*	Address of System Code	Reserved
xxxx	xxxx	x	xxx	xxxx	xxxx	xxxx	xxxx	xxxx

10C 268	110 272	114 276	118 280	11C 284		120 288	124 292	128 296	12C 300
Pointer to Label Area	Address of Supv.-IPL Comm. Region	Address of SVA Phase Area	Reserved	PIK of actual ICCF Partition	Address of ICCF Vector Table	Pointer to Access Control Vector Table	Pointer to Save Area if Progr. Check in SUPVR	Pointer to Table of System Units	Address of Library Control Table
xxxx	xxxx	xxxx	xxxx	x	xxx	xxxx	xxxx	xxxx	xxx



SYSTEM CONTROL PROGRAM COMMUNICATION REGION (. . . Cont'd)

Expansion of SYSCOM Flag Bytes

Byte		Description
Dec	Hex	
46	2E	Bit 0 always on Bit 1 1 = DOS/VSE and follow-on releases Bit 2 1 = TPBAL not active Bit 3 Reserved Bit 4 1 = CBF supported Bits 5–7 Reserved
47	2F	Bit 0 1 = 4300 support generated (ECPS:VSE mode) 0 = /370 support generated (370 mode) Bits 1–4 Reserved Bit 5 1 = At least on CKD disk supported Bit 6 1 = FBA support generated Bit 7 1 = 3800 support generated
52	34	Bit 0 1 = CRT support initialized Bits 1–5 Reserved Bits 6, 7 00 = Typewriter support generated 01 = 125D support generated 11 = 3277 support generated
64	40	Reserved for RMS X'80' RMSR supported X'40' Full RMS support (MCAR/CCH and RMSR) X'20' Reserved, must be 0 X'01' IT support down
65	41	X'04' SIO routine entered after interrupt X'02' Reserved X'01' IPL in progress
66	42	X'80' Initial RAS request X'40' RAS WAIT request outstanding X'20' RAS IPL in progress X'10' Reserved X'08' VSE/POWER supported, always on X'04' VSE/POWER initialized X'02' GETREAL for SDAID in progress X'01' Reserved
67	43	X'80' System GETVIS area initialized X'40' ECPREAL supported, always on X'20' VSAM supported, always on X'10' BTAM AUTOPOLL enabled for VSE/AF, VSE-VM/370 linkage improvements support X'08' XECB support generated X'04' Reserved X'02' Batch deactivated by TPIN X'01' VSE/AF, VSE-VM/370 linkage support generated
68	44	Always zero
224	E0	Zero if VM=YES
244	F4	SVA Flag X'80' Reserved X'40' SDL active X'20' Reserved X'10' Build of SDL in progress X'08' SDL overflow X'04' High-Level SDL search X'02' Reserved X'01' Reserved
264	108	X'00' Reserved X'80' Reserved X'40' Asynchronous operator communication task is active X'20' Read is requested X'10' Reply or command is already in input buffer of asynchronous operator communication task X'08' Reserved X'04' Print message 0D13D X'02' Message 0D13D has been printed X'01' Reserved

nnCOMREG

Hex Dec Displacement	0	8	0C	17	18	20	24	28	2C			
	0	8	12	23	24	32	36	40	44			
	Date	Reserved	User area	UP SI Byte	Job Name	Highest Storage Address of the Partition	End Address of Last Phase Loaded	Address of upper- most Byte of Phase with highest Ending Address	Label Area Length			
	xxxxxxx	xxxx	xxxxxxxxxxxx	x	xxxxxxxx	xxxx	xxxx	xxxx	xx			
	2E	30	34	35	36	37	38	39	3A	3B	3C	3E
	46	48	52	53	54	55	56	57	58	59	60	62
	PIK	End of Virtual Storage Address	Machine Configur. Byte	System Configur. Byte	Standard Language Translator I/O Options	Dump, Log, RELLDR and ASCII Options	Job Control Byte	Linkage Control Byte	Language Translator Control Byte	Job Duration Indicator Byte	Reserved	Address of FOCL
	xx	xxxx	x	x	x	x	x	x	x	x	xx	xx
	Job Control Switches											
	40	42	44	46	48	4A	4C	4E	4F	50	5A	5C
	64	66	68	70	72	74	76	78	79	88	90	92
	Address of PUBTAB	Address of FAVP	Address of JIBTAB	Reserved	Address of FICL	Address of NICL	Address of LUBTAB	Line Count for SYSLST	System Date	LIOCS Comm. Bytes	Address of PIB Table	ID Number of last Checkpoint or DASDFP Indicator
	xx	xx	xx	xx	xx	xx	xx	x	xxxxxxxx	xx	xx	xx

Note:

A communication region exists for each partition supported by the system.
The address of the communication region of the active partition is in fixed loc.X'14'—X'17'.

5E 94	60 96	62 98	63 99	64 100	69 105	6A 106	6C 108	6E 110
Job Zone in Minutes	Address of Disk Information Block (DIB)	Device Flag for Automatic Close	Reserved	Disk Address of Job Statement	Reserved	Key of Partition	Reserved	Logical Transient Key (LTK)
xx	xx	x	x	xxxxx	x	xx	xx	xx

70 112	74 116	78 120	7C 124	7E 126	80 128	84 132	86 134	87 135
Address of SYSPARM	Address of J. A. Partition Table	Address of TOD clock Common Area	Address of PIB Table Extension	Address of MICR DTF Table (PDTABB)	Slot for Pointer to Lable Area	Address of BG Comm. Region	Option Indicator	System Configuration Byte 2 and RMSR Open Flag Byte
xxxx	xxxx	xxxx	xx	xx	xxxx	xx	x	x

88 136	8C 140	8D 141	8E 142	8F 143	97 151	98 152	9F 159
Reserved for compatability Reasons	Standard Job Control Options 1	Temporary Job Control Options 1	Disk Configuration	Catalog Procedure Name	Switch for Catalog Procedure	JCL Statement Name	81 bytes SYSIN Indicator
xxxx	x	x	x	xxxxxxxx	x	xxxxxxxx	x

Note:

A communication region exists from each partition supported by the system.
The address of the communication region of the active partition is in fixed loc. X'14'-X'17'.

A0 160	A4 164	A5 165	A6 166	A8 168	AC 172	AD 173	AE 174	AF 175	B0 176	B4 180
Address of VSE/POWER Partition Control Block	VSE/POWER Flag Byte 1	VSE/POWER Flag Byte 2	Reserved	Address of LUB Table Extension	Job Control Switch 5	Job Control Switch 6	Standard Job Control Options 2	Temporary Job Control Options 2	Pointer Reserved to JPL	Slot for CICS
xxxx	x	x	xx	xxxx	x	x	x	x	xxxx	xxxx

BB 184
Pointer to Phase-Load Trace Table
xxxx

IV-19

Note:

A communication region exists for each partition supported by the system.

The address of the communication region of the active partition is in fixed loc. X'14'—X'17'.

PARTITION COMMUNICATION REGION (. . . Cont'd)

Expansion of COMREG Flag Bytes

Byte		Description
Dec	Hex	
0	0	MM/DD/YY or DD/MM/YY either set permanently by the job control date statement, or updated every time a GETIME macro is issued when time-of-day support is provided. Format controlled by BGCOMREG + 53. (System Configuration Byte, date convention bit 0.)
8	8	Reserved.
12	0C	User area.
23	17	User program switch indicator.
24	18	Job name set by the job control program form information found in the job statement.
32	20	Address of the uppermost byte available to the problem program.
36	24	Address of the uppermost byte of the last phase of the problem program fetched or loaded. Not filled in when phase is in SVA.
40	28	Address of the uppermost byte of the phase with the highest ending address for this partition, starting with the same 4 characters as the root phase (operand on the exec statement) and residing in the same core image library as the root phase. If the root phase is in the SVA, the partition start address plus 2K will be used.
44	2C	Length of the problem program label area.
46	2E	Partition identification key (PIK) of the partition owning this communication region. However, the communication region of the BG partition always contains the PIK of the currently active partition. That is, it contains the PIK of the BG partition only, if the BG partition is active.
48	30	End address of virtual storage.
52	34	Machine Configuration Byte (Values set at supervisor generation time) X'80' Always set to indicate standard storage protect X'40' Decimal feature (always set) X'20' Floating point feature X'10' Physical transient overlap option (always set) X'08' Always set to indicate standard timer feature X'04' Channel switching support X'02' Burst mode on multiplex channel support (always set) X'01' Reserved
53	35	System Configuration Byte X'80' DDMMYY (Date convention bit set by STDOPT statement) X'40' Two or more partitions, always on X'20' DASD file-protect support X'10' DASD SYSIN – SYSOUT X'08' Teleprocessing, always on X'04' Two or more partitions, always on X'02' Asynchronous processing, always on X'01' Track hold/Block hold
54	36	This byte contains the standard language translator I/O options after generation, defaults are valid: 1100 110 X'80' DECK option output object modules on SYSPCH X'40' LIST option output source module listings and diagnostics on SYSLST X'20' LISTX option output hexadecimal object module listings on SYSLST (compilers only) X'10' SYM option output symbol tables on SYSLST/SYSPCH X'08' XREF option output symbolic cross-reference list on SYSLST X'04' ERRS option output diagnostics on SYSLST (compilers only) X'02' CHARSET option 0 = input on SYSIPT is 48 character set 1 = input on SYSIPT is 60 character set X'01' Reserved
55	37	This byte contains the standard supervisor options for abnormal EOJ, Relocating Loader and Control statement display and the indicator for the presence of the ASCII-EBCDIC and EBCDIC-ASCII translation tables. X'80' Always on X'40' DUMP option (DUMP=YES or DUMP=PART), dump registers and storage on SYSLST

PARTITION COMMUNICATION REGION (. . . Cont'd)

Expansion of COMREG Flag Bytes

Byte		Description
Dec	Hex	
55 (Cont'd)	37	X'20' Partition is in wait state, because a volume is to be mounted X'10' LOG option Yes, list all control statements on SYSLST X'08' Dummy device search in progress; do not enter ERP X'04' Reserved X'02' Relocating Load option yes, Relocating Loader supported (always set) X'01' ASCII option yes, ASCII supported
56	38	Job Control Byte X'80' Job accounting Interface (JA) not supported, off = supported X'40' Return to caller on LIOCS disk open failure X'20' Job control input from SYSRDR, bit 2=0: from SYSLOG X'10' Job control output on SYSLOG X'08' Cancel job X'04' Pause at end-of-job step X'02' SYSLOG is a console printer-keyboard or DOC (always 0) X'01' SYSLOG is assigned to the same device as SYSLST
57	39	Linkage Control Byte X'80' SYSLNK open for output X'40' Reserved X'20' Allow EXEC X'10' Catalog linkage editor output X'08' Reserved X'04' Reserved X'02' Update of System Core Image Library in progress (interface between CONDENSE and FETCH) X'01' Reserved

Cont'd next page.

PARTITION COMMUNICATION REGION (. . . Cont'd)

Key to Communication Region Displacement

Byte		Description
Dec	Hex	
58	3A	Language processor control byte. This is a set of switches used to specify nonstandard language translator options. The switches within the byte are controlled by job control OPTION statements and when set to 1, override standard options. The format of this byte is identical to the standard option byte (displacement 54) with one exception: Bit 7 in this byte is used to indicate to LIOCS that the rewind and unload option has been specified.
59	3B	Job Duration Indicator Byte X'80' Job in progress X'40' Dump or partition dump on an abnormal EOJ condition (see byte 141) X'20' Pause at EOJ step. Set by attention routine for job control X'10' Job control output on SYSLST X'08' Job is being run out of sequence with a temporary assignment for SYSRDR X'04' Testmode (SDL scanned as specified in LIBDEF statement) X'02' // DATE statement processed for current job X'01' Batch command just issued
60	3C	Reserved
62	3E	Addresses of I/O tables as illustrated
76	4G	illustrated
78	4E	Set to the value nn specified in the LINES=nn parameter of the STDOPT statement. Initial value = 56.
79	4F	The format of the system date contained within this field is determined by the IPL program from information supplied in the date convention bit (displacement 53). Bytes 85 - 87 contain the day count.
88	58	Bytes reserved for use by LIOCS
90	5A	Address of the first part of the Program Information Block (PIB) table
92	5C	ID number of the last checkpoint (hexadecimal)
94	5E	Job zone for Time-of-Day. If ZONE=EAST, value is positive, if ZONE=WEST, value is negative.
96	60	Address of disk I/O position data. This is the starting address of the Disk Information Block (DIB) table for the partition.
98	62	Device flag for automatic close. Bit 0: One or more 3800 printer extended buffering DTFs is/are open.
99	63	Flag byte X'80' = BTAM in the partition.
100	64	Disk address of last job statement on Hard Copy File.
105	69	Reserved
106	6A	PIK of partition
108	6C	Reserved
110	6E	Logical Transient Key (LTK) contains the same value as the PIK (Displacement 46) when the logical transient is requested. When the transient area is not in use, LTK is equal to zero. (Only significant in BG communication region.)
112	70	Address of SYSPARM field.
116	74	Address of Job Accounting partition table.
120	78	Address of Time-of-Day clock common area.
124	7C	Address of second part of Program Information Block (PIB) table.
126	7E	Address of PDTABB, table of DTF addresses for MICR support.
128	80	Slot for pointer to label area.

PARTITION COMMUNICATION REGION (. . . Cont'd)

Expansion of COMREG Flag Bytes

Byte		Description
Dec	Hex	
132	84	Address of background communications region.
134	86	Option Indicator Byte X'80' Reserved X'40' Reserved X'20' Teleprocessing request X'10' Supervisor support for tape, always on X'08' Reserved X'04' Reserved X'02' Count of referenced pages for JA is active X'01' GETVIS function has been initiated
135	87	System Configuration Byte 2 and RMSR Open Flag Byte X'80' PCIL supported, always on X'40' TOD clock supported, always on X'20' PFI macro supported, always on X'10' Fetch \$\$\$BOPEN by \$JOBCTLJ X'08' Fetch \$\$\$BOPEN by \$JOBCTLD X'04' Fetch \$\$\$BOPEN by \$JOBCTLJ for WTM X'02' Count of referenced pages for JA is active X'01' RPS supported
136	88	Reserved for compatibility reasons.
140	8C	Standard Job control option byte Initial value: X'80' EDECK Standard Option 0 X'40' ALIGN Standard Option 1 X'20' PARTDUMP Standard Option 0 X'10' RLD Standard Option 0 X'08' SXREF STD Option 0 X'04' TERM STD Option 0 X'02' Reserved – X'01' ACANCEL Standard Option 0
141	8D	Temporary Job control option byte X'80' EDECK Temporary Option X'40' ALIGN Temporary Option X'20' PARTDUMP Temporary Option X'10' RLD Temporary Option X'08' SXREF Temporary option X'04' TERM Temporary option X'02' SUBLIB=DF Temporary Option X'01' 1=ACANCEL Temporary Option
142	8E	Disk Configuration Byte 0–3 Reserved X'08' 3350 supported X'04' 3340 supported X'02' 3330 supported X'01' 2311 and 2314/2319 supported.
143	8F	Cataloged Procedure Name
151	97	Interface Byte for Cataloged Procedures X'80' Procedure being executed X'40' Overwrite processing X'20' Procedure with data X'10' Overwrite request for Job Control X'08' Insert request for Job Control X'04' Procedure end X'02' SYSLOG procedure X'01' Overwrite request for Supervisor
152	98	ICL statement name for Cataloged Procedure

PARTITION COMMUNICATION REGION (. . . Cont'd)

Expansion of COMREG Flag Bytes

Byte		Description
Dec	Hex	
159	9F	SYSIN 81 Bytes Indicator X'80' Permanent 81 bytes on SYSRDR X'40' Permanent 81 bytes on SYSIPT X'20' Temporary 81 bytes on SYSRDR X'10' Temporary 81 bytes on SYSIPT Reserved X'01' Allow/& for MAINT CATALS
160	A0	Pointer to VSE/POWER partition control block
164	A4	VSE/POWER Flag Byte 1 X'80' VSE/POWER Accounting Supported X'40' Partition under control of VSE/POWER X'20' VSE/POWER Partition X'10' Reserved X'08' Partition is waiting for work Reserved
165	A5	VSE/POWER Flag Byte 2:Reserved
166	A6	Reserved
168	A8	Pointer to LUB Table Extension
172	AC	Job Control Switch 5 Bit 0: 1= EXEC LNKEDT statement is to be generated 1: 1= EXEC statement is to be generated 2: 1 and OPTION LINK ON=Continue link and execution 1 and OPTION LINK OFF=Do not execute link and execution, assembler found a link problem 3: 1= NEWVOL ignored 4: LISTLOG executed because of cancel 5+6: 00=no ASI 01=end of ASI procedure 10=generate EXEC=PROC 11=NO-OP 7: 1= Job control active
173	AD	Job Control Switch 6 Bit 0-4: Reserved 5: 1= SLA active in partition 6: 1= System procedure library in use 7: Current procedure library on FBA
174	AE	Standard Job Control Option 2 (Reserved)
175	AF	Temporary Job Control Option 2 Bit 0: 1= No Fast translation for this job 1: 1= System dump SYSDMP on DASD 2-7: Reserved

LOGICAL TRANSIENT OWNER IDENTIFIER (LTID)

The LTID, a halfword (LIK) at displacement 88 in SYSCOM contains the same value as the TID when the Logical Transient Area (LTA) is in use and therefore identifies the owner of the LTA. When LTA is free, the halfword LIK (LTID) contains zeros. The SVC2 routine sets the LTID, and the SVC11 routine resets it to zero.

LOGICAL TRANSIENT KEY (LTK)

The halfword LTK at displacement 110 in each partition communication region has a zero value in the high-order byte and a key value in the low-order byte. In a foreground communication region, the key value in the LTK is not significant. The LTK in the background communication region (BGCOMREG) has the same value as the PIK of partition of the task that owns the LTA, or contains zeros when the LTA is free.

I/O REQUESTOR'S PARTITION OR SYSTEM TASK ID (REQID)

The REQID is a one-byte identifier in the Channel Queue (CHANQ) entry, used for storing the service owner identification. When a background or foreground program requested the I/O operation, the REQID has the value of the partition identification key. When a system task requested the I/O operation the REQID contains the partition identification key of the service owner. The REQID is set by the Channel Scheduler Routine.

RASLINK

0	8	9	0A	0B	0C	10	14	16	18
0	8	9	10	11	12	16	20	22	24
CPU ID Field	Damaged Channel Byte	RAS Flag Byte	Machine Check Flags	Reserved	RAS Table (RASTAB) Address	Base Address for RAS Monitor	Internal Model Number	Length of I/O Extended Logout Area	Address of extended mach. check LOGOUT area
xxxxxxx	x	x	x	x	xxxx	xxxx	xx	xx	xxxx

Hex
Dec
Displacement

Key to RAS Linkage Area displacement

0	CPU ID Field	
8	Address of damaged channel, or X'FF' if no channel damaged	
9	RAS Flag Byte	
bit	flag	description
0	X'80'	RAS active
1	X'40'	RAS SIO flag
2	X'20'	RTA in control
3	X'10'	RAS I/O delayed
4	X'08'	Channel check on error SIO
5	X'04'	Reserved
6	X'02'	Channel check on SIO
7	X'01'	I/O active for SIO

10	Machine Check Flags	
bit	flag	description
0-4		Reserved
5	X'04'	Hard machine check
6	X'02'	All machine records built
7	X'01'	All channel check records built
11	Reserved	
12	Address of RAS Monitor Table (RASTAB)	
16	Address for base register in RAS Monitor Program	
20	Internal Model Number	
22	Length of I/O extended logout area	
24	Address of machine check extended LOGOUT area (if byte 0 = X'80', address not yet valid)	

Bytes 112-115 (X'70'-X'73') of the System Communication Region (SYSCOM) contain the address of the area. Label RASLINK identifies the first byte of the area.

Define the Lock (DTL)

0	2	3	4	//	16	21
Length of DTL X'0016'	DTL Flag 1	DTL Flag 2		Resource name	Volume identification	

Byte 2 DTL Flag 1: X'01' LOCKOPT = 1 CONTROL = S
 X'11' LOCKOPT = 1 CONTROL = E
 X'02' LOCKOPT = 2 CONTROL = S
 X'12' LOCKOPT = 2 CONTROL = E
 X'04' LOCKOPT = 4 CONTROL = S
 X'14' LOCKOPT = 4 CONTROL = E

Byte 3 DTL Flag 2: Bit 0 = ON if KEEP = YES
 1 = ON if OWNER = PARTITION
 2 = ON if CHANGE = ON
 3 = ON if SCOPE = EXT
 4 = ON if VOLID specified
 5-7 zero

Note: On entry to SVC 110 Register 1 contains the address of DTL.

LOCKTAB Entry

0	4	//	16	17	18	19
Chain Pointer to Owner Elements		Resource name	LOCK Flag 1	LOCK Flag 2	LOCKCNTE No. of exclusive users	

Byte 16 same contents as DTL Flag 1 in DTL.


Byte 17 LOCK Flag 2: Bit 0 = ON if LOCKUSED
 1 = ON if LOCKPART
 2 = ON if LOCKWAIT
 3 = ON if LOCKEXT

OWNER Element


0	4	6	8	10	11
Chain forward pointer to next owner element 0 if end of chain	TID of owning task	No. of shared users	No. of exclusive users	Flag byte	zero


Byte 10 Flag Byte: Bit 0 = ON if KEEP until EOJ
 1 = ON if OWNER = PARTITION
 2 zero
 3 = ON if CONTROL = EXC
 4-7 zero

Partition Control Blocks Interrelationship



Partition Control Block (PCB)





IV-30

Byte 0: X'00' Partition is active
 X'80' Partition is unbatched
 X'82' Partition is stopped

*Byte 1: Old main task status, saved at cancel by operator

Byte 4: X'80' Program running in virtual mode, always on in System PIB


Byte 5-7: Begin address of virtual partition, reserved in System PIB

Byte 12: X'40' Channel appendage allowed
 X'08' Hold foreground assignments

Byte 15: X'20' /& on SYSRDR or SYSIPT
 X'10' Partition stopped

Byte 90-91 (X'5A'-X'5B') of partition COMREG contain the address of the PIBTAB.

PROGRAM INFORMATION BLOCK TABLE EXTENSION (PIB2TAB)



Byte 124-125 (X'7C'-X'7D') of partition COMREG contain the address of the PIB2TAB.

SAVE AREAS

Layout of LTA and Partition Save Area

Dec	Hex	0	1	2	3	4	5	6	7
0	00	Program name (Transient Name)							
8	08	Return PSW							
16	10	Register 9				Register 10			
24	18	Register 11				Register 12			
32	20	Register 13				Register 14			
40	28	Register 15				Register 0			
48	30	Register 1				Register 2			
56	38	Register 3				Register 4			
64	40	Register 5				Register 6			
72	48	Register 7				Register 8			
80	50	see (A)							
88	58	Save area for floating point registers (optional on a /370).							
120	70	0	1	2	3	4	5	6	7

(A) Byte 0, 1: Reserved; Byte 2: Job start time; LTA: Reserved.

Layout of User-Exit Save Area

Dec	Hex	0	1	2	3	4	5	6	7
0	00		(A)	Mapped PSW					
8	08	Registers 0 through 15 in this sequence.							
64	40								
		0	1	2	3	4	5	6	7

(A) Byte 2 of the mapped PSW contains interrupt status information.

Byte 0: Reserved

Byte 1: Protection key and mask (from PSW byte 1)

Bytes 2, 3: Interruption Code


Byte 4: Bits 0 - 1 Instruction Length Code

Bits 2 - 3 Condition Code

Bits 4 - 7 Program Mask


Bytes 5 - 7: Instruction Address

I/O TABLE INTERRELATIONSHIP



*CHNADDR
 00C = only one Channel Address
 009 = Address in PUB 009 and 109

LOGICAL UNIT BLOCK (LUB) TABLE



LUB Table for any Partition

SYSRDR	
SYSIPT	
SYSPCH	
SYSLST	
SYSLOG	
SYSLNK	
SYSRES	
SYSSLB	
SYSRLB	
1) SYSUSE	
SYSREC	
SYSCLB	
SYSDMP	
SYSCAT	
SYS000	
SYS001	
SYS002	
SYS003	
SYS004	
2) SYSnn	

0 0 0 0 0 0 0 – Points to first PUB and PUBOWNER
 0 0 0 0 0 0 1 – Points to second PUB and PUBOWNER
 0 0 0 0 0 1 0 – Points to third PUB and PUBOWNER
 .
 .

1 1 1 1 1 1 0 – Ignore, assigned ignore
 1 1 1 1 1 1 1 – Null Pointer, the LUB is unassigned

When a logical unit is assigned, the system inserts a pointer to the PUB for the physical device specified.

Format of any LUB

Byte 0	Byte 1
PUB Pointer	JIB Pointer

JIB Index (Multiply by 4 = Displacement into JIB Table) or X'FF' = Null Pointer, no JIB for this LUB.

A LUB has a JIB pointer when:

1. The logical unit is temporarily assigned.
2. The logical unit assignment is alternate (ALT).

Bytes 76 and 77 (X'4C'–'4D') of the partition communication region contain the address of the LUB table. Label LUBTAB identifies the first byte of the table.

Note 1: SYSUSE may be called SYSCTL in error recovery messages.

Storage Protection Key
Partition Identification Key (PIK)

Storage protection keys are assigned depending on the number of partitions according to the following scheme:

Part. name	PIK value in COMREG										
	12	11	10	9	8	7	6	5	4	3	2
SYS	00	00	00	00	00	00	00	00	00	00	00
BG	10	10	10	10	10	10	10	10	10	10	10
F1	C0	B0	A0	90	80	70	60	50	40	30	20
F2	B0	A0	90	80	70	60	50	40	30	20	
F3	A0	90	80	70	60	50	40	30	20		
F4	90	80	70	60	50	40	30	20			
F5	80	70	60	50	40	30	20				
F6	70	60	50	40	30	20					
F7	60	50	40	30	20						
F8	50	40	30	20							
F9	40	30	20								
FA	30	20									
FB	20										

Task Identifier (TID)

Tasks are identified by hexadecimal numbers 1 to n where n depends on the number of subtasks generated in the supervisor. The following table shows the task identifier (TID) values and their assignments to particular tasks:


System Tasks:					
01	SNS	07	SUP	0D	Reserved
02	DSK	08	DIR	0E	Reserved
03	RAS	09	CRT	0F	SVT
04	PMR	0A	ASY	10-1F	Reserved
05	PGT	0B	ERP	20	AR
06	PGN	0C	LCK		

Main Tasks:					
20	AR	26	F5 *	2B	FA *
21	BG	27	F6 *	2C	FB *
22	F1 *	28	F7 *	2D	Reserved
23	F2 *	29	F8 *	2E	Reserved
24	F3 *	2A	F9 *	2F	Reserved
25	F4 *				


* depending on the number of partitions all or some of these keys may be unused (in descending order of values).

Subtasks:


30-nn



SUPERVISOR
SYSTEM GETVIS AREA



JOB INFORMATION BLOCK (JIB) TABLE




Byte(s)	Description	
0-1 (Contents depends on the bit setting in byte 2)	Bit setting Byte 2	Contents
	Bit 0 = 1 Stored standard assignment Bit 1 = 1 Alternate assignment	LUB entry of stored standard assignment. (PUB and JIB pointer) Byte 0: PUB Pointer Byte 1: X'00'
2	Meaning if bit = 1 Bit 0: Stored standard assignment Bit 1: Alternate assignment Bit 4: The alternate assignment indicated in bit 1 is permanent. Bit 5: Cataloged procedure processing Bit 6/7: Reserved	
3	Chain byte Contains the displacement index of the next JIB. X'FF' defines the end of the chain.	

Bytes 68-69 (X'44'-'45') of the partition communication region contain the address of the JIB table entry. Label JIBTAB identifies the first byte of the table.

CHANNEL QUEUE TABLE (CHANQ)

Bytes 37–39 (X'25'–X'27') of the system Communication Region (SYSCOM) contain the address of the Channel Queue table. Label CHANQ identifies the first byte of the table.



Channel Queue Table (CHANQ)

The layout of an entry is as follows:


Bytes	Contents
0	Contains the displacement within the channel queue of the next entry in the free list or in the list for a specific device, or X'FF' when it is the last entry in the free list or a device list.
1–3	Contains the CCB/IORB address for the specified device.
4	Contains the partition identification key, PIK.
5	Contains information on special processing that is required for this I/O request: <ul style="list-style-type: none"> X'80' Interrupt not yet processed X'40' Dequeue unconditional X'20' Do not dequeue entry X'10' Console buffering request X'08' Reserved X'04' DASD file protect needed X'02' SYSFIL on CKD device X'01' SYSFIL on FBA device
6	Contains pointer (displacement index) to the LUB table, identifying the logical unit making the I/O request. This is doubled to get the actual displacement into the LUB table. This byte contains X'FF' if this is not a request for a system logical unit.
7	Contains the Task ID (TID).
8	Contains information on the conditions encountered at SIO-time. <ul style="list-style-type: none"> X'F0' Physical I/O information X'80' Device running X'40' Alternate channel I/O X'30' Reserved X'0F' SIO condition code X'08' Condition code is 0 X'04' Condition code is 1 X'02' Condition code is 2 X'01' Condition code is 3

CHANNEL QUEUE TABLE (. . . Cont'd)

- 9–11 Contains transmission information as passed from the user CCB/IORB (bytes 2, 3 and 12).
- 12 Reserved for page fixing routine.
- 13–15 Address of internal fix list as returned from page-fix routine.
- 16 Error retry count
- 17 Special CCW chain pointer
- 18 Reserved
- 19 PUB entry number
- 20 Contains head queue related processing information:
 X'80' Reserved
 X'40' Head queue request
 X'20' Device busy status from PUB
 X'10' Queued-in-error from PUB
 X'08' SIO request was accounted
- 21 Contains information on the requestor issuing the I/O request:
 X'04' RAS retry request
 X'FB' Reserved
- 22 Contains information on the group of devices the device belongs to:
 X'80' CKD device or diskette
 X'40' FBA device
 X'20' Tape device
 X'10' Teleprocessing device
 X'08' 2260 or 3277 device
 X'04' Unit record device
 X'03' Reserved
- 23 Contains information on where to continue I/O interrupt processing:
 X'00' Dispatcher (DISP)
 X'04' I/O initiator (INITRG)
 X'08' I/O interrupt handler (INTRIN)
 X'0C' I/O error IGNORE routine (IGNORE)
 X'10' CANCEL (ERR 1A)
 X'14' CANCEL (ERR 31)
- 24–31 Contain the accumulated I/O interrupt information.

CHANNEL CONTROL TABLE

CHNTAB




Channel Control Table (CHNTAB)

Bytes

- 0 X'10' Byte Multiplexer Channel
 X'11' Byte Multiplexer Channel with burst mode support
 X'13' Byte Multiplexer Channel running in burst mode
 X'20' Block Multiplexer Channel
 X'00' Selector Channel
 X'80' Channel not operational or not present to the system
 - 1 Number of unit checks pending on this channel
 - 2 Flag Byte
 X'80' Channel must be restarted
 X'7F' Reserved
 - 3 Channel ID
 - 4–7 Address of first PUB on channel
 - 8–11 Address of next PUB started on channel
 - 12–15 Address of PUB that needs channel exclusively
- Label CHNTAB identifies the first byte of this table.

TRACK HOLD (THTAB) TABLE



Track Hold Table (THTAB)


Bytes

- 0 Pointer to next entry in chain (forward pointer). All table entries belonging to one PUB are chained together. The chain delimiter is X'FF'.
- 1–3 CCB/IORB address
- 4–11 For CKD devices: Address of the track held, in the form BBCCHHOO.
For FBA devices: Physical block number of first and last block of the range held.
- 12 Pointer to previous entry (backward pointer). The first entry of the chain contains the PUB index.
- 13 Flag and count byte:
 - Bit 0: A task is waiting for this track or range of blocks.
 - Bit 1: First entry of queue. Byte 12 contains PUB index.
 - Bit 2, 3: Reserved
 - Bit 4–7: Hold count: the number of holds is one more than this value.
- 14, 15 Key of task owning this entry.

Bytes 77–79 (X'4D'–X'4F') of the System Communication Region (SYSCOM) contain the address of the Track Hold table. Label THTAB identifies the first byte of the table.

Byte 76 (X'4C') of the System Communication Region (SYSCOM) contains the address of the Track Hold Free List Pointer. Label THFLPTR identifies the location of the pointer.

CONSOLE BUFFERING TABLE




CBNEXT points to next buffer entry

- Bytes 0–7 **CCW**:
Command code, chain byte, and count field copied from the user's CCW. The data address is always the address of the data portion of the buffer entry.
- Bytes 8–23 **CCB**:
The CCB used by the console buffering routine. The CCW address is always the address of the CCW in the buffer entry.
- Bytes 24–103 Contains the data moved from the requestor's output area.

Label CBTAB identifies the first byte of the Console Buffer Table.


LINE MODE TABLE



Bytes 140–143 (X'8C'–X'8F') of the System Communication Region (SYSCOM) contain the address of the table. Label MODTAB identifies the first byte of the table.

This table is required by the models 115/125 only and is used to save the TP mode at IPL time.

RELATIONSHIP OF CONTROL AND WORKBLOCKS FOR CHANNEL PROGRAM FIXING



LAYOUT OF FIXLIST HEADER BLOCK

FHB1

X'00'	Flag Byte 1 (General Fixing Function)	Flag Byte 2 (Reserved)	TIK/PIK of Requestor
X'04'	Pointer to next active FHB		
X'08'	BA1*		EA1*
X'0C'	BA2		EA2
X'10'	BA3		EA3
X'14'	BA4		EA4
X'18'	BA5		EA5
X'1C'	BA6		EA6
X'20'	Pointer to next fixlist block		

Layout of Fixlist Header Block (FHB) for General Fixing Function

FHBn

X'00'	Flag Byte 1 (General Fixing Function)	Flag Byte 2 (Fast Fixing Support)	TIK/PIK of Requestor
X'04'	Saved queue forward pointer		
X'08'	Saved queue backward pointer		
X'0C'	Pointer to replica or zero		
X'10'	Pointer to next active FHB		
X'14'	BA1*		EA1*
X'18'	BA2		EA2
X'1C'	BA3		EA3
X'20'	Pointer to next fixlist block		

Note:
Bytes 16–19 (X'14'–X'17') of the Fix Request Block (FRB) contain the address of the Fixlist Header Block (FHB).

Layout of Fixlist Header Block (FHB) for Fast Fixing Support

Flag Byte 1 (General Fixing Function):

- Bit 0 = 1 Fixing function request complete.
- Bit 1 = 1 At least one page is fixed for this task or the fixing request is pending.
- Bit 2 = 1 Fixing of pages required.
- Bit 3–7 Reserved.

Flag Byte 2 (Fast Fixing Support):

- Bit 0 = 1 Fast fixing in progress.
- Bit 1 = 1 FHB belongs to saved FHB queue.
- Bit 2–7 Reserved.

- * BA = Page number multiplied by 8 of first page to be TFIXed.
- EA = Page number multiplied by 8 of last page to be TFIXed.

LAYOUT OF FIXLIST BLOCK (FLB)

X'00'	BA1	EA1
X'04'	BA2	EA2
X'08'	BA3	EA3
X'0C'	BA4	EA4
X'10'	BA5	EA5
X'14'	BA6	EA6
X'18'	BA7	EA7
X'1C'	BA8	EA8
X'20'	Pointer to next fixlist block or zero	

Note:
Bytes 32–36 (X'20'–X'24') of the Fixlist Header Block (FHB) contain the address of the Fixlist Block (FLB).

Layout of Fixlist Block (FLB)

FIX REQUEST BLOCK

X'00'	Flag byte 0
X'01'	Flag byte 1
X'02'–'03'	Reserved
X'04'–'07'	PTR to Setflag RTN
X'08'–'0B'	PTR to Statusmodifier
X'0C'–'0F'	PTR to Contr.Comm.List
X'10'–'13'	PTR to FHB (Fixlist)
X'14'–'17'	PTR to LINEPTR Stack
X'18'–'1B'	PTR to Locate List
X'1C'–'1F'	Actual locate list entry
X'20'–'33'	Work area
X'34'–'73'	Reg. (0–F) save area

Note:
Note: FRB is located in the TCB work area.

Fix request Block Example

Flag Byte 0:

- Bit 0 = 1 Data chaining specified
- Bit 1 = 1 READ/SENSE command
- Bit 2 = 1 READ BACKWARD command
- Bit 3 = 1 Status modifier command (STM) and data chaining
- Bit 4 = 1 Status modifier command (STM)
- Bit 5 = 1 Status modifier handling in process
- Bit 6 = 1 Reserved
- Bit 7 = 1 DOIO request (Routine CCWDOIO)

Flag Byte 1 (Fast Fixing Support):

- Bit 0 = 1 Replica creation required
- Bits 1–7 Reserved

LAYOUT OF LOCATE LIST BLOCK

Locate List Block 1

BA1	EA1
BA2	EA2
X'00 00 00 00'	
Pointer to Next Block	

Note:
Bytes 24–27 (X'18'–X'1F') of FRB contain the address of Locate List Block 1.

Locate Block 2

BA4	EA4
X'00 00 00 00'	
Pointer to Next Block	

LAYOUT OF LINE POINTER BLOCKS

Free Entry	Free Entry
LP8	LP7
LP6	Pointer to Current Entry Block
Pointer to Next Block	

Note:
Bytes 20–23 (X'14'–X'17') of FRB contain the address of Line Pointer Block.

LP 5	LP4
LP3	LP2
LP1	Pointer to Current Entry in Block
X'00 00 00 00'	


Line Pointer List Example

DENSITY DATA


Density (Bytes per inch)	Parity	Convert Feature	Translate	SS Code *
200	odd	on	off	10
200	odd	off	off	30
200	odd	off	on	38
200	even	off	off	20
200	even	off	on	28
556	odd	on	off	50
556	odd	off	off	70
556	odd	off	on	78
556	even	off	off	60
556	even	off	on	68
800	odd	on	off	90
800	odd	off	off	B0
800	odd	off	on	B8
800	even	off	off	A0
800	even	off	on	A8
800	dual density nine-track			C8
1600	dual density nine-track			C0
6250	dual density nine-track			D0
800	single density nine-track			C0
1600	single density nine-track			C0
6250	single density nine-track			D0

* Refer to PUB Table, byte 5


EVENT CONTROL BLOCK (ECB)



RESOURCE CONTROL BLOCK (RCB)



CROSS PARTITION ECB (XECB) TABLE



Byte 8 (Access Code):

- Bits 0 Table entry in use
- 1 Task that issued XPOST has terminated
- 2, 3 Always zero
- 4, 5 XWAIT access indicator
 - 01 = Access = XWAIT specified
 - 10 = Access = XPOST specified
- 6, 7 XPOST access indicator
 - 01 = Access = XPOST specified
 - 10 = Access = XWAIT specified


Parameterlist for TYPE = DEFINE

- Bytes 0–7 XECB name
- Byte 8 X'0n', bits 4–7 contain the access code

Parameterlist for TYPE = DELETE or DELETALL or RESET or CHECK

- Bytes 0–7 XECB name
- Bytes 8–9 X'1000' TYPE = RESET
- X'4000' TYPE = DELETE
- X'4800' TYPE = DELETALL
- X'8000' TYPE = CHECK

DSKPOSBG

DSKPOSF_n

DSKPOSF2

DSKPOSF1

The number of DIB tables depends on the number of partitions specified at supervisor generation.

Format of any DIB table if SYSFIL = YES

	0						6	7	9			10				16	17	18	19	20	21	22	23	
	Current Address						K	D	D	End Address				UL	LL	M	RC							
SYSLNK	C	C	H	H	00	00	00	P	P	00	00	00	00	00	00	00	00	00	00	00	00	00		
SYSLN	B	B	C	C	H	H	R	00	00	50	B	B	C	C	H	H	R	H	H	XX	XX	XX	00	00
SYSPCH	B	B	C	C	H	H	R	00	00	51	B	B	C	C	H	H	R	H	H	XX	XX	XX	00	00
SYSLST	B	B	C	C	H	H	R	00	00	78	B	B	C	C	H	H	R	H	H	XX	XX	XX	00	00
PRCDIB	B	B	C	C	H	H	R	00	00	50	B	B	C	C	H	H	R	H	H	XX	XX	XX	00	00

Format of any DIB Table if SYSFIL = NO

	0						6	7	9			10				16	17	18	19	20	21	22	23	
	Current Address						K	D	D	End Address				UL	LL	M	RC							
SYSLNK	C	C	H	H	00	00	00	P	P	00														
PRCDIB	B	B	C	C	H	H	R	00	00	50	B	B	C	C	H	H	R	H	H	Xx	XX	XX	00	00

Format of 3540 Diskette DIB Table

	0						6	7	9			10				16	17	18	19	20	21	22	23	
	Current Address						K	D	D	End address						M	RC							
SYSLN	00	00	00	00	C	H	R	00	00	00	FLG	EXT	HDR	00	C	H	R	00	00	XX	00	00	00	00
SYSPCH	00	00	00	00	C	H	R	00	00	00	FLG	EXT	HDR	00	C	H	R	00	00	XX	00	00	00	00
SYSLST	00	00	00	00	C	H	R	00	00	00	FLG	EXT	HDR	00	C	H	R	00	00	XX	00	00	00	00

DISK INFORMATION BLOCK (DIB) TABLE (. . . Cont'd)

Bytes 0–6	Current address
Bytes 0–5	Current address of key: the next address to be used (both for input and output).
Byte 6	Record number of current address.
Bytes 7–9	KDD Key and data length of the symbolic device. PP: starting cylinder of private core image library if PCIL is assigned; otherwise zero.
Bytes 10–16	End address Bytes 10–15 End address of key: the last address within the limits of the extent. 16 Record number of end address.
Byte 17	UL Upper head limit
Byte 18	LL Lower head limit
Byte 19	M Maximum number of records per track.
Byte 20–21	RC Record count: residual capacity for beginning of operator notification. Set a system generation time with SYSFIL parameter, or after IPL with SET statement (RCLST and/or RCPCH operands). A warning message is issued by job control after end-of-job step when the minimum number of remaining records has been reached or exceeded during the previous job (not supported for 3540).
Byte 22	X'40' Indicates RPS support
Byte 23	Reserved

Label DSKPOSBG identifies the first byte of the BG DIB table.

The address of the DIB tables are contained in bytes 96 and 97 (X'60'–X'61') of the appropriate partition communication region.

DIB Table for FBA devices

Byte(s)	Label	Description
0–3	ULPBN	End address of extent. Upper limit of physical block number
4–7	CRPBN	Current address. Current physical block number
8, 9	CIOFF	Offset of current record within control interval
10, 11	LNGCI	Length of control intervals in bytes
12	PBPERCI	Number of physical blocks per control interval
13–15	PBUFFER	Pointer to data buffer
16	DIBFLAGS	X'01' Buffer-in-use flag X'02' End of extent reached X'04' Force write out X'10' Source begin readjustment required X'40' Task waiting for DIB X'80' DIB gage flag
17–19	PDIBX	Pointer to DIB extension (DIBX).
20, 21	DIBRSCNT	Residual count for JCL message
22, 23		Reserved

A FBA device also requires a DIB extension (DIBX) table. It has the following format:

Byte(s)	Description
0–23	IORB
24–31	Fixlist first area
32–39	Fixlist second area
40–47	DEFINE EXTENT CCW
48–55	LOCATE CCW
56–63	READ/WRITE CCW
64–79	Parameter field for DEFINE EXTENT CCW
80–87	Parameter field for LOCATE CCW

Disk Information Block Extension Table (DIBX) for FBA Devices

TABLES FOR MICR DTF ADDRESSES AND POINTERS

The table of DTF addresses (PDTABB) contains six 8-byte entries; one for each line of the direct control feature on the system.

PDTABB

Byte	0	1	2	3	4	5	6	7
	AND instruction				Owner ship Flags	DTF address for MICR		
0	NI	PDSTAT+1	X'FE'			Device on line 7		
8	NI	PDSTAT+1	X'FD'			Device on line 6		
16	NI	PDSTAT+1	X'FB'			Device on line 5		
24	NI	PDSTAT+1	X'F7'			Device on line 4		
32	NI	PDSTAT+1	X'EF'			Device on line 3		
40	NI	PDSTAT+1	X'DF'			Device on line 2		

Bytes 0–3 The NI instruction is executed in main line coding to turn off the external line status after its detection.

PDSTAT+1 will contain one more of the following interrupt codes:

External interrupt code bit	Interrupt Code (byte X'B7')	External interrupt cause
15	nnnnnnn1	External signal 7
14	nnnnnn1n	External signal 6
13	nnnnn1nn	External signal 5
12	nnnn1nnn	External signal 4
11	nnn1nnnn	External signal 3
10	nn1nnnnn	External signal 2

n = other external interrupt conditions

Byte 4 Contains the flag of the partition containing the DTF
Background = X'10'
Foreground = X'20'–X'n0', depending on the number of partitions

Bytes 5–7 Contain the address of the DTF table

Table of pointers (PDTABA) to DTF addresses with the external interrupt line. The table is set up to handle the status in descending order from bit 15 to bit 10 of the external interrupt code.


PDTABA

Byte	0	1	2	3	4	5	6	7
0	00	08	00	10	00	08	00	18
8	00	08	00	10	00	08	00	20
16	00	08	00	10	00	08	00	18
24	00	08	00	10	00	08	00	28
32	00	08	00	10	00	08	00	18
40	00	08	00	10	00	08	00	20
48	00	08	00	10	00	08	00	18
56	00	08	00	10	00	08	00	

Bytes 126 and 127 (X'7E'–X'7F') of the partitions communication region contain the address of these tables. Label PDTABB identifies the first byte of the first table. The tables are also used for optical reader/sorters.

ERROR RECOVERY PROCEDURE INFORMATION BLOCK (ERPIB)

ERPIBQ




Byte 20 Flag Byte:

- Bit 0 1 = Channel Check on SIO
- 1 1 = Channel Damage ERPIB
- 4 1 = Record has been built
- 6 1 = DASD ERPIB active
- 2,3,5,7 = Reserved

Note: A free entry is indicated by X'FE' in byte zero, end of queue is indicated by 'FF' in byte zero. Label ERPIBQ identifies the first byte of queue.

ERBLOC

ERRQ1



The A-transient loads one of these addresses in register 15 before branching to the return address (see bytes 20-23).

Note:

The address of the ERBLOC can be found in SYSCOM at Displacement 0 (X'00').

Layout of an error queue entry for I/O error or BTAM

Bytes 0-7 CSW

Bytes 8-9 Address of PUB for device in error

Byte 10 Flag byte:

- Bit 0 1 = No record found on DASD
- 1 1 = Intervention required
- 2 1 = Passback (set by device ERP)
- 3 1 = Allow ignore
- 4 Force automatic retry
- 5 1 = Allow retry
- 6 Sense command outstanding
- 7 1 = Active entry

Byte 11 Message code: may refer to a device error recovery message generated by physical IOCS (See Cancel Codes and Messages) or:

This location may contain one of the following:

- X'E2' The error is recoverable
- X'AE' A record is to be recorded on the system recorder file and a physical transient is to be fetched (last two characters of phase name are in bytes 20-21).

CKD devices:

Bytes 12-15 Disk seek address. For an alternate entry, this field contains the address of the PUB of the originating routine.

FBA devices:

Byte 12 OS FBA device type code

Bytes 13-15 X'00'

Byte 16 PUB channel queue pointer

Bytes 17-19 Address of CCB/IORB

Bytes 20-51 Sense data or alternate entry name: If byte 11 contains X'AE', bytes 20-21 contain the last two characters of the phase name of the physical transient to be fetched.

IV-52

CANCEL CODES AND MESSAGES

Cancel Code (hex)	Message Code	Description part of Message or Condition	Label
00	-----	In all cases default value except those listed	
0A	0S21I	Processing error in access control	ERR0A
0B	0S20I	Access control violation	ERR0B
0C	0S19I	Execution failure in ICCF pseudo partition	ERR0C
0D	0V013I	Program Check in subsystem or appendage	
0E	0V014I	Page fault in subsystem or appendage	
0F	0P80I	Invalid 'read from/or write to' system file on FBA device	ERR0F
10	-----	Normal EOJ	ERR10
11	0V07I	No channel program translation for unsupported device	ERR11
12	0V06I	Insufficient buffer space for channel program translation	ERR12
13	0V05I	CCW with count greater than 32 K	ERR13
14	0V04I	Page pool too small	ERR14
15	0V02I	Page fault in disabled program	ERR15
16	0V11I	Error in privately translated CCW	
17	0S02I	Program request (Same as 23 but causes dump because subtasks were attached when maintask issued CANCEL macro).	ERR17
18	-----	Eliminates cancel message when maintask issues DUMP macro with subtasks attached	
19	0P74I	I/O operator option	ERR19
1A	0P73I	I/O error	ERR1A
1B	0P82I	Channel failure	ERR1B
1C	0S14I	CANCEL ALL macro	
1D	0S12I	Maintask termination	
1E	0S13I	I/O error on lock file	
1F	0P81I	CPU failure	ERR1F
20	0S03I	Program check	ERR20
21	0S04I	Illegal SVC	ERR21
22	0S05I	Phase not found	ERR22
23	0S02I	Program request	ERR23
24	0S01I	Operator intervention	ERR24
25	0P77I	Invalid address	ERR25
26	0P71I	SYSxxx not assigned (unassigned LUB Code)	ERR26
27	0P70I	Undefined logical unit (invalid LUB Code in CCB)	ERR27
2A	0V10I	I/O error on page data set	
2B	0P84I	I/O error during fetch from PCIL	ERR2B
2C	0V09I	Illegal parameter passed by PHO routine	ERR2C
2D	0P88I	Failing storage block (program cannot be executed)	ERR2D
2E	0S16I	Invalid resource request (possible deadlock)	ERR2E
2F	0V03I	More than 255 PFIX requests for 1 page	ERR2F
30	0P72I	Reading past /& Statement (on SYSRDR or SYSIPT)	ERR30
31	0P75I	I/O error queue overflow (error queue overflow)	ERR31
32	0P76I	Invalid DASD address	ERR32
33	0P79I	Invalid first CCW	
34		Reserved	
35	0P85I	Job control open failure	ERR35
36	0V08I	Program check or page fault in I/O appendage routine	ERR36

CANCEL CODES AND MESSAGES (. . . Cont'd)


Cancel Code (hex)	Message Code	Description part of Message or Condition	Label
37		Reserved	
38	0V11I	Wrong privately translated CCW	ERR38
39	0V12I	Invalid CCW chain for SYSLOG	
40	5J97I	ACF/VTAM error (invalid condition code)	
41	5J97I	ACF/VTAM error (invalid condition code)	
42	0P86I	Violated DASD file Protection	
XX	0P78I	Unrecognized Cancel Code	
	0P83A**	Supervisor catalog failure	
	0P87A**	IPL Failure	

* If the CCB/IORB is not available, the logical unit is SYSxxx.

** The cancel code is not significant in case of a supervisor catalog or IPL failure, because the system is placed in the wait state without any further processing by the terminator.

xx Any other DIGITS.

PHYSICAL UNIT BLOCK (PUB) TABLE



Byte 0: Channel number (Hex 0–6, FF = NULL)

Byte 1: I/O device unit number

Byte 2: Hex 0, 1, 2, points to the first channel queue entry for this device

Byte 3: Reserved

Byte 4: Device type code

Byte 5: SS of the MODE = parameter in the DVCGEN macro for tape unit. (See section 2)
 For an ICA line Model 115 or 125, this byte contains the displacement index of the entry in the Line Mode Table (LMT). The address of the LMT is in SYSCOM.

For DASD with track hold this byte contains a pointer to the track hold table or X'FF'.

For MICR type devices, this byte indicates which external interrupt line is in use.

For a 3704/3705 Communications Controller, this byte contains the type of the Channel Adapter.

For 2560 or 5424/5425

- | | |
|-------|--|
| Bit 0 | 1 = Repositioning required |
| 1 | 0 = SYSPCH temporarily assigned to hopper 1
1 = SYSPCH temporarily assigned to hopper 2 |
| 2 | 0 = SYSIPT temporarily assigned to hopper 1
1 = SYSIPT temporarily assigned to hopper 2 |
| 3 | 0 = SYSRDR temporarily assigned to hopper 1
1 = SYSRDR temporarily assigned to hopper 2 |
| 5 | 0 = SYSPCH permanently assigned to hopper 1
1 = SYSPCH permanently assigned to hopper 2 |
| 6 | 0 = SYSIPT permanently assigned to hopper 1
1 = SYSIPT permanently assigned to hopper 2 |
| 7 | 0 = SYSRDR permanently assigned to hopper 1
1 = SYSRDR permanently assigned to hopper 2 |

For 3800

- Bits 0 and 1
- | | |
|----|-----------|
| 00 | = 3800 |
| 01 | = 3800 B |
| 10 | = 3800 C |
| 11 | = 3800 BC |

PHYSICAL UNIT BLOCK TABLE (. . . Cont'd)

Byte 6: Channel Scheduler Flags

- Bit 0 1 = Device busy
- 1 1 = Switchable device
- 2 1 = Unit check is pending on device
- 3 1 = I/O error queued for recovery
- 4 1 = Operator intervention outstanding
- 5 1 = I/O interrupt outstanding
- 6 1 = Burst or overrunnable device
- 7 1 = 7-track tape unit


Byte 7: Job Control Flags

- Bit 0–4 Standard MODE assignment for 7-track and 9-track tape (all ones if not tape, all zeros if device is down)
- Bit 5 1 = Device supports RPS
- 6 Reserved
- 7 Unit check pending on alternate channel

Notes: A null entry is generated at supervisor generation time for each device to be supported by the supervisor. Then standard physical unit assignments are made to the PUB table. Physical unit assignments can also be made during IPL. PUBs are ordered by channel and priority within a channel. A PUB entry must be generated or added during IPL for any device of the installation.

An entry in the PUB ownership table is associated with each entry in the PUB table. Bytes 64–65 (X'40'–X'41') of part. com. reg. contain the address of the PUB table entry. Label PUBTAB identifies the first byte of the table.

PHYSICAL UNIT BLOCK OWNERSHIP TABLE



- Byte 0+1: Bit 0 1 = Device is owned by ACF/VTAM
- 1 1 = Waiting for volume to be mounted
- Bit 2–15 Partition ID


Byte 1: Identifies the partition that owns the PUB according to following table:

Flag	Partition owning PUB if number of partition is											
	2	3	4	5	6	7	8	9	10	11	12	
X'0000'	UA*											
X'0001'	BG	BG	BG	BG	BG	BG	BG	BG	BG	BG	BG	BG
X'0002'	F1	F2	F3	F4	F5	F6	F7	F8	F9	FA	FB	FB
X'0004'		F1	F2	F3	F4	F5	F6	F7	F8	F9	FA	FA
X'0008'			F1	F2	F3	F4	F5	F6	F7	F8	F9	F9
X'0010'				F1	F2	F3	F4	F5	F6	F7	F8	F8
X'0020'					F1	F2	F3	F4	F5	F6	F7	F7
X'0040'						F1	F2	F3	F4	F5	F6	F6
X'0080'							F1	F2	F3	F4	F5	F5
X'0100'								F1	F2	F3	F4	F4
X'0200'									F1	F2	F3	F3
X'0400'										F1	F2	F2
X'0800'											F1	F1

*unassigned

Note: The number of entries in the PUB Ownership table is equal to the number of entries in the PUB table. Associated with each PUB entry is an entry in the PUB Ownership table. Bytes 120–123 (X'78'–X'7B') of the system communication region (SYSCOM) contain the address of the PUB Ownership table. Label PUBOWNER identifies the first byte of the table.

PUB2 ENTRY ADDRESSING



How to find the PUB2 entry for a device:

- 1 Subtract from the address of the device PUB, the PUB Table start address and divide the result by 4.
- 2 Find in the RF Table at displacement 64 (X'40') the PUB2 Index Table.
- 3 Use the result from 1 as a displacement into the PUB2 Index Table. This will give you the two bytes index (i. e. displacement) of the PUB2 entry of the device PUB.
- 4 Find in the RF Table at displacement 60 (X'3C') the address of the PUB2 AREA.
- 5 Use the value from 3 as a displacement in the PUB2 AREA.

See PUB2 for the format of the entries for the various device types

PUB 2 TABLE

PUB 2 Table Entry Format for Unit Record and Unsupported Devices

Decimal Displacement	Byte Length	Description
0	3	Usage Count (number of non-ERP SIOs)
3	1	Flag Byte: Bit 0: 1 = Device in intensive mode Bit 1: 1 = Device in diagnostic mode Bit 2: 1 = No recording mode Bit 3: 1 = Call statistics transient 2 Bit 4: 1 = Use PUB 2 name completion field Bit 5: 1 = Volume opened on this device Bit 6,7: Reserved
4	1	CE mode limit byte
5	1	CE mode byte/bit mask
6	6	Statistical data counters
Total length 12		

PUB 2 Table Entry Format for DASD

Decimal Displacement	Byte Length	Description
0	3	Usage Count (number of non-ERP SIOs)
3	1	Flag byte: Bit 0: 1 = Device in intensive mode Bit 1: 1 = Device in diagnostic mode Bit 2: 1 = No recording mode Bit 3: 1 = Call statistics transient 2 Bit 4: 1 = Use PUB 2 name completion field Bit 5: 1 = Volume opened on this device Bit 6,7: Reserved
4	1	CE mode limit byte
5	1	CE mode byte/bit mask
6	1	Flag byte: Bit 0: 1 = Soft DASD error is queued Bit 1: 1 = ERP requests logging of error Bit 2–7: Reserved
7	2	Reserved
9	1	Physical module identifier
10	6	Volume serial number
End 3330/3340/3350/FBA Total length 16		
16	8	Statistical data counters
End 2311 and 2314/2319 Total length 24		

PUB 2 Table Entry Formats for Tapes

Decimal Displacement	Byte Length	Description
0	3	Usage Count (number of non-ERP SIOs)
3	1	Flag Byte: Bit 0: 1 = Device in intensive mode Bit 1: 1 = Device in diagnostic mode Bit 2: 1 = No recording mode Bit 3: 1 = Call statistics transient 2 Bit 4: 1 = Use PUB 2 name completion field Bit 5: 1 = Volume opened on this device Bit 6,7: Reserved
4	1	CE mode limit byte
5	1	CE mode byte/bit mask
6	2	Name of ERP that wants control

PUB 2 TABLE (. . . Cont'd)

PUB 2 Table Entry Formats for Tapes

Decimal Displacement	Byte Length	Description
8	1	Flag byte 1: Bit 0: Reserved Bit 1: 1 = Unsolicited interrupt Bit 2: 1 = ERP is in control Bit 3: 1 = ERP requests repositioning* Bit 4: 1 = Use original TIE byte * 0 = Use opposite TIE byte * Bit 5: 1 = Intercept next SIO request * Bit 6: 1 = ERP read opposite request * Bit 7: 1 = Restart user's CCW chain *
9	1	Flag byte 2: Bit 0: 1 = Last ERP operation was ERG * Bit 1: 1 = Last ERP operation was reposition * Bit 2: 1 = Cleaner action in progress * Bit 3: 1 = Read Opposite Recovery in progress * Bit 4: 1 = Message stored in P2ORGTIE Bit 5: 1 = Error on attempt to recover by repositioning * Bit 6: 1 = Data check after ERP in control * Bit 7: Reserved
10	1	Flagbyte3*: Bit 0: 1 = Failing CCW is Write or Control command Bit 1: 1 = User reading backwards Bit 2: 1 = Read Opposite Recovery (ROR) Bit 3: 1 = Maximum ROR retries Bit 4: 1 = Command chaining ROR Bit 5: 1 = ROR suppressed incorrect length Bit 6: 1 = User used SILI (Suppress Incorrect Length Indicator) Bit 7: 1 = Reserved
11	1	Temporary read count
	8	Save Area for 1st 8 sense bytes (8809)
12	1	Temporary write count
13	1	Noise record count
14	2	Erase gap count
16	2	Cleaner action count
18	1	Permanent read errors count
19	1	Permanent write errors count *
20	1	TIE original direction
	1	SAVE AREA for message number (8809)
21	1	TIE opposite direction *
22	1	ERP counter 0 *
23	1	ERP counter 1 *
24	8	ERP work area
32	6	Tape serial number
38	2	Block Length
40	4	User ROR command address from CSW
	8	User CCW area during rewind/unload (8803)
44	2	User ROR residual count from CSW
46	2	Reserved
48	16	Work area for rewind-unload error action
	24	SAVE AREA for last 24 sense bytes (8809), end of 8809 entry: total length 72 bytes
64	10	2400-series statistical data counter area
74	2	Reserved
End 2400-series: Total length 76		
64	20	3410/3420 statistical data counter area
End 3410/3420: Total length 84		

* Fields not used for 8809 tape entry

PUB 2 TABLE (. . . Cont'd)

PUB 2 Table Entry Format for 3886 Optical Character Reader

Decimal Displacement	Byte Length	Description
0	3	Usage count (number of non-ERP SIOs)
3	1	Flag byte: Bit 0: 1 = Device in intensive mode Bit 1: 1 = Device in diagnostic mode Bit 2: 1 = No recording mode Bit 3: 1 = Call statistics transient 2 Bit 4: 1 = Use PUB2 name completion field Bit 5: 1 = Volume opened on this device Bit 6, 7: Reserved
4	1	CE mode limit byte
5	1	CE mode byte/bit mask
6	20	Statistical data counters
End 3886		Total length 26

PUB 2 Table Entry Format for 3540 Diskette

Decimal Displacement	Byte Length	Description
0	3	Usage Count (number of non-ERP SIOs)
3	1	Flag byte: Bit 0: 1 = Device in intensive mode Bit 1: 1 = Device in diagnostic mode Bit 2: 1 = No recording mode Bit 3: 1 = Call statistics transient 2 Bit 4: 1 = Use PUB2 name completion field Bit 5: 1 = Volume opened on this device Bit 6, 7: Reserved
4	1	CE mode limit byte
5	1	CE mode byte/bit mask
6	8	Statistical data counters
14	1	Bit 0–5: Reserved Bit 6: 1 = System file opened by Job Control Bit 7: 1 = System file opened by Problem Program
15	1	Reserved
End 3540		Total length 16

PUB 2 Table Entry Format for 3895 DOC Reader/Inscriber and 3890 DOC Processor

Decimal Displacement	Byte Length	Description
0	3	Usage Count (number of non-ERP SIOs)
3	1	Flag byte: Bit 0: 1 = Device in intensive mode Bit 1: 1 = Device in diagnostic mode Bit 2: 1 = No recording mode Bit 3: 1 = Call statistics transient 2 Bit 4: 1 = Use PUB 2 name completion field Bit 5: 1 = Volume opened on this device Bit 6, 7: Reserved
4	1	CE mode limit byte
5	1	CE mode byte/bit mask
6	2	Name of ERP requesting control
End 3895:		Total length 8
6	10	Statistical Data Counters
End 3890:		Total length 16

PUB 2 TABLE (. . . Cont'd)

PUB 2 Table Entry Format for 3800 Printer

Decimal Displacement	Byte Length	Description
0	6	Standard PUB 2 area prefix
6	1	SDR counter 1 Channel data checks
7	1	SDR counter 2 Stacker misfolds
8	1	SDR counter 3 Burster-trimmer jams
9	1	SDR counter 4 No burst checks
10	1	SDR counter 5 Burster-stacker jams
11	1	Default flags Bit 0: 1 = Default specification is to burst Bit 1-7: Reserved
12-15	4	Reserved
16	4	Default FCB identifier
20	4	Default character arrangement table identifier
24	4	Default copy modification identifier
28	4	Default forms overlay frame identifier
32	4	Default paper forms identifier
36	4	IDs of character sets loaded in printer
40	1	WCGMs with modified character sets Bit 0: WCGM0 contains a modified character set Bit 1: WCGM1 contains a modified character set Bit 2: WCGM2 contains a modified character set Bit 3: WCGM3 contains a modified character set Bit 4-7: Reserved
41	1	Flag Byte 1: X'30': Burst = Y requested X'10': Burst = N requested X'08': DCHK = U specified
42	1	Flag Byte 2: X'30': TRC=Y specified X'10': TRC=N specified X'0E': DEBUG=TRAC last specified X'0A': DEBUG=DUMP last specified X'06': DEBUG=TERM last specified X'02': DEBUG=NONE last specified
43	1	Reserved
44	4	ID for currently loaded FCB
48	4	ID for first character arrangement table currently loaded
52	4	ID for second character arrangement table currently loaded
56	4	ID for third character arrangement table currently loaded
60	4	ID for fourth character arrangement table currently loaded
64	4	ID of the character arrangement table used for the current copy modifications
68	4	ID of the copy modification currently loaded
72	4	ID of forms currently loaded
76	4	ID of current forms overlay frame
80	8	Eight copy group counts last received by SETPRT
88	1	ID of copy group last received by SETPRT
89	1	Flash count last received by SETPRT
90	2	Reserved

RECORDER FILE TABLE (RF TABLE)

Displacement		Label	Byte Length	Description
Dec	Hex			
		RFTABLE		Label of Starting Address
0	0	RFFLAGS1	1	Bit 0: 1 = File full Bit 1: 1 = RDE option included Bit 2: 1 = Initial IPL Bit 3: Reserved Bit 4: 1 = File is to be created Bit 5: 1 = File has been created Bit 6: 1 = File is on FBA device Bit 7: 1 = File open and ready
1	1	RFFLAGS2	1	Bit 0: 1 = File full message request Bit 1: 1 = Threshold message request Bit 2: 1 = I/O error message request Bit 3: 1 = Data lost message request Bit 4: 1 = EVA message request Bit 5: 1 = File owned by RTA recorder Bit 6: 1 = File owned by PTA recorder Bit 7: 1 = File being accessed by EREP
2	2	RFLAGS3	1	Bit 0: 1 = Threshold message issued once Bit 1: 1 = Error is to be recorded Bit 2: 1 = Short form records request Bit 3: 1 = Individual records for unlabeled tapes Bit 4: 1 = Reserved Bit 5: 1 = Reserved Bit 6: 1 = Exit to \$\$BOMT05 indicator for \$\$BOPEN Bit 7: 1 = Exit to \$\$BOMT01 indicator for \$\$BOPEN
3	3	RFFLAGS4	1	Work area switches for various transients including BTAM Bit 0: 1 = Multiple records required (PRT1, 3895, recording) Bit 1: 1 = PLB record required (PRT1 recording) OBR record required (3895 recording) Bit 2: 1 = FCB record required (PRT1 recording) MDR records required (3895 recording) Bit 3: 1 = UCB record required (PRT1 recording) Bit 4: 1 = Ignore exit requested (PRT1 recording) Bit 5: Reserved Bit 6: 1 = Retry exit requested Bit 7: 1 = Record not written
4	4	RFFLAGS5	1	Reserved
5	5	RFNOFN	1	N of N records (low order 4 bits contain the number of records to be recorded and high order 4 bits contain the record number being processed)
6	6	RFRECTYP	1	Record type code
7	7	RFREL	1	ID/release code of VSE/AF
8	8	RFRDSW1	1	Record dependent switch 1
9	9	RFRDSW2	1	Record dependent switch 2
10	A	RFBUFLG	2	Length of data buffer (FBA)
12	C	RFMCONST	2	Multiplier for track balance (CKD)
		RFBUFAD	4	Address of data buffer (FBA)
14	E	RFDCONST	2	Divisor for track balance (CKD)
16	10	RFOCONST	2	Overhead for track balance (CKD)
		RFNAVR	(2)	Displacement of next available RDF in buffer (FBA)
18	12	RFRECLN	2	Length of record
20	14	RFTIMEA	4	Address of RMSR time entry
24	18	RFRECADR	4	Address of record
28	1c	RFSEEK	7	Work area for seek address (BBCCHRR) (CKD)
		RFCUBL	(4)	Work area for block number (FBA)
			(3)	Reserved

RECORDER FILE TABLE (RF TABLE) (. . . Cont'd)

Displacement		Label	Byte Length	Description
Dec	Hex			
35	23	RFEREPK	1	Key of EREP partition
36	24	RFHDRCH	4	SYSREC cylinder/head (CKD)
		RFHDRBL	(4)	SYSREC block number (FBA)
40	28	RECHMAP	2	Map of supported channels
42	2A	RFCHIDC	8	Channel ID codes
50	32	RFRDSWO	1	Record dependent switch
51	33		1	Reserved
52	34	RFEXIT	4	Exit phase name or exit address
56	38	RFEVARTH	1	EVA read threshold
57	39	RFEVAWTH	1	EVA write threshold
58	3A	RFP2ENTL	2	Length of PUB2 Entry Area
60	3C	RFP2ENT	4	Address of PUB2 Entry Area
64	40	RFP2ITAB	*	PUB2 Index Table

* Two bytes are generated for each PUB2 entry in the system. (See PUB2 Entry Addressing for using the PUB2 Index Table to access the PUB2 entries.)


Bytes 100–103 (X'64'–X'67') of the system communication region (SYSCOM) contain the address of the Recorder File Table. Label RFTABLE identifies the first byte of the table.

TASK INFORMATION BLOCK (TIB)


Bytes			Contents
Dec	Hex	Length	
0	0	4	TIB Pointer of WAIT chain
4	4	4	Bound state of WAIT chain
8	8	4	Flag byte, pointer Byte 0: X'80' Flag for PHO TIBs X'40' PHO initialized for this task X'40' PHO TIB: Request enqueued X'20' End of Task is active X'10' Task is seizing system X'08' Task active in LTA X'04' Task is LTA owner X'02' Terminator active for task X'01' At least on VTAM ACB open Bytes 1–3: Pointer to TCB (normal TIB), address of PHO appendage (PHO TIB)
12	C	2	TID and significant byte Byte 0: User task: TID of task System task: TID of serviced task PHO TIB: TID of PHO owner in partition Byte 1: Significant byte of TIBRTID
14	E	2	User task: owner partition PIK System task: Service partition PIK
16	10	4	Pointer to PCB of owner partition
20	14	4	Address of task status byte in PCB
24	18	1	Flags (display exit routines) X'80' Return to SVC routine after page fault X'40' Delayed CCB posting X'20' Initialize task termination X'10' ICCF PP eligible for roll-out X'08' Process delayed timer interrupt X'04' Schedule user OC exit X'02' Call VTAM AP exit routine X'01' Restart SVC processing
25	19	1	Flag byte X'80' ICCF pseudo partition X'40' Power main task X'20' Account CPU time as overhead X'10' Status saved in special area
26	1A	1	First cancel code
27	1B	1	Last cancel code; X'80' flag for terminator canceled
28	1C	6	Significant part of timer interrupt
34	22	2	Offset within TIBATAB of next TIB in IT chain

TASK CONTROL BLOCK (TCB)


1) Short SYSTEM task TCB




2) Long SYSTEM task TCB



3) Attention or user task TCB




4) Overlay within TCB work area



The actual length of a TCB is contained in the field TIBTCB of the corresponding TIB.


TASK SELECTION

Partition Selection String (PSS)




n = number of Partitions
 S = 0: no task of the partition is ready to run
 S not 0: at least one task of the part. is ready to run

Partition Identifier String (PIDSTR)




n = number of Partitions
 0, P₁...P_n = partition identifiers

PCB Address Table (PCBATAB)




Task Selection String (TSS)



S = Status Byte
 A task is ready to run when S is pointing to a free resource in RETAB.


Internal Resource Table (RETAB)



n = number of resources
 S = 0: resource is occupied
 S not 0: resource is free


TASK SELECTION (. . . Cont'd)

Task Identifier String (TIDSTR)



TIDSTR describes the priority of tasks within a partition. It is located in the PCB.

TIB Address Table (TIBATAB)




n = number of partitions

m = number of subtasks

PTR = TIB Pointer

TASK SELECTION (. . .Cont'd)

Task Selection Control Block Interrelationship



TASK SELECTION (...Cont'd)

Task Status Flags and Resource Gates

<u>TYPE</u>	<u>FLAG VALUE (HEX)</u>	<u>FLAG SYMBOL. NAME</u>	<u>MEANING</u>	
P	63	ICCFBND	GATE FOR ICCF HIGH PRTY TASK	
QS	64	OREBND	GATE FOR OPER.REQ.ELEMENT	
QS	65	EOTBND	GATE FOR EOT ROUTINE	
P	66	SCYBND	GATE FOR SECURITY TASK	
P	67	LCKBND	GATE FOR LOCK FILE I/O	
P	68	PGFXBND	GATE FOR PAGE TO BE FREED	
QS	69	GSMBND	GATE FOR ALLOCATE PROCESSING	
QS	6A	THTABBND	GATE FOR TRACK HOLD TABLE	
QS	6B	GSLBND	GATE FOR SETLIMIT PROCESSING	
P	6C	SFILBND	GATE FOR SYSFIL I/O	
QS	6D	SGTVSBND	GATE FOR GETVIS SVA	
QS	6E	LQ BND	GATE FOR SECURITY LOGGER QUEUE	
QS	6F	CBFBND	GATE FOR CONSOLE BUFFERS	
P	70	MICRBND	GATE FOR MICR I/O	
QS	71	GETRBND	GATE FOR GETREAL PROCESSING	
QS	72	FDIRBND	GATE FOR PROGRAM FETCH DIRECTORY	
QS	73	SEIZEBND	GATE FOR SEIZE TO BE FREED	
QS	74	CILBND	GATE FOR CIL UPDATE	
QS	75	BUFBND	GATE FOR COPY BLOCKS	
QS	76	SDLBND	GATE FOR SDL UPDATE	
QS	77	PFRBND	GATE FOR PAGE FRAMES	
QS	78	PFGBND	GATE FOR PAGE FRAMES	
QS	79	CHQBND	GATE FOR CHANNEL QUEUE ENTRY	
QS	7A	DIBBND	GATE FOR DIB ACCESS	
QS	7B	CCWBND	GATE FOR CCW TRANSLATION	
CP	7C	TRKBND	GATE FOR TRACK TO BE FREED	
CP	7D	AVRBND	GATE FOR AVR PROCESSING	
QS	7E	G41BND	GATE FOR ENQ/DEQ PROCESSING	
QS	7F	G92BND	GATE FOR XECB PROCESSING	
P	80	NOTACT	INACTIVE	
QS	81	LTABND	GATE FOR LTA TO BE FREED	
FP	82	WAITBND	GATE FOR ECB/XECB (I/O OR TIMER OR POST)	
P	83	READY	READY TO RUN	
QS	84	IDRABND	GATE FOR PROGRAM FETCH IDRA	
P	85	FETCBND	GATE FOR PROGRAM FETCH PROCESSING	
CP	86	PGIOBND	GATE FOR PAGE I/O	
P	87	PMRBND	GATE FOR PAGE FAULT PROCESSING	
FP	88	ENQBND	GATE FOR RCB TO BE FREED	
QS	89	TERMBND	GATE FOR TERMINATOR PROCESSING	
P	8A	PGINBND	GATE FOR PAGEIN	
QS	8B	USEBND	GATE FOR LOCK/UNLOCK PROCESSING	
P	8C	CNCLBND	GATE FOR SUBTASK TO BE CANCELLED	
QS	8D	SSI0BND	GATE FOR SUBSYSTEM ID PROCESSING	
CP	8E	RURBND	GATE FOR LOCK TO BE FREED	
QS	8F	EXNTBND	GATE FOR EXTENT PROCESSING	
S	90	GTVBND	GATE FOR PARTITION GETVIS	} FOR SYSTEM PARTITION
S	91	CDLBND	GATE FOR CDLOAD	
S	92	PFXBND	GATE FOR PFIX	
S	93	GTVBND8G	GATE FOR PARTITION GETVIS	} FOR FIRST USER PARTITION
S	94	CDLBND8G	GATE FOR CDLOAD	
S	95	PFXBND8G	GATE FOR PFIX	
S	A2	GTVBND87	GATE FOR PARTITION GETVIS	} FOR 6TH USER PARTITION
S	A3	CDLBND87	GATE FOR CDLOAD	
S	A4	PFXBND87	GATE FOR PFIX	
S	B4	GTVBND81	GATE FOR PARTITION GETVIS	} FOR 12TH USER PARTITION
S	B5	CDLBND81	GATE FOR CDLOAD	
S	B6	PFXBND81	GATE FOR PFIX	

Note and declaration of type see next page.

TASK SELECTION (. . . Cont'd)

NOTE: PARTITION DEPENDENT BOUND CONDITIONS X'96' TO X'B6' MAY BE ASSIGNED TO DIFFERENT PARTITIONS DEPENDING ON THE NUMBER OF PARTITIONS GENERATED.

EXAMPLE: TWO PARTITION SYSTEM;
X'96', X'97', X'98' BELONG TO F1
X'99' TO X'B6' ARE NOT USED

DECLARATION TO TYPE ENTRY:

P: PERMANENTLY OPENED/CLOSED GATE
S: SWITCHABLE GATE
QS: WAITER QUEUE WITH SWITCHABLE GATE
CP: WAITER CHAIN WITH PERMANENTLY CLOSED GATE
FP: FLAGGED TASKS WITH PERMANENTLY CLOSED GATE

JOB ACCOUNTING INTERFACE COMMON TABLE

Displacement	Label	Description
	(ACCTCOMN)	
0–15	ACCTSVRG	Temporary register save area
16–17	ACCTSVRX	Reserved
18–19	ACCTSVRE	Reserved
20–23	ACCTPCNT	Count of partitions using the Job Accounting interface
24	ACCTSAID	Reserved
25	ACCTFAID	Reserved
26	ACCTRAID	Accounting ID: X'00' Overhead time X'04' Allbound time Byte 1 of PIK for CPU time
27	ACCTSWCH	Accounting switches: Bit 0 1 = Cancel accounting Bit 1 1 = No active partitions Bit 2 1 = Catalog in process Bit 3 1 = Alternate label area Bit 4 1 = IPL indicator Bit 5 1 = Reserved Bit 6 1 = Reserved Bit 7 1 = Reserved
28–31	ACCTIME	Reserved
32–33	ACCTRESC	Reserved
34–35	ACCTUSEP	Address of user save area (ACCTUSER)
36–37	ACCTUSEL	Length of user save area (Set with 1st operand of FOPT macro parameter JALIOCS)
38–39	ACCT&JOB	Job accounting partition indication
40–43	ACCTBLES	Address of BG Job Accounting Table

This table is to be extended (depending on the number of supported partitions) according to the pattern shown below.

NPARTS=n

44–47		Address of Fn Accounting Table
+ 4		Address of F2 Job Accounting Table
+ 4		Address of F1 Job Accounting Table
+ (n*2)-1	ACCTSEAS	Control Field: prevents the accounting routine being loaded twice

* These values are the same as the PIK values for the relevant tasks.

Byte 124–127 (X'7C'–X'7F') of the system communication region (SYSCOM) contain the address of the Job Accounting Interface Common Table. Label ACCTCOMN identifies the first byte of the table.

JOB ACCOUNTING INTERFACE PARTITION TABLE

Displacement	Label	Description
	(ACCTABLE)	
0-3	ACCTWK1	Work area used by job control
4-7	ACCTWK2	Work area used by job control
8-11	ACCTSVPT	Job card pointer; address of job card field following job-name
12-13	ACCTPART	ID of partition in charge (partitions switch name)
14-15	ACCTLEN	Length of SIO area = 6n+1, where n = number of devices for this partition in SYSGEN option JA = (n, n, . . .)
16-21	ACCTLOAD	Label area instruction; moves JAI label area address to OPEN/CLOSE transients
22-23	ACCTRES3	Reserved
24-27	ACCTLADD	Address of alternate label area
28-31	ACCTCPUT	Counter for program execution time (processor time) in the current jobstep. Counted in 300th of a second.
32-35	ACCTOVHT	Counter for system execution time (overhead time) in the current job step, distributed in proportion of the processor time.
36-39	ACCTBNDT	Counter for all-bound time; system wait state time divided between running partitions.
40-47	ACCTSVJN	Save area for job name during simulated EOJ
48-55	ACCTJBNM	Job name; taken from job card
56-71	ACCTUSRS	User information; 16 bytes form job card
72-73	ACCTPTID	Partition ID: 'BG', 'F1', 'F2', etc. in EBCDIC format
74	ACCTCNCL	Cancel code; see Cancel Codes and Messages
75	ACCTYPER	Type of record 'S' = job step, 'L' = last step of job
76-83	ACCTDATE	Date in format specified at SYSGEN (MM/DD/YY or DD/MM/YY)
84-87	ACCTSTRT	Start time of a job-step, in packed decimal (DHHMSSF; F = sign)
88-91	ACCTSTOP	Stop time of a job step in the same format as ACCTSTRT. This value is used as the start time for the next step.
92-95	ACCTRES	Reserved
96-103	ACCTEXEC	Phase name; taken from execute card
104-107	ACCTHICR	2K * number of partition pages referenced (or PFIxed for real execution) by the problem program in the current job step. If the system supports the VSE/Advanced Functions linkage enhancement (VM=YES), this area contains the highest virtual storage address allocated for this partition.
108-111	ACCTIMES	Same as ACCTOPUT at the end of the job step.
112-115		Same as ACCTOVHT at the end of job step.
116-119		Same as ACCTBNDT at the end of job step.
120	ACCTSIOS	SIO tables: 6 bytes for each device specified by SYSGEN options, as follows: 2 bytes for device address (Ocuu), 4 bytes for count of SIOS in current jobstep. Overflow byte: normally X'20', but is X'30' if more devices are used within a partition that specified by SYSGEN options.

Notes:

DSECT ACCTABLE symbolically addresses the JAI Partition Tables with labels, as shown. Each partition in which JAI is supported has its own JAI Partition Table. This table is labeled ACCTBG for the active partition BG; ACCTF1 for the active partition F1; ACCTF2 for F2, etc.

The address of this table is in the partition Communication Region at displacement 116 (X'74').

ASCII EBCDIC TRANSLATION TABLES

ASCII/EBCDIC (0/0 to 3/2)

Charact.	ASCII			EBCDIC				Comments	
	Col	Row	Bit Pattern	Col	Row	Bit Pattern			
				(in hex)					
NUL	0	0	0000	0000	0	0	0000	0000	
SOH	0	1	0000	0001	0	1	0000	0001	
STX	0	2	0000	0010	0	2	0000	0010	
ETX	0	3	0000	0011	0	3	0000	0011	
EOT	0	4	0000	0100	3	7	0011	0111	
ENQ	0	5	0000	0101	2	D	0010	1101	
ACK	0	6	0000	0110	2	E	0010	1110	
BEL	0	7	0000	0111	2	F	0010	1111	
BS	0	8	0000	1000	1	6	0001	0110	
HT	0	9	0000	1001	0	5	0000	0101	
LF	0	10	0000	1010	2	5	0010	0101	
VT	0	11	0000	1011	0	B	0000	1011	
FF	0	12	0000	1100	0	C	0000	1100	
CR	0	13	0000	1101	0	D	0000	1101	
SO	0	14	0000	1110	0	E	0000	1110	
SI	0	15	0000	1111	0	F	0000	1111	
DLE	1	0	0001	0000	1	0	0001	0000	
DC1	1	1	0001	0001	1	1	0001	0001	
DC2	1	2	0001	0010	1	2	0001	0010	
DC3	1	3	0001	0011	1	3	0001	0011	
DC4	1	4	0001	0100	3	C	0011	1100	
NAK	1	5	0001	0101	3	D	0011	1101	
SYN	1	6	0001	0110	3	2	0011	0010	
ETB	1	7	0001	0111	2	6	0010	0110	
CAN	1	8	0001	1000	1	8	0001	1000	
EM	1	9	0001	1001	1	9	0001	1001	
SUB	1	10	0001	1010	3	F	0011	1111	
ESC	1	11	0001	1011	2	7	0010	0111	
FS	1	12	0001	1100	1	C	0001	1100	
GS	1	13	0001	1101	1	D	0001	1101	
RS	1	14	0001	1110	1	E	0001	1110	
US	1	15	0001	1111	1	F	0001	1111	
SP	2	0	0010	0000	4	0	0100	0000	
!	2	1	0010	0001	4	F	0100	1111	Logical OR
"	2	2	0010	0010	7	F	0111	1111	
#	2	3	0010	0011	7	B	0111	1011	
\$	2	4	0010	0100	5	B	0101	1011	
%	2	5	0010	0101	6	C	0110	1100	
&	2	6	0010	0110	5	0	0101	0000	
'	2	7	0010	0111	7	D	0111	1101	
(2	8	0010	1000	4	D	0100	1101	
)	2	9	0010	1001	5	D	0101	1101	
*	2	10	0010	1010	5	C	0101	1100	
+	2	11	0010	1011	4	E	0100	1110	
,	2	12	0010	1100	6	B	0110	1011	
-	2	13	0010	1101	6	0	0110	0000	Hyphen, Minus
.	2	14	0010	1110	4	B	0100	1011	
/	2	15	0010	1111	6	1	0110	0001	
0	3	0	0011	0000	F	0	1111	0000	
1	3	1	0011	0001	F	1	1111	0001	
2	3	2	0011	0010	F	2	1111	0010	

ASCII EBCDIC TRANSLATION TABLES (. . . Cont'd)

ASCII/EBCDIC (3/3 to 6/6)

ASCII				EBCDIC				Comments
Charact.	Col	Row	Bit Pattern	Col (in hex)	Row	Bit Pattern		
3	3	3	0011	F	3	1111	0011	
4	3	4	0011	F	4	1111	0100	
5	3	5	0011	F	5	1111	0101	
6	3	6	0011	F	6	1111	0110	
7	3	7	0011	F	7	1111	0111	
8	3	8	0011	F	8	1111	1000	
9	3	9	0011	F	9	1111	1001	
:	3	10	0011	7	A	0111	1010	
;	3	11	0011	5	E	0101	1110	
<	3	12	0011	4	C	0100	1100	
=	3	13	0011	7	E	0111	1110	
>	3	14	0011	6	E	0110	1110	
?	3	15	0011	6	F	0110	1111	
@	4	0	0100	7	C	0111	1100	
A	4	1	0100	C	1	1100	0001	
B	4	2	0100	C	2	1100	0010	
C	4	3	0100	C	3	1100	0011	
D	4	4	0100	C	4	1100	0100	
E	4	5	0100	C	5	1100	0101	
F	4	6	0100	C	6	1100	0110	
G	4	7	0100	C	7	1100	0111	
H	4	8	0100	C	8	1100	1000	
I	4	9	0100	C	9	1100	1001	
J	4	10	0100	D	1	1101	0001	
K	4	11	0100	D	2	1101	0010	
L	4	12	0100	D	3	1101	0011	
M	4	12	0100	D	4	1101	0100	
N	4	14	0100	D	5	1101	0101	
O	4	15	0100	D	6	1101	0110	
P	5	0	0101	D	7	1101	0111	
Q	5	1	0101	D	8	1101	1000	
R	5	2	0101	D	9	1101	1001	
S	5	3	0101	E	2	1110	0010	
T	5	4	0101	E	3	1110	0011	
U	5	5	0101	E	4	1110	0100	
V	5	6	0101	E	5	1110	0101	
W	5	7	0101	E	6	1110	0110	
X	5	8	0101	E	7	1110	0111	
Y	5	9	0101	E	8	1110	1000	
Z	5	10	0101	E	9	1110	1001	
[5	11	0101	4	A	0100	1010	
\	5	12	0101	E	0	1110	0000	Reverse Slant
]	5	13	0101	5	A	0101	1010	
_	5	14	0101	5	F	0101	1111	Logical Not
-	5	15	0101	6	D	0110	1101	Underscore
·	6	0	0110	7	9	0111	1001	Grave accent
a	6	1	0110	8	1	1000	0001	
b	6	2	0110	8	2	1000	0010	
c	6	3	0110	8	3	1000	0011	
d	6	4	0110	8	4	1000	0100	
e	6	5	0110	8	5	1000	0101	
f	6	6	0110	8	6	1000	0110	

ASCII EBCDIC TRANSLATION TABLES (. . . Cont'd)

ASCII EBCDIC (6/7 to 7/15)

ASCII				EBCDIC				Comments
Charact.	Col	Row	Bit Pattern	Col	Row	Bit Pattern		
g	6	7	0110 0111	8	7	1000 0111		
h	6	8	0110 1000	8	8	1000 1000		
i	6	9	0110 1001	8	9	1000 1001		
j	6	10	0110 1010	9	1	1001 0001		
k	6	11	0110 1011	9	2	1001 0010		
l	6	12	0110 1100	9	3	1001 0011		
m	6	13	0110 1101	9	4	1001 0100		
n	6	14	0110 1110	9	5	1001 0101		
o	6	15	0110 1111	9	6	1001 0110		
p	7	0	0111 0000	9	7	1001 0111		
q	7	1	0111 0001	9	8	1001 1000		
r	7	2	0111 0010	9	9	1001 1001		
s	7	3	0111 0011	A	2	1010 0010		
t	7	4	0111 0100	A	3	1010 0011		
u	7	5	0111 0101	A	4	1010 0100		
v	7	6	0111 0110	A	5	1010 0101		
w	7	7	0111 0111	A	6	1010 0110		
x	7	8	0111 1000	A	7	1010 0111		
y	7	9	0111 1001	A	8	1010 1000		
z	7	10	0111 1010	A	9	1010 1001		
{	7	11	0111 1011	C	0	1100 0000		
}	7	12	0111 1100	6	A	0110 1010	Vertical Line	
~	7	13	0111 1101	D	0	1101 0000		
DEL	7	14	0111 1110	A	1	1010 0001	Tilde	
DEL	7	15	0111 1111	0	7	0000 0111		

EBCDIC				ASCII				Comments
Charact.	Col	Row	Bit Pattern	Col	Row	Bit Pattern		
NUL	0	0	0000 0000	0	0	0000 0000		
SOH	0	1	0000 0001	0	1	0000 0001		
STX	0	2	0000 0010	0	2	0000 0010		
ETX	0	3	0000 0011	0	3	0000 0010		
HT	0	5	0000 0101	0	9	0000 1001		
DEL	0	7	0000 0111	0	15	0111 1111		
VT	0	B	0000 1011	0	11	0000 1011		
FF	0	C	0000 1100	0	12	0000 1100		
CR	0	D	0000 1101	0	13	0000 1101		
SO	0	E	0000 1110	0	14	0000 1110		
SI	0	F	0000 1111	0	15	0000 1111		
DLE	1	0	0001 0000	1	0	0001 0000		
DC1	1	1	0001 0001	1	1	0001 0001		
DC2	1	2	0001 0010	1	2	0001 0010		
DC3	1	3	0001 0011	1	3	0001 0011		
BS	1	6	0001 0110	0	8	0000 1000		
CAN	1	8	0001 1000	1	8	0001 1000		
EM	1	9	0001 1001	1	9	0001 1000		
FS	1	C	0001 1100	1	12	0001 1100		
GS	1	D	0001 1101	1	13	0001 1101		
RS	1	E	0001 1110	1	14	0001 1110		
US	1	F	0001 1111	1	15	0001 1111		

EBCDIC to ASCII (X'00' to '1F')

ASCII EBCDIC TRANSLATION TABLES (. . . Cont'd)

EBCDIC to ASCII (X'25' to X'93')


Charact.	EBCDIC			ASCII			Comments		
	Col	Row	Bit Pattern	Col	Row	Bit Pattern			
LF	2	5	0010	0	10	0000	1010		
ETB	2	6	0010	1	7	0001	0111		
ESC	2	7	0010	1	11	0001	1011		
ENQ	2	D	0010	1	101	0	5	0000	0101
ACK	2	E	0010	1	110	0	6	0000	0110
BEL	2	F	0010	1	111	0	7	0000	0111
SYN	3	2	0011	0	010	1	6	0001	0110
EOT	3	7	0011	0	011	0	4	0000	0100
EC4	3	C	0011	1	100	1	4	0001	0100
NAK	3	D	0011	1	101	1	5	0001	0101
SUB	3	F	0011	1	111	1	10	0001	1010
SP	4	0	0100	0	000	2	0	0010	0000
[4	A	0100	0	101	5	11	0101	1011
.	4	B	0100	0	101	2	14	0010	1110
<	4	C	0100	1	100	3	12	0011	1100
(4	D	0100	1	101	2	8	0010	1000
+	4	E	0100	1	110	2	11	0010	1011
!	4	F	0100	1	111	2	1	0010	0001
&	5	0	0101	0	000	2	6	0010	0110
]	5	A	0101	0	101	5	13	0101	1101
^	5	B	0101	0	101	2	4	0010	0100
*	5	C	0101	0	110	2	10	0010	1010
)	5	D	0101	0	110	2	9	0010	1001
;	5	E	0101	0	111	3	11	0011	1011
_	5	F	0101	0	111	5	14	0101	1110
-	6	0	0110	0	000	2	13	0010	1101
/	6	1	0110	0	001	2	15	0010	1111
	6	A	0110	0	101	7	12	0111	1100
,	6	B	0110	0	101	2	12	0010	1100
%	6	C	0110	0	110	2	5	0010	0101
—	6	D	0110	0	110	5	15	0101	1111
∏	6	E	0110	0	111	3	14	0011	1110
?	6	F	0110	0	111	3	15	0011	1111
ˆ	7	9	0111	0	001	6	0	0110	0000
:	7	A	0111	0	101	3	10	0011	1010
#	7	B	0111	0	101	2	3	0010	0011
@	7	C	0111	0	110	4	0	0100	0000
'	7	D	0111	0	110	2	7	0010	0111
=	7	E	0111	0	111	3	13	0011	1101
”	7	F	0111	0	111	2	2	0010	0010
a	8	1	1000	0	001	6	1	0110	0001
b	8	2	1000	0	010	6	2	0110	0010
c	8	3	1000	0	011	6	3	0110	0011
d	8	4	1000	0	100	6	4	0110	0100
e	8	5	1000	0	101	6	5	0110	0101
f	8	6	1000	0	110	6	6	0110	0110
g	8	7	1000	0	111	6	7	0110	0111
h	8	8	1000	0	100	6	8	0110	1000
i	8	9	1000	0	101	6	9	0110	1001
j	9	1	1001	0	001	6	10	0110	1010
k	9	2	1001	0	010	6	11	0110	1011
l	9	3	1001	0	011	6	12	0110	1100

ASCII EBCDIC TRANSLATION TABLES (. . . Cont'd)

EBCDIC to ASCII (X'94' to X'F9')

Charact.	EBCDIC		ASCII				Comments		
	Col	Row (in hex)	Bit Pattern	Col	Row	Bit Pattern			
m	9	4	1001	0110	6	13	0110	1101	
n	9	5	1001	0101	6	14	0110	1110	
o	9	6	1001	0110	6	15	0110	1111	
p	9	7	1001	0111	7	0	0111	0000	
q	9	8	1001	1000	7	1	0111	0001	
r	9	9	1001	1001	7	2	0111	0010	
~	A	1	1010	0001	7	14	0111	1110	Tilde
s	A	2	1010	0010	7	3	0111	0011	
t	A	3	1010	0011	7	4	0111	0100	
u	A	4	1010	0100	7	5	0111	0101	
v	A	5	1010	0101	7	6	0111	0110	
w	A	6	1010	0110	7	7	0111	0111	
x	A	7	1010	0111	7	8	0111	1000	
y	A	8	1010	1000	7	9	0111	1001	
z	A	9	1010	1001	7	10	0111	1010	
{	C	0	1100	0000	7	11	0111	1011	
A	C	1	1100	0001	4	1	0100	0001	
B	C	2	1100	0010	4	2	0100	0010	
C	C	3	1100	0011	4	3	0100	0011	
D	C	4	1100	0100	4	4	0100	0100	
E	C	5	1100	0101	4	5	0100	0101	
F	C	6	1100	0110	4	6	0100	0110	
G	C	7	110	0111	4	7	0100	0111	
H	C	8	1100	1000	4	8	0100	1000	
I	C	9	1100	1001	4	9	0100	1001	
]	D	0	1101	0000	7	13	0111	1101	
J	D	1	1101	0001	4	10	0100	1010	
K	D	2	1101	0010	4	11	0100	1011	
L	D	3	1101	0011	4	12	0100	1100	
M	D	4	1101	0100	4	13	0100	1101	
N	D	5	1101	0101	4	14	0100	1110	
O	D	6	1101	0110	4	15	0100	1111	
P	D	7	1101	0111	5	0	0101	0000	
Q	D	8	1101	1000	5	1	0101	0001	
R	D	9	1101	1001	5	2	0101	0010	
\	E	0	1110	0000	5	12	0101	1100	Reverse Slant
S	E	2	1110	0010	5	3	0101	0011	
T	E	3	1110	0011	5	4	0101	0100	
U	E	4	1110	0100	5	5	0101	0101	
V	E	5	1110	0101	5	6	0101	0110	
W	E	6	1110	0110	5	7	0101	0111	
X	E	7	1110	0111	5	8	0101	1000	
Y	E	8	1110	1000	5	9	0101	1001	
Z	E	9	1110	1001	5	10	0101	1010	
0	F	0	1111	0000	3	0	0011	0000	
1	F	1	1111	0001	3	1	0011	0001	
2	F	2	1111	0010	3	2	0011	0010	
3	F	3	1111	0011	3	3	0011	0011	
4	F	4	1111	0100	3	4	0011	0100	
5	F	5	1111	0101	3	5	0011	0101	
6	F	6	1111	0110	3	6	0011	0110	
7	F	7	1111	0111	3	7	0011	0111	
8	F	8	1111	1000	3	8	0011	1000	
9	F	9	1111	1001	3	9	0011	1001	

SEGMENT AND PAGE TABLE



Bytes 0 and 1

- Bit 0 1 = Address of any byte in the corresponding page is invalid
- Bits 0–12 Leftmost 13 bits of address of page in real storage if bit 13 = 0
- Bits 8–11 Storage key of corresponding partition if bit 13 = 1
- Bit 13 0 = Page is in real storage
 1 = Page is not in real storage
- Bit 14 Always zero
- Bit 15 PDS (Page Data Set) bit:
 1 = Page must be read from page data set
 (a valid copy of the page is on the page data set)
 0 = Page need not be read from page data set
 (no valid copy of the page on the page data set)

Bytes 208–211 (X'D0'–X'D3') of the System Communication Region (SYSCOM) contain the address of the Segment Table.

PAGE DATA SET TABLE

Page management uses the Page Data Set Table (DPDTAB) to calculate the correct address for a given page on the Page Data Set, if a read or write operation is necessary. Bytes 224–227 (X'E0–X'E3') of the System Communication Region (SYSCOM) contain the address of the DPDTAB. The DPDTAB consists of a header and 15 extent definitions. Label DPDTAB identifies the first byte of the table. The table has the following layout:

Header

Bytes:

0–1	Number of extents specified in IOTAB
2–3	Number of extents specified by DPD commands
4–5	Number of virtual pages supported
6–7	Length of DPDTAB entry
8–11	Address of constant table for load leveler
12–13	If /370 mode: Relocation value for Supervisor pages
	If ECPS:VSE mode: Reserved
14–15	If /370 mode: Relocation value for Non-Supervisor pages
	If ECPS:VSE mode: Reserved

Extent definitions:

Bytes:

0–1	Channel and unit number of Page Data Set device
2	Indicates FBA (1), CKD (2), or RPS (3) device
3	Device type code
4–5	If FBA device: Block length
	If CKD device: Number of records per track
6–7	If FBA device: Number of blocks per page
	If CKD device: Number of tracks per cylinder
8–11	If FBA device: Block number of lower limit
	If CKD device: Relative track number of lower extent limit
12–15	If FBA device: Number of blocks used for the extent
	If CKD device: Number of tracks used for the extent
16–17	PUB index
18–23	Volume ID of Page Data Set
24–25	Page number of upper limit on the extent
26–27	Not used (for alignment only)

TASK TIMER TABLE (TTTAB)

0 3 4 7 8 15

Exit Routine Address	Save Area Address	Task Timer Interval
----------------------	-------------------	---------------------

Bytes 0–3 No STXIT issued: zero
 STXIT issued: Address of entry point of user's task timer routine
 STXIT issued and user's routine already in use: Complement of the task timer routine address

Bytes 4–7 No STXIT issued: zero
 STXIT issued: Address of the user's save area

Bytes 8–15 No SETT issued: zero or negative
 SETT issued: Time remaining of the interval specified. The time is expressed in micro-seconds in bits 0–51. Bits 52–63 are ignored.

Note: Bytes 176–179 (X'B0'–X'B3') of the System Communications Region (SYSCOM) contain the address of Task Timer Table. Label TTTAB identifies the first byte of the table.

INTERVAL TIMER REQUEST ENTRY IN TCB

0 5 6 7

Sign. Part of Clock Comparator Value (=end of time interval)	Note
--	------

Note: Displacement to TIB address of next task in chain.

The entries in the TIB ITREQ are either active or inactive. An active entry contains in bytes 0–5 the clock comparator value (=end of interval) and in bytes 6–7 the displacement to the TIB address table entry of the next task in chain. The lowest value occupies the first position of the table, the highest value the position before the inactive entries.

All bits of an inactive entry are set to one (binary format). The last entry is always inactive and all entries are set inactive after IPL.

The clock comparator is set to the value contained in the first entry of the chain.

PAGE-OUT QUEUE ENTRY (PGQU0)

0 1 3

Flag Byte	Address of PFTE	
-----------	-----------------	--

Page-out Queue (PGQU0) Entry

Bytes:

0 Flag Byte
 Bit 0 = 1 Posting required
 Bits 1–7 Reserved

1–3 Address of PFTE to be handled

The page-out queue consists of 9 four-byte entries, and the label PGQU0 identifies the first byte of the table.

PAGE FRAME TABLE ENTRY (PFTE)

0	1	3	4	5	6	8	12	15
PFTE Flag	Page Number (PNR)	370 Mode Flag	Waiting Task ID (WID)	PFIX Counter	TFIX Counter	Forward Pointer	Backward Pointer	

Initialize at IPL time:


Byte 0–3	Page frame address
370 mode only Byte 3	Bit 4 = 0 If page frame belongs to supervisor or IPL partition Bit 4 = 1 If page frame belongs to initial page pool
Byte 4–7	Zero

Meaning of Bytes of PFTE:

Byte 0 (PFTE Flag)	Bit 0 (Hold bit) 1 = Ensures that each task causing a page fault can use the page before it is disconnected again. Bit 1 (POE bit) 1 = Indicates that the PFTE has an entry in PGQUO Bit 2 (PO bit) 1 = Indicates that an active entry from the PMR task is in PGQUO. Bit 3 (POA bit) 1 = Indicates that I/O for a page out has been started for this PFTE. Bits 4–7 Reserved
Byte 1 + 2	If the page belongs to the page frame, byte 1 and 2 contains the leftmost 16 bits of the 3 byte address.
Byte 3 (370 mode flag byte)	Bit 0 (NFRP bit) 1 = Page in this page frame must not be TFIXed, since the page frame is in the PSQ. Bit 1 (NFVP bit) 1 = Page belonging to this page frame is requested by PFIX. The page frame is not in the PSQ. Bit 2 (DRAP bit) 1 = Indicates that the address space belonging to the PFTE is failing storage. Bit 3 (PC bit) 1 = Indicates that a page is connected to the page frame. Either a page-in or an unconditional page-out request is in progress. Bit 4 (PNRINV bit) 1 = Page frame is unused. It indicates that the PNR field, the FIX counters, the WID field, the PFTE flag, and the 370 Mode flag (except for the NFRP, DRAP, and RPRESFP bits) are invalid. Bit 5–7 Reserved
Byte 4 (370 mode only) Byte 5 (PFIXC) Byte 6 + 7 (TFIXC) Byte 8–11 (PFTEFPTR) Byte 12–15 (PFTEBPTR)	Contains the PIK of the task requesting PFIX. The page frame of the page to be PFIXed does not belong to the corresponding real partition. Indicates how often the page is permanently fixed. Indicates how often the page is temporarily fixed. Pointer to the next PFTE. Pointer to the preceding PFTE.

Note: The pointers in bytes 7 through 15 are only valid if the PFTE is in the PSQ, or, for 370 mode, in the unused page frame queue.

PAGETAB



Byte 0	TIK (identifier of tasks that issued the PAGEIN macro).
Bytes 1–3	Pointer to a list of areas that are to be paged in.
Byte 4	bit 0 1 = PAGEIN request has been completed bit 1 Reserved bit 2 1 = One more of the requested pages are outside the requesting program's partition. bit 3 1 = One or more negative length specifications were detected. bit 4 Reserved bit 5 Paging activity too high. Terminator required by load level. bit 6 Task is terminating, request has to be deleted. bit 7 Second scan in progress.
Byte 5–7	Pointer to ECB (if used) or zero.

Note:

The number of entries is determined at supervisor generation time. Label PAGETAB identifies the first byte of the table.

TRANSLATION CONTROL BLOCK (CCWTCB)

0	1	2	3 4	7 8	11 12	15 16	19
Flag byte	used by BTAM	TIK/PIK	Pointer to Status Modifier List	Pointer to Control Command List	Pointer to TIC Line	Pointer to Copy Block End	
20	23 24	27 28	47 48	51 52	55 56	59	60
Address of copied CCB (for cancel)	Number of free IDA words in IDAL blocks	Work areas	Address of last TFIX request	Pointer to DIDAL chain	Address of current DIDAL	Fast Translation Flag Byte	
61	62	63 64	67 68	71 72	127 128	131	
Reserved	Number of free DIDAL entries	Address of current DIDAL entry	Virtual CCW address	Save Area (Registers 2-F)	Pointer to next used TCB		

- Byte 0 (TCBFLAG):**
 = 1: Data chaining specified
 = 1: Read/Sense command specified
 = 1: Read backward command specified
 = 1: Status modifier command with data chaining
 = 1: Status modifier command with command chaining
 = 1: Request for FIX information block
 6,7: Reserved
- Byte 1 (ADBTAMCB):**
 Number of copy blocks needed in addition to those required for current CCW-translation request (refer to the section "BTAM Considerations").
- Byte 4 (DEVSTPTR):**
 Pointer to status modifier list belonging to handled device. Zero if device does not support status modifier commands.
- Byte 8 (DEVCDPTR):**
 Pointer to control command list which belongs to handled device. Zero if device does not support control commands with data area.
- Byte 12 (LINEPTR):**
 Chain of knots of free structure caused by TIC following status modifier command. (Refer to the section "Translating Status Modifier Commands".) Zero if no knots exist in the CCW chain.
- Byte 16 (BENDPTR):**
 Chain of knots built because status modifier command is last one fitting in CCW copy block. Zero if no status modifier commands at end of CCW copy blocks.
- Byte 60 (TCBFLAG1):**
 Bit 0 = 1 Replica creation requested
 Bit 1 = 1 Replica test in process
 Bit 2 = 1 Request for replica block
 Bit 3 = 1 Request for DIDAL block
 Bit 4-7 Reserved


Bytes 52-71 as shown are for fast CCW translation only. For a normal translation byte 52 is the first byte of the save area.

The CCWTCB is located in the work area of the task control block (TCB) of the requesting task.

TRANSLATION CONTROL AND COPY BLOCKS

The following control and copy blocks are used to copy and translate a CCB and channel program for a virtual mode I/O request:

- A translation control block (CCWTCB, or abbreviated as TCB). This block is used as a work and save area during translation.
- A CCB copy block. The user CCB and sense CCW (if any) are copied into this block. The CCB copy block also contains information about the copied and translated channel program.
- CCW copy blocks. Each block contains copy locations for up to 7 contiguous CCWs and queuing information.
- IDAL blocks. Blocks used for building Indirect Data Address Lists for CCWs having IDALs or for data areas which cross page boundaries.
- Fix information blocks. Each block contains a bit string for fix information for a block of 1088K of real storage. One or more fix informations blocks are generated if a page is fixed at a location greater than 384K (information for page frames up to that address is kept in the CCB copy block).



COPY BLOCKS (. . . Cont'd)

Layout of CCB Copy Block

	0	1	2	3	4	5	6	7	Copied CCB
0	CCBCNT		CCB COM1	CCB COM2	CCB STA1	CCB STA2	CCB CLS *	CCB LNO	
8	CCBCCW Address of first CCW				CCBBY3	CCBCSWW			
16	CCBSENS Sense CCW if any								
24	CCBPIK User PIK		CCB FLAG **	Unused	CCBVA Virtual Address of CCB				
32	CCBACB Address of first CCW copy block in channel program with lowest VBA				CCBICB Address of first IDAL block in channel program				
40	CCBXINF (Fix information; 24 bytes)								
48	Each bit in this field represents one page frame. If a bit is on, the associated page frame contains a page fixed for this I/O request. If more than 384K of real storage are available, the address in CCBXPTR will point to any additional field which contains bits for the page frames beyond 384K.								
56									
64	CCBXPTR Address of additional Fix information				CCBNEXT Address of next CCB copy block				

Note:

If the fast CCW translation option is active, bytes 56–67 of the CCB copy block have a different meaning, as shown below:

Bytes 56–59 The address of the REPLIC block associated with this channel program.

Bytes 60–63 Pointer to the next CCB in the saved CCB queue used by the fast CCW translation routines.

Bytes 64–67 Pointer to the previous CCB in the saved CCB queue.

* Set to X'20' (= copied CCB)

** Legend CCBFLAG:

- Bit 0 Indicates that CCW-translation of this request is complete; indicator is set before I/O request is enqueued in channel queue.
- Bit 1 Indicates that at least one time during CCW-translation control has been transferred to TFIX routine. In case TTFIX is 0 scan through CCBXINF for freeing pages is skipped. Indicator is set immediately before control is transferred to TFIX routine.
- Bit 2 Reserved
- Bit 3 Indicates that the next CCW-translation request from BTAM is from the BTAM channel appendage. This indicator is set immediately after 1st time request from BTAM has been completed.
- Bit 4 Valid for fast translation.
- Bit 5 CCB copy block is on saved CCB queue.
- Bit 6 Data area pages require fixing.
- Bit 7 Reserved

COPY BLOCKS (. . . Cont'd)

Layout of CCW Copy Block

	0	1	2	3	4	5	6	7
0	1st Copy location for CCW							
8	2nd Copy location for CCW							
16	3rd Copy location for CCW							
24	4th Copy location for CCW							
32	5th Copy location for CCW							
40	6th Copy location for CCW							
48	7th Copy location for CCW							
56	X'80' *	X'000000'			Virtual address of first CCW in the Copy block			
64	X'88' **	X'000000'			Address of next CCW Copy block in the chain			

* X'80' indicates the end of the CCW copy locations in the block. It is replaced by a TIC (Transfer in Channel command) if the 7th copy location contains a copied CCW with data- or command chaining. Bytes 57–59 will then point to the copy location of the CCW following in the CCW in the 7th location. Bytes 56–59 will not be changed if the CCW in the 7th copy location is a TIC.

** X'88', indicates the last 8-byte entry in the block. It is replaced by a TIC if the CCW in the 7th copy location is a status modifier CCW. Bytes 65–67 will then point to the copy location of the second CCW following the status modifier CCW.

COPY BLOCKS (. . . Cont'd)

MAIN REPLICA BLOCK

0	4
VCCBA	RCCBA
TIMEST	REPIIK REPLCNT CCWSTRL
REPDIDAL	
	CCB
	CCW1
CCW1	CCW2
CCW2	CCW3
CCW3	REPFPT
REPBPT	REPNEXT

ADDITIONAL REPLICA BLOCK

	CCW4
	CCW5
	⋮
	•
	REPNEXT

Legend:

- VCCBA Virtual CCB address
- RCCBA Address of copied CCB
- TIMEST Timestamp
- REPIIK Partition Identification Key
- REPLCNT The number of tasks currently testing this REPLICA for a match with their channel program
- CCWSTRL Length of CCW string (number of CCWs)
- REPDIDAL Address of DIDAL block
- REPFPT, REPBPT Pointers used for chaining REPLICAs (forward and backward pointer)
- REPNEXT Pointer to (next) additional REPLICA block

DIDAL BLOCK


ENTRY	1
	2
	3
	4
	5
	6
	7
	8
RESERVED	CHAIN POINTER***

DIDAL ENTRY

VIRTUAL ADDRESS	FLAG BYTE*	POINTER TO REAL LOC.**
0	3 4 5	7





- * FLAGBYTE
 - Bit 0 Indicates that TFIXing is not necessary because the page has already been TFIXed for this request.
 - Bit 1–6 Reserved
 - Bit 7 Indicates that TFIX request for this entry has been completed.
- ** Real location (either copied CCW or IDA word) that should contain the translated I/O area address.
- *** Points to (next) additional DIDAL. Contains 4X'00' in last DIDAL.

CONVERTING VIRTUAL TO REAL ADDRESS



Note:
Values used in the figure are hypothetical.

PAGE DATA SET FORMAT



Virtual Disk Format 3310 and 3370 (FBA Mode)

In Fixed Block Mode the 3310 and 3370 DASD will provide logical block number in ascending sequence. That means 4 blocks with 512 bytes are required to store one page on the PAGE DATA SET.

LAYOUT OF REPLICA HEADER BLOCKS

RHB1

X'00'	Flag Byte *	Number of Tests on Replica	PIK of Requestor
X'04'	Forward pointer in partiton's replica queue		
X'08'	Backward pointer in partiton's replica queue		
X'0C'	Address of virtual CCB/IORB		
X'10'	Saved CCB/IORB		
X'20'	Pointer to RHB2		

RHB2


X'00'	Pointer to RHB1		
X'04'	Pointer to associated FHB (fixlist)		
X'08'	Time stamp		
X'0C'	Length of saved channel program		
X'10'	Reserved		
X'14'	Reserved		
X'18'	Saved user SENSE		
X'20'	Pointer to next replica block		

REPLICA BLOCK

X'00'	CCW1
X'08'	CCW2
X'10'	CCW3
X'18'	CCW4
X'20'	Pointer to next block or zero

- * Flag Byte:
 Bit 0 = 1 Freeing of replica request
 Bit 1-7 Reserved

LAYOUT OF SHARED VIRTUAL AREA (SVA)



Field	Length	Contents
VLT	8	Date plus time SVA has been updated
VDSA	4	Start address of the System Directory List
VLSA	4	Start address of the virtual library ¹
VLNA	4	Address of next available location in SVA
VLEA	4	Address of end of the SVA
	4	Pointer to next free SDL entry
	2	Number of SDL entries
TB	16	STOWTABLE (Communication area between Job Control and \$MAINDIR/\$MAINDIF)
VD	any	System Directory List ²
AL	<8	Alignment bytes for doubleword boundary
VL	any	Virtual library containing reenterable and relocatable phases
GV	any	GETVIS area for the system (starts on page boundary)

Note 1:
Address of first doubleword aligned byte after SDL.

Note 2:
The layout of this area is compatible with a directory block in the Core Image Library. The SDL has fixed length entries of 34 bytes. The last entry contains 8X'FF' as phasename.

LAYOUT OF DIRECTORY ENTRY

0	8	11	12	14	16	17	18	21	24	26	27	30	34
Phase name	TTR	N	TT	LL	C	T	PPP	EEE	RR	R	AAA	VEE	LIB
	LB LN												

Bytes 0–7	Phase name	
Bytes 8–10	TTR	Relative disk address of phase (note 2)
Byte 11	N	Number of halfwords containing user data
Bytes 8–11	LB LN	Logical block number of phase on FBA device
Bytes 12–13	TT	Number of text blocks
Bytes 14–15	LL	Number of text bytes in last text block
Byte 16	C	Switch indicating type of phase X'80' selfrelocating phase X'40' relocatable phase X'20' SVA eligible X'10' phase is in the SVA (Note 1) X'08' phase found in a PICL (Note 1) X'04' phase not found or deleted directory entry (Note 1) X'02' active entry (filled in) (Note 1) X'01' not used
Byte 17	T	Always X'00' (used as type byte for stow table)
Bytes 18–20	PPP	Load point at LNKEDT time (Note 3)
Bytes 21–23	EEE	Entry point at LNKEDT time (Note 3)
Bytes 24–25	RR	Number of RLD items (Note 4)
Byte 26	R	Number of additional RLD blocks (Note 4)
Bytes 27–29	AAA	Partition start address at LNKEDT time (Note 4)
Bytes 30–33	VEE	Entry point of phase in SVA (Notes 1 and 5)
Bytes 34–37	LIB	Pointer to FTTAB which the directory entry belongs to (Note 1)

Note 1: Only used for directory entries that are in storage.

Note 2: The TTR is relative to the beginning of the directory.

Note 3: PPP and EEE are not present if both are zero and the phase is not relocatable.

Note 4: RR, R and AAA are only present if the phase is relocatable.

Note 5: VEE is only present if the phase is SVA eligible.

Note:

The last entry in the directory is a 12-byte with a dummy phasename (contains 8X'FF'), a dummy TTR (contains XL3'00') and a dummy N (contains X'00'). Directory entries in storage always have the standard length of 34 bytes (including the last entry).

ROUTINE IDENTIFIERS (RID)

NAME	ID	MEANING	ACTION
SYSTEMID	00	System error condition, for example, page fault in I/O interrupt handler.	Hard Wait.
REENTRID	04	Page fault or GETREAL request in a reenterable routine.	Save PSW and registers to user task's system save area.
USERID	08	Page fault from a user task or system task.	If TCB shows that the system task must not be interrupted by P.F., the system enters hardwait FFB. Registers and interrupt status are saved in the user save area. If the task was working in disabled mode, the user is canceled with code X'15'. Otherwise the page fault request is enqueued.
APPENDID	0C	Page fault in I/O appendage routine.	Cancel user task with error code X'36'.
RESVCID	10	Page fault in SVC 7 or 29.	Set on the RETRY SVC bit in TIB and save interrupt status and registers in user save area and ENQU page fault request.
DISPID	14	Page fault in a routine which requires no information to be saved for example a page fault in the dispatcher.	ENQU page fault request.
PFARID	18	Page fault in a page fault appendage routine.	Save interrupt status and registers in special supervisor save area.
ETSSID SUBSYSID	1C	Page fault in subsystem (e.g. ICCF).	Save interrupt status and registers in special supervisor save area.
MICRID	20	Page fault in MICR, SS appendage.	Save interrupt status and registers in special supervisor save area and cancel user task with error code X'0E'.
	40 through FF	Page fault in a gated supervisor service.	Close gate to routine (routine cannot be used until gate is opened). Save PSW and registers to user task's system save area set TIBFLAG to call SVRETURN. ENQU page request. (Any task trying to use a gated resource is placed in a wait state and marked resource bound. It is released from the wait state when the resource is un gated after the page request has been handled.)


VTAM ADDRESS VECTOR TABLE (ISTAVT)

Label	Length	Description
ISTACVT	4	ADDR OF VTAM CVT
ISTAS49	4	ADDR OF SCV 49 CODE
ISTAS5C	4	ADDR OF SVC 53 CODE
ISTCFCSA	4	ADDR OF COMMAND HANDLER
ISTAPSEX	4	ADDR OF APS EXIT
ISTAPSTA	4	ADDR OF APS TABLE
ISTARID	4	ADDR OF RID
ISTVTP	4	ADDR OF CODE TO CHECK FOR
ISTRETR6	4	BASE REG FOR DOS DISPATCHER
ISTRETR7	4	RETURN REG FOR DISPATCHER
ISTTTXSZ	4	
ISTVTTIK	2	VTAMRP TASK ID
ISTPHNM	5	PHASE NAME OF TRANSIENT
ISTX1	1	TOLTEP SAVES SIO COND CODE

Bytes 96–99 (X'60–X'63) of the system communication region (SYSCOM) contain the address of VTAM Address Vector Table.

ENTRY IN THE ASYNCHRONOUS PROCESS SCHEDULER (APS) OPTION TABLE

Label	Length	Description
APSFFLAG	1	X'20' USER EXIT DELAY FOR LTA
	3	POINTER TO VTAM APT
APSCNT	1	COUNT OF VTAM ACBs OPEN
VTAMFLAG	1	X'80' TPBAL ISSUED (AR ONLY)
		X'40' DUMP ALREADY TAKEN
		X'20' VTAM DELAYED CANCEL
		X'10' AP DELAYED FOR TERM.
		X'08' VTAM USER EXIT IN CTL.
		X'04' VTAM SVC ACTIVE
		X'02' VTAM APPENDAGE ACTIVE
		X'01' KEY 0 / SUBSTATE REQUIRED
	3	RESERVED



CRT CONSTANT TABLE (CRTTAB)

0	7	8	9	11	12	13	15	16	17	19	20	27
Name of CRT Routine	Dummy Sense Byte	Address of CRT Save Area	Flag Byte 1	Address of CRT Trans. Area	Flag Byte 2	Address of System Task Save Area	CRT error Information *					

* limited channel logout is saved here

Byte 8 – Sense byte:

- Bit 0 1 = Command reject
- Bit 1 1 = Intervention required (only if Console Printer is attached)
- Bit 4 1 = Equipment check (only if Console Printer is attached)
- Bit 7 1 = Operation check

or: this byte is used for saving Name Indicator

Byte 12 – Flag byte 1:

- X'80' ERP message
- X'40' Unit check for CRT
- X'20' CRT Fetch bound
- X'10' Device End simulated
- X'08' Validation error
- X'04' Redisplay mode
- X'02' CRT error

Byte 16 – Flag Byte 2:

- X'80' CRT busy
- X'40' Sense byte prepared
- X'20' End of CRT routine
- X'10' Data already read
- X'08' Attention pending
- X'04' Request pending
- X'02' Attention request
- X'01' EOJ on CRT

Bytes 52–55 (X'34'–X'37') of the System Communication Region (SYSCOM) contain the address of the CRT CONSTANT Table. Label CRTTAB identifies the first byte of the table.

The first byte of this address, byte 52, indicates the type of the generated CRT support. The bits have the following meaning:

Bits 0–5 Reserved

Bits 6–7 Indicate the support for the operator console that has been generated in the supervisor:

- 00 = Typewriter
- 01 = 125 D
- 11 = 3277/3278

CHAPTER V
VSE/AF2 SERVICE AIDS

OLTEP

Functions:

- Diagnosing I/O errors
- Verifying I/O device repairs and Engineering Changes
- Checking I/O devices

System Generation requirements:

None

Requirements for Execution of OLTEP:

- OLTs and CDSs available in Core Image Library
- Devices to be tested are in 'Ready' Status
- Any real partition having at least 18 K of Storage
- If OLTEP runs in a VSE/POWER controlled partition or has to test devices being spooled by VSE/POWER, please consult the DOS/VSE-OLTEP SRL (GC33-5383) for special recommendations.

JCL to invoke OLTEP:

Statement	Comments
// JOB XXXX	Mandatory.
// ASSGN SYS000,cuu	This ASSGN statement is necessary if NST loading is to be performed.
// DLBL BGBPDTF, 'SAK.SYSM'	This DLBL statement is necessary if NST loading is to be performed.
// EXTENT BGBPDTF	This EXTENT statement is necessary if NST loading is to be performed.
// ASSGN SYSnnn,cuu	One ASSGN statement is necessary for each device tested or accessed by a test. None is required if the device was permanently assigned.
// UPSI 01	This statement is necessary if a console device is available but the test-run definition is to be entered via the input job stream (SYSIPT).
10	This statement is necessary if READD data input is contained on diskette.
11	This statement is used when both of the above options are being used.
// UPSI 001 0001	This statement is needed if OLTs reside on an NST disk. This statement is necessary if OLTs reside on an NST tape.
EXEC IJZADOLT, REAL,[SIZE=NK]	Mandatory, OLTEP will run only in real. Size=parameter must be minimum of 18K; this will allow a 4K OLT to execute. If OLTs larger than 4K are to be run, the SIZE=parameter must specify a size equal to 14K plus the size of the OLT. The size specified must be a multiple of 2K. If the SIZE=parameter specifies a size of 22K or larger, add 4K since the 4K history tape input buffer will be automatically allocated during OLTEP initialization. If NST loading is to be performed, the minimum core needed is 26K. If 30K is available, a history tape read buffer will automatically be allocated. The SIZE=parameter must always be used when NST loading, because a 4K buffer is allocated in the GETVIS area.
dev/test/opt	This statement is included if the test-run definitions are entered via the input job stream.
/*	Mandatory.
/&	Mandatory.

OLTEP (. . . . Cont'd)

Table of Options


Option	Entry	Description
Testing Loop	<u>TL(n)</u> <u>NLT</u>	Recycle the test. If you specify a value (n), OLTEP runs the test the number of times indicated. If you do not specify a value, the test cycles 10 times. The maximum value allowed is 32,767 decimal. (See Note 1)
Error Loop	<u>EL(n)</u> <u>EL(l)</u> <u>NEL</u>	Authorizes any error loop coded in the OLT to be executed the specified number of times. If you specify a value (n), the test loops the number of times indicated. If you do not specify a value, the test loops the number of times indicated in the preface of the OLT. If you specify the character l, a flag is set which indicates to the OLT, that it must loop indefinitely on the error. You can terminate the loop by specifying NEL following a request for communications. (See Note 1)
Print	<u>PR</u> <u>NPR</u>	Print messages from the OLT. If you enter NPR, all messages originated by the OLT and normally designated for SYSLSST are suppressed. (See Note 2)
Error Print	<u>EP</u> <u>NEP</u>	Print diagnostic error messages from the OLT. The FE option overrides NEP when a first error is encountered (once per section). (See Note 3)
Control Print	<u>CP</u> <u>NCP</u>	Print OLT start and termination messages on SYSLSST and SYSLOG.
Parallel Print	<u>PP(n)</u> <u>NPP</u>	Use the console device, in addition to SYSLSST for OLT messages. Four levels of print are available on the parallel printer by entering one of these numbers at (n). 0: HEADER only 1: HEADER, DESCRIPTION and COMMENTS 2: HEADER and RESULTS 3: HEADER, DESCRIPTION, COMMENTS and RESULTS
First error Communications	<u>FE</u> <u>NFE</u>	Forces a communications interval when the first error is encountered. (See Note 3.) A message is printed indicating the test being run and the device being tested. This is followed by the 01E105D message that allows you to: <ul style="list-style-type: none"> • Change the device and/or test fields. • Continue the test by entering <code>///</code> or <code>/(option change)/</code>. • Enter any OLTEP verb. • Cancel OLTEP by entering CANCEL. There cannot be a first error communication if a console device is not available.
Manual Intervention	<u>MI</u> <u>NMI</u>	Informs the OLT section to run all manual intervention routines within the test request. (Manual Intervention and RE are mutually exclusive options.)
Trace	<u>TR</u> <u>NTR</u>	Trace all functions called by OLT. (See Note 4)
EXT=	<u>EXT=</u>	Information following this option is passed to the OLT section by way of a 56-byte buffer. This information must be the last entry in the option field and can contain any character but a slash. EXAMPLE: 181/2400C/TL,EXT=BLOCK 4FFPRINT/ BLOCK 4FFPRINT goes into a buffer area within OLTEP and then passes on to the OLT section.
The default options are underlined.		
Note 1: The FE option overrides the TL and EL options, unless NPR is also in effect. However if you enter <code>///</code> or <code>/(option change)/</code> at a first error communications interval, the TL and EL options, if specified, are in effect.		
Note 2: NPR without EL and/or TL is ignored.		
Note 3: Error print and FE are ignored if no print and either EL or TL are specified.		
Note 4: Routine-to-routine linkage is not traced. Do not attempt to use Trace function when SYSLSST is assigned to the test device.		

OLTEP (. . . . Cont'd)

Example of OLTEP Operation (in BG, but can also run in foreground)

BG assign sys001, 181	
BG assign sys002, 182	← OLTEP is loaded into the back-ground partition
BG // exec ijzadolt,real,size=nK (minimum 18K)	
BG E1021 OLTS RUNNING	
BG E1341 WARNING - DASD VOLUME LABELED CEPACK NOT PROTECTED FROM WRITE	
BG E1071 OPTIONS ARE NTL,NEL,NPP,FE,NMI,EP,CP,PR,NTR	
BG 01E105D ENTER--DEV/TEST/OPT/←	Initial communications interval
BG 181/2400a//	
BG E1191 NON-STANDARD TAPE LABEL 0181←	← OLTEP finds a nonstandard labeled tape mounted on the test device
BG 04E139D REPLY B TO BYPASS,R TO RETRY,P TO PROCEED (MAY DESTROY DATA)	
BG p	
BG E1581 S T2400A \$ UNIT 0181	← Error encountered
BG E1291 FIRST ERROR COMMUNICATION T2400A 001 UNIT 0181	
BG E1071 OPTIONS ARE NTL,NEL,NPP,FE,NMI,EP,CP,PR,NTR	
BG 01E105D ENTER--DEV/TEST/OPT/←	First error communications interval
BG 182//nfe,tl (2)/	
BG E1581 *T T2400A \$ UNIT 0181	
BG E1581 S T2400A \$ UNIT 0182	
BG E1581 T T2400A \$ UNIT 0182	
BG E1581 S T2400A \$ UNIT 0182	← Console interrupt key pressed
BG E1071 OPTIONS ARE TL,NEL,NPP,NFE,NMI,EP,CP,PR,NTR	
BG 01E105D ENTER--DEV/TEST/OPT/←	Interrupt communications interval
BG /2400c,e/n tl/	
BG E1581 *T T2400A \$ UNIT 0182	
BG E1581 S T2400C \$ UNIT 0182	
BG E1581 T T2400C \$ UNIT 0182	
BG E1581 S T2400E \$ UNIT 0182	
BG E1581 T T2400E \$ UNIT 0182	
BG E1071 OPTIONS ARE NTL,NEL,NPP,FE,NMI,EP,CP,PR,NTR	
BG 01E105D ENTER--DEV/TEST/OPT/←	Test completion communications interval
BG cancel	
BG I100A READY FOR COMMUNICATIONS	

Storage Layout



OS/VS, VSE/AF2, VM/370 - EREP
(Environmental Recording, Editing and Printing)

The service aid program IFCEREP1 can be used to retrieve all or selected records from the input data set(s), edit the records, and write them to any specified output device supported by the Sequential Access Method (SAM). A direct access device may be required for allocation of a temporary work data set.

Executing IFCEREP1

Program IFCEREP1 is the main execution routine for running EREP. The parameters may be specified only via card (SYSIPT) input.

The operator should execute the ROD command prior to running EREP from SYSREC.

Executing IFCOFFLD

Program IFCOFFLD is a special purpose load of EREP modules which is provided for clearing SYSREC, under emergency conditions, without losing the data recorded thereon.

There are no parameters allowed when executing IFCOFFLD.

- SYSREC is input.
- SYS009 is the history output data set logical unit number.
- System Summary Report is printed.
- If message IFC1191 is received, alter the SIZE parameter on the // EXEC card and, if necessary, alter the partition size.

EREP Functions

EREP Basic Functions
1. Create an Accumulation data set from the SYSREC data set.
2. Clear SYSREC.
3. Copy an Input Accumulation data set to an Output Accumulation data set.
4. Merge data from an Accumulation data set and SYSREC.
5. Format Reliability Measurement data.
6. Print detail description of hardware error records.
7. Summarize and print statistics for device failures.

EREP Reporting Functions
1. System Summary Reporting
2. Trends Reporting
3. Event History Reporting
4. Media Error Statistics Reporting
5. Threshold Reporting
6. Record detail and/or Summary Reporting
7. RDE Summary Reporting
8. Offload

EREP (. . . Cont'd)

JCL for EREP

Statement	Usage
// JOB EXAMPLE	This statement initiates the job.
// TLBL HISTINT or // DLBL HISTIND // EXTENT SYS008,XXXX,1,,XXXX,XX ¹ // ASSGN SYS008, cuu	These Job Control Statements are used to process History Input. Either History Input or SYSREC Input or both must be processed each IFCEREP1 execution. The ASSGN statement must always be used for History Input. The TLBL is used for Tape resident History Input; the DLBL and EXTENT for Disk resident History Input.
// TLBL HISTOT or // DLBL HISTOD // EXTENT SYS009,XXXX,1,,XXXX,XX ¹ // ASSGN SYS009, cuu	These Job Control Statements are used to create a History Output data set. The TLBL statements is used for Tape resident History Output; the DLBL and EXTENT statements are used for Disk resident History Output.
// ASSGN SYS001, cuu // DLBL IJSYS01 // EXTENT SYS001,XXXX,1,,XXXX,XX ^{1,2}	These Job Control Statements are used to define the temporary work data set on a direct access device. These statements are necessary when a History Input data set is read. ³ EXTENT and DLBL statements should not be necessary as SYS001 should already be defined for the linkage editor. The standard SYS001 EXTENT should provide enough space for most IFCEREP1 executions; at any rate, enough space must be allocated to store all records selected from the input data set(s).
// EXEC PGM=IFCEREP1,SIZE=64K	This statement specifies the program name to be executed. The minimum virtual region size for VSE/AF2 is 100K. The default GETVISI area of 36K is specified.
The following system logical units are used by IFCEREP1 but should already be assigned.	
SYSREC	The assignment for the System Recording Data Set must already be made.
SYSLST	Both message output and report output are sent to this logical unit.
SYSLOG	If SYSLST is unavailable, a termination message is written to the console.
SYSIPT	IFCEREP1 input parameters and control cards are input to this required system logical unit.

¹ Ask your system programmer how to code EXTENT statements.

² DISKWRK must be a ONE EXTENT Data Set.

³ RDESUM and PRINT=NO do not require the Work Data Set for History Input.

Logical Units Required by Function

Logical Units	EREP Keywords					
	ACC=Y	HIST=Y	MERGE=Y	RDESUM=Y	ALL OTHERS	HIST=N
SYS009	X					
SYS008		X	X	X		
SYS001		X	X			
SYSREC			X		X	X
SYSLST	X	X	X	X	X	X
SYSLOG	X	X	X	X	X	X
SYSIPT	X	X	X	X	X	X

EREP (. . . Cont'd)

EREP Keywords

EREP uses Keyword parameters to determine the functions requested and any restrictions placed on the records to be processed. The default value is underlined, where applicable. Multiple parameters within one Keyword have to be separated by commas. Keywords which have operands Y or N may be abbreviated to the Keyword only to imply the Y value, o.g. ACC implies ACC=Y. For details please consult OS/VS, DOS/VSE, VM/370-EREP (GC28-0772).

Keyword Parameters	Purpose
ACC = $\left[\begin{matrix} Y \\ N \end{matrix} \right]$ Default exceptions are: MES, RDESUM and THRESHOLD	Accumulate selected records
CPU = (serial,model [,serial,model]) Maximum of 7 entries	Select CPU by serial number (nnnnnn) and model (nnnn)
CPUCUA = (serial,addr [,serial,addr]) Maximum of 4 entries	Select unique device addresses on a specific CPU
CUA = (entry [,entry]) Maximum of 8 entries	Select device/control units by unique addresses (nXX,nnX or nnn where n=hex digit and X=character 'X')
DATE = (yyddd [<u>;</u>]yyddd) Single date or date range	Date span for selected records
DEV = (type [,type]) Maximum of 8 entries	Select device type (nnnn or nnXX where X = character 'X')
DEVSER = (serial [,serial]) Maximum of 8 entries	Select device serial numbers (nnnnnn), (3410/3420 devices only)
EVENT = $\left[\begin{matrix} Y \\ N \end{matrix} \right]$	Provide an event history report
HIST = $\left[\begin{matrix} Y \\ N \end{matrix} \right]$ Default exception is: RDESUM	Indication for input data set
LIBADR = address	Select records by Line interface base address (XXXX - hexadecimal)
LINECT = nnn Number of lines Default = 50 lines	Number of Lines to be printed on a page (nnn - decimal)
MES = $\left[\begin{matrix} Y \\ N \end{matrix} \right]$	Allows selection by channel/unit address and volume serial number (3410/3420 only)
MERGE = $\left[\begin{matrix} Y \\ N \end{matrix} \right]$	Allows merging of EREP input (Accumulation data set + SYSREC)
MOD = (model [,model]) Maximum of 4 entries	Select specific CPU-models (nnn or nnnn)
PRINT = $\left\{ \begin{matrix} SU \\ PS \\ PT \\ NO \end{matrix} \right\}$	Select format of printout (see Note 2)
RDESUM = $\left[\begin{matrix} Y \\ N \end{matrix} \right]$	Allows printing of RDE-information from IPL
SHORT = $\left[\begin{matrix} Y \\ N \end{matrix} \right]$	Allows suppression of detail printing of OBR-records
SYMCDE = $\left\{ \begin{matrix} nnn \\ nnX \\ nnXX \\ nXXX \end{matrix} \right\}$	Select records by fault symptom code (33XX-DASDs only) n = hexadecimal digit X = character 'X'
SYSUM = $\left[\begin{matrix} Y \\ N \end{matrix} \right]$	Allows printing of a system summary report
TABSIZE = nnnK Default = 4K for VSE/AF2	Specify size of internal sort table
TERMN = name	Select records by terminal name (VTAM only)

EREP (. . . Cont'd)

EREP Keywords (. . . Cont'd)

Keyword Parameters	Purpose
THRESHOLD = (xxx,yyy)	Specify threshold value for temporary read/write errors (3410/3420 only) - decimal digits
TIME = (hhmm{;} hhmm)	Time span for selected records
TRENDS [= {Y} / {N}]	Generate a Trends report
TYPE = [C] [D] [E] [I] [M] [O] [T]	Select records by their type (see note 1)
VOLID = (volser [, volser]) Maximum 4 entries	Select records by volume serial number (3410/3420/33XX only) - 1 to 6 alphanumeric characters
ZERO [= {Y} / {N}]	Clear SYSREC after processing

Note 1

Record types

Code	Meaning	Selection Keywords*
C	CCH	CPUCUA, CUA
D	DDR	CPUCUA, CUA, DEV
E	EOD	
I	IPL	
M	MCH	ERRORID
O	OBR	CPUCUA, CUA, DEV, SYMCDE, TERMN, VOLID, DEVSER
T	MDR	CPUCUA, CUA, DEV, LIBADR, VOLID

*Other selection keywords apply to all record types

Note 2

SU	Suppress full printing (print summary only)
PS	Print full record and summary
PT	Suppress summary printing (print full record only)
NO	Suppress full printing and summary printing

EREP (. . . Cont'd)

Keyword Parameter Specifications not accepted by EREP (X = Conflicting Parameters)

Keyword	ACC	CPU	CPUCUA	CUA	DATE	DEV	DEVSER	HIST	LIBADR	LINECT	MERGE	MOD	SHORT	SYMCDE	TABSIZE	TERMN	TIME	TYPE	VOLID	ZERO	
ACC																					
CPU							x														
CPUCUA		x																			
CUA			x																		
DATE				x																	
DEV																					
DEVSER	x						x ¹														
HIST																					
LIBADR									x ²												
LINECT																					
MERGE											x										
MOD																					
SHORT																					
SYMCDE																					
TABSIZE																					
TERMN																					
TIME																					
TYPE																					
VOLID																					
ZERO		x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x	x

Notes: ¹ Devices 3410 and/or 3420 are allowed.

² Device 3705 is allowed.

EREP Functions with allowable Keyword Specifications (x = Allowable):

Keyword EREP Functions	Selection													Input	Output	Control					
	CPU	CPUCUA	CUA	DATE	DEV	DEVSER	LIBADR	MOD	SYMCDE	TERMN	TIME	TYPE	VOLID	MERGE	HIST	ACC	SHORT	LINECT	TABSIZE	ZERO	
EVENT	x																				
MES ³	x																				
PRINT=PS	x	x	x	x	x	x ²	x														
PRINT=PT	x	x	x	x	x		x	x	x	x	x	x	x	x	x	x	x	x	x	x	x ¹
PRINT=SU	x	x	x	x	x		x	x	x	x	x	x	x	x	x	x	x	x	x	x	x ¹
PRINT=NO	x	x	x	x	x		x	x	x	x	x	x	x	x	x	x	x	x	x	x	x ¹
RDESUM																					
SYSDUM																					
TRENDS																					
THRESHOLD	x																				

Notes: ¹ ZERO is acceptable only when no selective parameters are requested and a full print or Accumulation data set is generated.

² Devices 3410 and/or 3420 are allowed.

³ PRINT = PT, PS, or SU is allowed.

During an execution of EREP one of the above functions is performed. The default function is PRINT=su which is underscored and generates summary reports for all data contained on SYSREC; this is the defaulted input.

EREP (. . . Cont'd)

EXAMPLES FOR AN EREP RUN.

(For further examples please consult OS/VS, DOS/VSE, VM/370-EREP (GC28-0772))

1) Generating a System Summary Report from SYSREC

In this example:

- All data on SYSREC is summarized for the System Summary Report
- All records on SYSREC are written to an Accumulation data set and SYSREC is cleared.

```
// JOB EREP
// TLBL HISTOT
// ASSGN SYS009,TAPE
// EXEC IFCEREP1
SYSUM
END PARM
/*
/ &
```

The TLBL and ASSGN statements define the History Output Data Set which resides on magnetic tape (Accumulation Data Set).

The messages generated by EREP and the System Summary Report will be written to the device assigned to SYSLST.

The EXEC statement specifies that EREP is to be run.

The SYSUM parameter read from SYSIPT specifies that a System Summary Report is to be generated. Effective defaults are ACC=Y and ZERO=Y; therefore, SDR records are dumped to SYSREC before data retrieval is begun.

2) Printing selected records from an Accumulation data set

In this example:

- All DDR and OBR records for 33XX-devices with specific VOLIDs are printed on SYSLST.
- Data are taken from a previously created Accumulation data set (SYS008).

```
// JOB EREP
// TLBL HISTINT
// ASSGN SYS008, TAPE
// EXEC IFCEREP1
TYPE=DO,PRINT=PS, ACC=N, DEV=(33XX)
VOLID=(SYSRES, xxx xxx)
END PARM
/*
/ &
```

The TLBL and ASSGN statements define the History Input Data Set which resides on magnetic tape (Accumulation data set).

TYPE=DO specifies that DDR and OBR records are to be printed.

PRINT=PS specifies full record and summary printing.

ACC=N specifies that no accumulation has to take place.

DEV=33XX specifies that only 33XX-related records are to be printed.

VOLID=(SYSRES,xxx) specifies that only records related to the given VOLIDs are to be printed.

GLOSSARY OF ABBREVIATIONS USED IN EREP OUTPUT

BYTES RD/SRCHD	Megabytes Read/Searched
CCH	Channel Check Record
CCH-CRH	CCH-Channel Reconfiguration Hardware
CCH-INC	CCH Incomplete Record
CHNL	Channel
CK or CHK	Check
CMD or CMND	Command
CNTRL	Control
CNTRLR	Controller
COMP/MOD	Component/Module
CONS+UR	Console plus Unit Record
CORR	Correctable
CSECTID	Control Section Identification
CSW	Channel status word
C.U.	Control Unit
CUA	Channel-control unit-device address
DATA CKS CORR/RTRY	Data checks correctable/retry
DDR	Dynamic Device Reconfiguration Record
DDR-OPR	DDR-Operator Requested
DDR-SYS	DDR-System Requested
EOD	End-of-Day Record
EQUIP	Equipment
ERDS	Error Recording Data Set (SYS1.LOGREC for OS/VS, SYSREC for VSE/AF2, Recording Cylinders for VM)
ERROPS	Error Operations
FMT	Format
HDR SER	Header(tape)/serial number of drive that created tape
ID	Identification
INV	Invalid
IPL	Initial Program Load
LEN	Length
MCH	Machine Check Record
MCH-TRM	MCH-System Terminated
MDR	Miscellaneous Data Record
MIH	Missing Interrupt Handler Record
MIH-CE	MIH-Channel End Pending
MIH-DE	MIH-Device End Pending
OBR	Outboard Record
OBR-DMT	OBR-Dismount Record
OBR-EOD	OBR End of day
OBR-PRM	OBR-Permanent error record
OBR-SHT	OBR-Short Record
OBR-TMP	OBR-Temporary Error
OVERRN	Over run
OVERRUN CDDA/CDDA	Overrun Command Data/Command Data
PERM	Permanent
PRGM INT	Program Initiated
PROG-EC	Program-Extended Control Mode
PSW	Program Status Word
RCYRYXIT	Recovery Exit module
REC-TYP	Record Type
RTN	Routine
SCP	System Control Program
SEEKS CNTR/HH	Seek errors Cylinder Track/Head
SFT	Software Record
SFT-ABN	SFT-ABEND record
SFT-MCH	SFT-Machine Error, recoverable
SFT-PI	SFT-Program Interrupt
SFT-RST	SFT-Restart
SSYS ID	Sub-system Identification
TEMP	Temporary
TERM	Terminal
WRTS	Writes

Note: Most other abbreviations are meant only for the Customer Engineer, and are not meaningful to other personnel, even in translation.

SDAIDSGeneral

The VSE/AF2 SDAID provides all of the functions that have been available with programs PDAID and SDAID under DCS VS Releases 34 and before, plus a number of additional functions.

Requirements

- DOS/VSE or VSE/AF
- SDAID virtual space 100 KBytes
- SDAID BASIC real space 11 KBytes

Restrictions

- Time dependent programs may not be debugged.

How to execute SDAID from the OPERATOR Console

SDAID provides a prompting facility, which will assist you in entering the control commands, needed by SDAID.

To request a prompting information, you should enter a question mark (?) in response to SDAID's prompting message. If you had made an error in control commands, key in two question marks (? ?) and hit END/ENTER. This causes SDAID cancel all control commands.

The following is an example in which SDAID is used to trace SIO activities.

SDAID will be started by entering in attention routine (AR) the command.

```
SDAID 
4C05I Processing of 'SDAID' Command Successful

TRACE 
4C08D Specify TRACE Type.+

SIO 
4C08D Specify Type of IO/SIO TRACE. +

UNIT 
4C08D Specify Unit Address(es). +

O2C 
4C08D Specify Output. +

CCW 
4C08D Specify Occurrence Range. +


4C08D Specify 'HALT' or 'NOHALT' or Press END/ENTER.


4C08D Specify Termination Options. +


4C05I Processing of 'TRACE' Command Successful

OUTDEV P=E 
4C05I Processing of 'OUTDEV' Command Successful

READY 
4C05I Processing of 'READY' Command Successful

STRTSD 
4C05I Processing of 'STRTSD' Command Successful
```


Note: = Operator Presses END/ENTER Key.

SDAID (. . . . Cont'd)

Command	Summary of purpose	Add'l info re- requested by SDAID	
		yes	no
AREA	Establishes the address range within which the occurrence of the specified event (s) is (are) to be traced. An AREA command may be overridden by the area definition of a TRACE command, but only for the event(s) specified in that TRACE command. If, for an SDAID session, no AREA command is submitted, you must provide an area definition in each of your TRACE commands for the session.	x	
OUTDEV	Establishes the method of trace information output. The command is mandatory.	x	
TRACE	Establishes the program event(s) to be traced. At least one TRACE command must be entered per SDAID session; up to ten different trace commands may be submitted per SDAID session. The command is mandatory.	x	
READY	Ends SDAID initiation command input (AREA, OUTDEV, and TRACE commands, which must precede the READY command). The command is mandatory.		x
STRTSD	Starts SDAID execution. The command may follow the READY command or a STOPSD command, if one was entered. The command is mandatory.		x
STOPSD	Stops SDAID execution. The command is optional. If entered, it must follow a STRTSD command.		x
ENDSD	Ends SDAID execution. The command must be issued at the end of an SDAID session; it requests SDAID to release all system resources that the program used during the preceding session.		x


Summary of available SDAID commands

Note: For more information and detailed description of SDAID refer to the VSE/AF2 Serviceability Aids and Debugging Procedures.




Specification path diagram for the AREA command

SDAID (. . . Cont'd)




Specification path diagram for the TRACE command




Specification path diagram for the TRACE command

SDAID (. . . Cont'd)



Specification path diagram for the TRACE command



Specification path diagram for the OUTDEV command

TRACING of 4331 Communication Adapter EVENTS

Functions: – Activates or deactivates the communication adapter line trace.
 – Records the trace entries on tape while line is running.
 – Prints entries after a line related error has occurred.

Prerequisites: – VSE/AF on a 4331.
 – Runs in minimum virtual partition.
 – Uses the 03B subchannel.
 – Dynamic trace ILT must be invoked.

Statements: **OPtion FBCDE:**

F Function	BC Data	DE Bytes	Meaning
4	10	xx	Start line trace on subchannel xx
4	11	xx	Stop line trace on subchannel xx

DYnadmp Dynamic: Initiates recording of trace on the work file dynamically as entries are made.

PRINT: Print a listing on device specified in SYSLST.

PRINT START=hh:mm:ss: Print trace blocks after specified time.

PAuse: Allows control statements to be entered at the console.

ENd: Specifies the end of job after trace has been printed.

SYsin: Causes to be read control statements from SYSIN.

Example of trace job stream:

```
// Job xxx
// Assgn SYSLST,cuu           Define the output file
// Assgn SYS010,cuu          Define the tape work file
// Assgn SYS011,03B         Required communication adapter
                             trace subchannel

// Exec IDUSVEP
PAuse                        Enter from console

OPTION 41033                 Starts a line trace on subchannel 33
DYNadmp Dynamic
-----                     Stop the dynamic dump,
                             establish operator communication

SYSin
PPrint
/*
/&
```

Trace recording can be stopped by stopping the trace ILT.

HARD AND SOFT WAIT CODES

BYTE 0	BYTE 1	BYTE 2	BYTE 3	EXPLANATION
MCH/CCH/IPL Hard Wait Codes placed in low address storage				
X'C1'	X'E2'	A,I,S(1)	Not used	Irrecoverable machine check.
X'C2'	X'E2'	Not used	Not used	Irrecoverable channel failure during FETCH.
X'C3'	X'E2'	A,I,S(1)	Not used	Channel failure on SYSLOG when RMS message scheduled.
X'C4'	X'E2'	A,I,S(1)	Not used	No ECSW stored.
X'C5'	X'E2'	A,I,S(1)	Not used	Channel failure: ERPIB queue exhausted.
X'C6'	X'E2'	A,I,S(1)	Not used	Channel failure; two channels damaged or a damaged channel situation occurred while RMS was executing an I/O operation.
X'C9'	X'E2'	A,I,S(1)	Not used	Channel failure; channel address invalid (370 mode only).
X'D1'	X'E2'	A,I,S(1)	Not used	Irrecoverable channel failure on the device assigned to the page data set.
X'07'	X'E6'	Channel	Unit or X'00'	IPL I/O error or equipment malfunction; condition code 2 during STIDC instruction. Channel and unit indicate whether device in error is SYSRES or communication device. When byte 3=X'00', byte 2 indicates the channel for which STIDC instruction was issued. Re-IPL system.
Note: Byte 1 is not set by RAS.				
(1) A (X'C1') = SYSREC recording unsuccessful -- run SEREP				
I (X'C9') = SYSREC recording incomplete -- run SEREP				
S (X'E2') = SYSREC recording successful -- run SEREP				
(this field is not set by IPL)				
The following Hard Wait Codes are placed in general register 11 X'B' as well as in low address location 0 and in bytes 4 to 7 in the system communications region.				
X'00'	X'00'	X'0C'	X'CC'	No recovery possible from CRT errors.
X'CC'	X'00'	X'0F'	X'D0'	Error during IPL. IPL canceled. (cc=cancel code).
X'00'	X'00'	X'0F'	X'F1'	System error detected by the page manager.
X'00'	X'00'	X'0F'	X'F4'	\$\$\$ transient phase not found (the name of the phase is record in ERBLOC).
X'00'	X'00'	X'0F'	X'F5'	TFIX count past maximum value or minus zero.
X'00'	X'00'	X'0F'	X'F6'	\$MAINDIR canceled during system CIL update. If this occurs, the system CIL is only partially updated and must be corrected before use. This hard wait condition can also occur if the FETCH QUEUE BIT (FCHQ) is set in the linkage control byte in the partition communication region owned by the terminating partition.
X'00'	X'00'	X'0F'	X'F7'	No copy blocks available for BTAM-ES appendage I/O request.
X'00'	X'00'	X'0F'	X'F8'	CRT phase not found.
X'00'	X'00'	X'0F'	X'F9'	Error on paging I/O.
X'00'	X'00'	X'0F'	X'FA'	Translation Specification Exception.
X'00'	X'00'	X'0F'	X'FB'	Page Fault in Supervisor routine with identifier RID X'00'.
X'00'	X'00'	X'0F'	X'FC'	Machine Check if RMS=NO is specified during system generation. (Models 115 and 125.)
X'00'	X'00'	X'0F'	X'FD'	Channel Failure if RMS=NO is specified during system generation. (Models 115 and 125.)
X'00'	X'00'	X'0F'	X'FE'	I/O error during fetch from System CIL.
X'00'	X'00'	X'0F'	X'FF'	Program Check in Supervisor.
Status for Stand-alone Utilities				
X'FF'	X'FF'	X'FF'	X'FF'	This display is only valid for standalone utilities. It does not indicate a hard wait.

HARD AND SOFT WAIT CODES (. . .Cont'd)

BYTE 0	BYTE 1	BYTE 2	BYTE 3	EXPLANATION
<u>Device Error Recovery Soft Wait Codes placed in low address storage</u>				
X'08' to X'60'	X'C1' or X'C4'	Channel	Unit	Error recovery messages. Refer to 0Pxx messages. After the problem is corrected, the operator must press the Interrupt key to allow processing to resume.
<u>Disabled Wait</u>				
X'00001111' entered when SYSRES, the Page Data Set, SYSLCB or concatenated libraries are not ready. Ready the device and press the RESTART key.				
<u>Other states during IPL</u>				
If there is an equipment malfunction during IPL, or if the IPL program cannot be loaded, a message is placed in bytes 0–3. In this state all interrupts are disabled, and you must repeat IPL after displaying these bytes.				
X'07'	X'E6'	Channel	Unit or X'00'	IPL input/output error: <ul style="list-style-type: none"> • I/O error on SYSRES Caution: If you use a different disk drive or pack because of errors on disk, caution is advisable. If there has been a headcrash, then this damage could be propagated to other drives and/or packs. <ul style="list-style-type: none"> • I/O error on communication device (see Note 1) • Equipment malfunction during the STORE CHANNEL ID instruction (see Note 2) • Supervisor entry not found
X'F0'	X'C9'	X'F0'	X'F0'	This code indicates that less than 18K of real storage is left for problem programs. Check that the correct disk volume is mounted on the device assigned to SYSRES and re-IPL. If the error recurs, the system programmer must check the allocations of real partitions specified in the supervisor to be used, and check that at least 18K of real storage is available for execution of problem programs running in virtual mode.
X'F0'	X'C9'	X'F0'	X'F1'	If a card reader has been assigned to SYSRDR and is to be the IPL communication device, press the INTERRUPT key. If a card reader has not been assigned to SYSRDR and yet it is to be the IPL communication device, simply READY the reader.
X'F0'	X'C9'	X'F0'	X'F2'	This code means that the supervisor requested cannot be found. Check that the correct disk column is mounted on the device assigned to SYSRES. If it is correct, re-IPL and specify a different supervisor when message 0I03A is issued and press the END/ENTER key, or press END/ENTER key only, to load the standard supervisor. (If possible contact the system programmer and check which supervisor to use.)
X'F0'	X'C9'	X'F0'	X'F6'	The device type of SYSRES could not be identified. The volume label (VOL1) or format-4 record of the VTOC contains invalid information. The pack was not initialized correctly. The system enters the hard wait state. Initialize the disk pack.
X'F0'	X'C9'	X'F0'	X'F7'	See message 0I07.
X'F0'	X'C9'	X'F0'	X'F9'	See message 0I09.
X'F0'	X'C9'	X'F1' to X'F3'	X'F1' to X'F8'	Refer to messages 0I11A–0I38A.
X'F0'	X'C4'	X'F3'	X'F8'	Refer to message 0D38A.

HARD AND SOFT WAIT CODES (. . . Cont'd)

BYTE 0	BYTE 1	BYTE 2	BYTE 3	EXPLANATION
X'F0'	X'C4'	X'F3'	X'F8'	Refer to message 0D38A.
Note 1: When the IPL procedure reaches the normal IPL wait state, and the IPL communication device is to be SYSLOG, press the REQUEST key on the console printer keyboard. Note 2: When byte 3=X'00', byte 2 indicates the channel for which the STIDC instruction was issued.				
<u>SDAID Wait Codes</u>				
X'62'	X'C5'	Not used	Not used	SDAID output device became unready. Make printer ready and press the EXTERNAL INTERRUPT key.
X'00'	X'00'	X'00'	X'00'	SDAID Stop on Event. Press EXTERNAL INTERRUPT key to continue operations.
Note: A value of X'EEEEEE' in the address part of the wait PSW indicates that a tape or printer is not ready. Ready the device and give an external interrupt. A value of X'EEEE' indicates that, if the HALT parameter of the TRACE command was given and the event occurred, you must give an external interrupt.				

ERROR BYTES AND INFORMATIONS IN LOW REAL STORAGE

(in variation to permanent main storage assignment, page I-14)

Storage Loc.		Byte	Byte	Byte	Byte
Hex	Dec				
0-3	0-3	Hard Wait Message Codes (MCH, CCH, IPL)			
0-4	0-4	Device error message codes in case of I/O error, and SYSLOG disabled			
10-13	16-19	In system with ACF/VTAM, address of the VTAM Communications Vector Table (ATCVT)			
14-17	20-23	Address of Communication Region for active partition			
80-83	128-131	Address of SCP Communication Region			
84-87	132-135	Processor Address (370 Hardware)	External Interruption Code		
88-8B	136-139	SVC Interrupt Information	ILC 0	SVC Interruption Code	
8C-8F	140-143	Progr. Check Interrupt Information	Program Interruption Code		
90-93	144-147	Address that caused page fault			
94-97	148-151	Monitor Class Number	PER Code		
98-9B	152-155	PER Address			
9C	156	Monitor Code			
AC-AF	172-175	Address of I/O Extended Logout (370 Hardware)			
B8-BB	184-187	Interrupt Information	I/O Address on Interrupt		
F8-FB	248-251	Failing Storage Address			
FC-FF	252-255	Region Code			
100-15F	256-351	Fixed Log-Out Area			

PDZAP

This program allows you to make changes to programs cataloged in a system or private core image library. It provides a printout of the changes on SYSLST. This printout should be kept on the installation to keep track of the changes made. Use this procedure only for user-written programs. Otherwise use the PDZAP of MSHP.

SYSTEM REQUIREMENTS

PDZAP can be executed in any partition. Since PDZAP accesses a core image library, other programs running currently should not use the phases PDZAP is operating on the same library. SYSLOG must be assigned to the operator console. When card input is used, SYSIPT must be assigned to a card reader (hopper 1 on 5425/2560). SYSLST should be assigned to a printer.

EXECUTING PDZAP

The PDZAP program can be executed from the operator console or from a card reader.

HOW TO EXECUTE PDZAP FROM THE OPERATOR CONSOLE

The following is an example in which the program PROG is used as a phase to be modified.

Call in the program
// EXEC PDZAP

The system will respond:

```
4C86I PDZAP EXECUTION BEGINS
4C99A Enter your name. Reply to this message by typing your name.
4C85A ENTER PHASENAME (XCIL= xxxxxxxx)
```

Reply to this message in one of the following ways:

- a) if PROG is in the system core image library enter SCIL=PROG, or simply PROG, as SCIL is the default.
- b) if PROG is in the private core image library enter PCIL=PROG.

When the phase is found, the following messages are issued:

```
4C87I LOAD ADDRESS=xxxxxx
4C88D ADDRESS XXXXXX, OFFSET=XXXXXX, SCAN=XX..XX, REF=XXXXXX
```

Reply to this message in one of the following ways:

- option 1 specify the hexadecimal address of the data you want displayed: 08072A
- option 2 specify the offset to the reference point of the data you want displayed (the initial reference point is the load address): +6D4
- option 3 specify a character string to be searched: SCAN='LABPROG'
- option 4 specify a hexadecimal string to be searched: SCAN=D3C1C2D7D9D6C7
- option 5 set a reference point: REF=08071C.

If an address is invalid or a string cannot be found, an error message will be issued.

To options 3 and 4 the system will first respond with:

```
4C94I SCAN ADDRESS xxxxxx
```

Options 1-4 will result in the display of up to 16 bytes of data in the format

```
4C89D
xxxx..xx cccc..cc
```

where xxxx..xx is the hexadecimal representation and cccc..cc is the corresponding character representation.

The data printed is contained in a single library block. If less than 16 bytes are displayed, it is either the end of the program or the end of the library block.

If only a display is wanted, press END/ENTER.

To modify the displayed data, type in replacement data for the number of bytes to be changed. For instance, if the data displayed is:

```
4C89D
05B01210746410000014790B42807F6 ..... 6
```

to change the first four bytes to NOP, type in:
07000700

The system will respond with message 4C88A again and you can use one of the five options mentioned above to display or modify another portion of the same phase, or to set another reference point.

PDZAP (. . . Cont'd)

HOW TO EXECUTE PDZAP FROM THE OPERATOR CONSOLE (: . . Cont'd)

If you are finished with this phase, but want to access another phase, use

- option 6 terminate processing with this phase by typing END PHASE

Now the program repeats message 4C85A, which allows you to specify the name of another phase.

If you want to terminate the execution of PDZAP, use

- option 7 end PDZAP operation by typing: END

HOW TO EXECUTE PDZAP FROM A CARD READER

Executing PDZAP from SYSIPT is the same as from SYSLOG, with the following exceptions:

// UPSI 1 must be specified to indicate card input
data must be verified before it can be changed.

Example:

```
// UPSI 1           indicate card input
// EXEC PDZAP      call the program
NAME=your name    specify your name
SCIL=PROG         specify the phase to be accessed
+6D4              specifies the position of the data to be displayed (option 2)
VER=05B0, 1211 or } specifies the data to be verified; if the data is
VER=05B01211      } not found, no update will take place
REP=07000700 or  } specifies the data which is to replace the date
REP=0700,0700    } just verified
END               } terminates the run
```

The format of the VER and REP data can be:

- a hexadecimal string (full bytes, or an even number of digits)
- a set of 2-byte entries, separated by commas
- a character string, preceded by a quote (VER='LABPROG').

OUTPUT OF PDZAP ON SYSLST

On SYSLST, which must be a line printer, the program prints the following in the sequence as shown:

PDZAP.

Date and time of the change.

Your name as specified.

Name of the phase that has been changed.

Load address of that phase.

Address of the changed data.

Old data in hexadecimal notation.

New data in hexadecimal notation.

Note: Full details about possible responses to PDZAP messages are given in VSE/AF messages.

DOSVSDMP AND STAND-ALONE DUMP

DOSVSDMP, A PROGRAM OF VSE/AF2, CAN BE USED TO CREATE A STAND-ALONE DUMP IN CARDS, ON A DISKETTE, ON MAGNETIC TAPE, OR ON DISK. THE PROGRAM CAN ALSO BE USED TO PRINT THE OUTPUT OF:

- A STAND-ALONE DUMP.
- A DUMP TAKEN IN RESPONSE TO A DUMP COMMAND IF THE OUTPUT WAS WRITTEN ONTO MAGNETIC TAPE OR DISK.
- AN EXECUTION OF THE SDAID PROGRAM IF ITS OUTPUT WAS WRITTEN ONTO MAGNETIC TAPE.

1. RECORD ANY ERROR OR STATUS INDICATORS ON THE SYSTEM CONSOLE.
2. USING ALTER/DISPLAY, RECORD THE CURRENT PSW, GENERAL REGISTERS, AND FLOATING POINT REGISTERS.
3. PERFORM THE STORE STATUS (43XX PROCESSORS SAVE MACHINE) PROCEDURE FOR YOUR SYSTEM.
4. IPL YOUR DUMP PROGRAM FROM CARDREADER, TAPE, DISKETTE, OR DISK.
5. IF MESSAGES 4C43I DOSVS DMP COMPLETE 0000XX TRACKS USED, RESTART VSE/AF AND PREPARE TO PRINT THE DUMP AS SOON AS THE SYSTEM HAS BEEN RESTARTED.

CREATING THE STAND-ALONE DUMP PROGRAM

THE PROGRAM, ONCE IT RECEIVED CONTROL, PROMTS YOU FOR FURTHER CONTROL INFORMATION, AND YOU SELECT THE DESIRED OPTION BY AN APPROPRIATE RESPONSE TO THE PROGRAM'S PROMT AS SHOWN.

PROMT MESSAGE

XX 4C50D SELECT YOUR OPTION BY THE CORRESPONDING NUMBER

1. CREATE DOSDMPF	2 PRINT DUMP	3 PRINT SDAID TAPE
4 PRINT FILE	5 INFORMATION	6 EOJ (DEFAULT)
7 CREATE DOSDMPG	8 CLR DOSDMPF	9 CLR DOSDMPG

EXAMPLE FOR JOB CONTROL

TAPE DUMP:

1. SELECT A NON-LABELED TAPE TO BE USED AS THE DUMP VOLUME.
2. EXECUTE DOSVSDMP:


```
// JOB
// ASSGN SYS006, 280
// EXEC DOSVSDMP
/ &
```
3. WHEN MESSAGE 4C50D IS ISSUED, REPLY: 1
(1 CREATE DOSDUMPF) (6 EOJ DEFAULT)
4. MESSAGE 4C79 I INDICATES THAT CREATION OF THE DUMP PROGRAM TAPE IS COMPLETED.
REFER TO VSE/AF2 MESSAGES FOR AN EXPLANATION OF THE ABOVE MESSAGES.

DISK DUMP:

1. SELECT A DISK PACK TO BE USED AS THE DUMP VOLUME.
NOTE THAT THE IPL TEXT ON THE PACK WILL BE REPLACED BY THE DUMP IPL TEXT. THE SELECTED PACK CANNOT BE A SYSTEM RESIDENCE VOLUME.
2. BEFORE YOU CAN EXECUTE DOSVSDMP, THE FILE WHICH IS TO HOLD THE DUMP OUTPUT MUST BE ALLOCATED ON THE SELECTED VOLUME. THIS FILE MUST BE NAMED DOSDMPF, AND BEGIN AND END ON A CYLINDER BOUNDARY. THE SIZE OF THE FILE IS CALCULATED USING THE FOLLOWING FORMULA:

FOR CKD DEVICE:

$$N = 2 + (V+R) / T$$

FOR AN FBA DEVICE USING BLOCKS OF 512 BYTES IN LENGTH:

$$N = 4 (7 + (V+R) (1 + 1/256))$$

DOSVSDMP AND STAND-ALONE DUMP (. . . Cont'd)

EXAMPLE FOR JOB CONTROL (. . . . Cont'd)

Where

N = IS THE NUMBER OF REQUIRED TRACKS FOR A CKD DEVICE AND THE NUMBER OF BLOCKS FOR AN FBA DEVICE.

V = IS THE NUMBER OF PAGES IN THE VIRTUAL ADDRESS AREA.

R = IS THE NUMBER OF PAGES IN THE REAL ADDRESS AREA.

T = 3 FOR A VOLUME ON A 2314 (2319) OR 3340
 6 FOR A VOLUME ON A 3330
 8 FOR A VOLUME ON A 3350

THE RESULT N MUST BE ROUNDED TO THE NEXT HIGHER NUMBER OF TRACKS EQUIVALENT TO THE NEXT WHOLE NUMBER OF CYLINDERS.

EXAMPLE:

3. EXECUTE DOSVSDMP

```
// JOB
// ASSGN SYS006, 132
// DLBL DOSDMPF, 'FILENAME'
// EXTENT SYS006, BALANCE OF EXTENT INFORMATION
// EXEC DOSVSDMP
/&
```

4. WHEN MESSAGE 4C50D IS ISSUED, REPLY: 1,6

(1 CREATE DOSMPF) (6 EOJ DEFAULT)

5. MESSAGE 4C79 I INDICATES THAT CREATION OF THE DUMP PROGRAM DISK IS COMPLETED.

REFER TO VSE/AF2 MESSAGES FOR AN EXPLANATION OF THE ABOVE MESSAGES.

DISKETTE OR IN CARDS

ASSIGN SYS006 TO A DISKETTE OR A CARD UNIT. THIS CAUSES PROGRAM DOSVSDMP TO PROMPT YOU FOR THE DESIRED OUTPUT MODE AS SHOWN.

PROMT MESSAGE

```
XX4C51D  SELECT YOUR OPTION BY NUMBER
1 cuu    PRINTER ADDRESS (DEFAULT IS 1=00E)
2 INTERRUPT      3 EOJ
```

EXAMPLE JOB CONTROL: DISKETTE AND CARDS

DISKETTE DUMP:

1. EXECUTE DOSVSDMP:

```
// JOB
// ASSGN SYS006, 04F
// DLBL DOSDMPF, 'DATA', 77/001, DU
// EXTENT SYS006
// EXEC DOSVSDMP
/&
```

CARD DUMP:

1. EXECUTE DOSVSDMP:

```
// JOB
// ASSGN SYS006, 00D
// EXEC DOSVSDMP
/&
```

EXECUTING THE STAND-ALONE DUMP PROGRAM

THE PROGRAM IS ACTIVATED VIA AN IPL OF THE TAPE, DISK, DISKETTE OR CARD-READER CONTAINING THE DUMP PROGRAM. THE IPL PROCEDURE LOADS THE PROGRAM INTO AND OVERLAYS STORAGE LOCATIONS X'A00' TO X'AFF'. ONCE LOADED, THE PROGRAM PROCEEDS TO WRITE OUT STORAGE IN VIRTUAL PAGE ORDER. FOLLOWING THE VIRTUAL STORAGE DUMP, OR AS A RESULT OF AN ERROR IN ATTEMPTING TO DUMP VIRTUAL STORAGE, A DUMP OF REAL STORAGE IN REAL PAGE ORDER IS TAKEN. UPON COMPLETION OF THE DUMP MESSAGE DOSVSDMP COMPLETE IS ISSUED AND THE SYSTEM IS PLACED IN THE WAIT STATE WITH A COMPLETION CODE IN BITS 48 TO 63 OF THE CURRENT PSW.

DOSVSDMP AND STAND-ALONE DUMP (. . . Cont'd)

PRINTING THE STAND-ALONE DUMP OUTPUT

FOR PRINTING THE STAND-ALONE DUMP OUTPUT, THE PROGRAM REQUIRES AT LEAST 40 K OF STORAGE, NOT INCLUDING THE SIZE OF THE SUPERVISOR.

EXAMPLE FOR JOB CONTROL: PRINTING FROM DISK

```
1. EXECUTE DOSVSDMP:
   // JOB
   // ASSGN SYS006,DEVICE
   // DLBL DOSDMPF, 'FILENAME'
   // EXTENT SYS006, BALANCE OF EXTENT INFORMATION
   // EXEC DOSVSDMP
   /&
```

2. WHEN MESSAGE XX4C50D IS ISSUED, REPLY: 2
(2 PRINT DUMP)

3. WHEN MESSAGE XX4C52D IS ISSUED, REPLY:
SELECT YOUR DUMP(S) BY NUMBER.

PROMPT MESSAGE

```
XX 4C50D SELECT YOUR OPTION BY THE CORRESPONDING NUMBER
1 CREATE DOSDMPF      2 PRINT DUMP      3 PRINT SDAID TAPE
4 PRINT FILE         5 INFORMATION     6 EOJ (DEFAULT)
7 CREATE DOSDMPG     8 CLR DOSDMPF     9 CLR DOSDMPG
```

2 ← OPERATOR'S RESPONSE

PROMPT MESSAGE

```
XX 4C52D SELECT YOUR DUMP(S) BY NUMBER
1 SUPVR  2 VIRT (DEFLT)  3 REAL      4 FORMATTED
5 SVA    6 BG OR F1 ETC  7 ADDR-ADDR  8 FORCE DUMP
9 EOJ    EXAMPLE: 5,6 BG,6 F1,7 0-37FF,8  E End of Select
```

1, 6 F2, 4, 8 ← OPERATOR'S RESPONSE

↑ ↑ ↑ | IF YOU SELECT MORE THAN ONE OPTION, THESE
↑ ↑ ↑ | OPTIONS MUST BE SEPARATED FROM EACH OTHER BY
↑ ↑ ↑ | A COMMA WITH NO PRECEDING BLANK.

BRIEF EXPLANATION OF POSSIBLE DUMP OPTIONS:

- 1—PRINT THE CONTENTS OF THE SUPERVISOR.
- 2—PRINT THE CONTENTS OF ALL OF VIRTUAL STORAGE (THIS IS THE DEFAULT IF NO DUMP OUTPUT OPTIONS ARE SPECIFIED; THAT IS, IF YOU RESPOND BY SIMPLY PRESSING END/ENTER.
- 3—PRINT THE CONTENTS OF PROCESSOR (REAL) STORAGE (APPLIES ONLY TO DOS/VSE IN 370 MODE).
- 4—FORMAT AND PRINT DOS/VSE CONTROL BLOCKS.
- 5—PRINT THE CONTENTS OF THE SVA.
- 6—PRINT THE CONTENTS OF THE SPECIFIED PARTITION(S).
- 7—PRINT THE CONTENTS OF ONE OR MORE (UP TO EIGHT) AREAS OF VIRTUAL STORAGE AS DEFINED BY PAIRS OF ADDRESSES SPECIFIED IN RESPONSE IN SUCCESSIVE PROGRAM PROMPTS. THESE ADDRESSES MUST BE SPECIFIED IN HEXADECIMAL NOTATION. IF YOU SPECIFY, FOR EXAMPLE
7 2001F-20 300
THE PROGRAM PRINTS THE CONTENTS OF ONE PAGE OF VIRTUAL STORAGE FROM 200 00 to 207FF) BECAUSE PRINTING FOR AN ADDRESS PAIR ALWAYS BEGINS AT THE NEXT LOWER 2K BOUNDARY OF THE ADDRESS SPECIFIED FIRST AND ENDS WITH THE NEXT HIGHER 2K BOUNDARY OF THE ADDRESS SPECIFIED LAST. IF YOU SPECIFY 2K BOUNDARIES, PRINTING STARTS AND ENDS ON THE SPECIFIED BOUNDARIES.
- 8—FORCES THE DUMP FROM THE MEDIUM TO THE PRINTER IN THE FORM IN WHICH IT WAS TAKEN.
- E—INDICATES TO DOSVSDMP THAT YOU HAVE FINISHED SELECTING DUMP OUTPUT OPTIONS.

PROMPTS AND RESPONSES FOR PRINTING FROM TAPE OR DISK.
FOR DETAILS REFER TO VSE/AF2 SERVICEABILITY AIDS AND
DEBUGGING PROCEDURES.

DOSVS DMP HARD WAIT CODES

The following wait state codes appear in the address portion of the current PSW when the stand-alone dump program (DMPROG) terminates. The codes are shown here as they would appear in the right half of the current PSW when displayed using the ALTER/DISPLAY function.

Hard Wait Codes (Hex)	Explanation
00CE 0001	This indicates an I/O error occurred after a start was issued on the dump device.
00CE 0002	The dump device is not operational.
00CE 0003	A channel error was detected on the dump device.
00CE 0004	A permanent I/O error was detected on the dump device. The original error was re-tried and found to be irrecoverable.
00CE 0005	An I/O error was detected during error recovery processing. This indicates an error other than the one for which error recovery is being tried.
00CE 0006	A machine check occurred.
00CE 0007	An I/O error was detected during the IPL procedure.
00CE 0008	The disk dump file (DOSDMPF) extent has been exceeded.
0000 AAAA	A program check occurred during IPL.
0000 FFFF	The dump has ended successfully.

MAINTAIN SYSTEM HISTORY PROGRAM

TABLE OF CONTENTS

General Information

The Purpose of MSHP	V-29
Installation Support by MSHP	V-29
The Need for a System History	V-29
Storage Requirements of MSHP	V-29
MSHP Processing Overview	V-29
The History Files	V-30
Description of number Symbols (Table 1)	V-30
Requirements of Logical unit assignment for MSHP Installation jobs (Table 2)	V-30
Rec. Size of Extents for the History File (Table 3)	V-30
Use of LIBDEF Statement	V-31
MSHP SUPPORT of CONCATENTED LIBRARIES	V-31

Installation Activities

Install System ONLINE	V-32
Prepare for Tapeless Configuration (New System)	V-32
Save your current System History File	V-32
Obtain an Installation Verification List	V-32

Procedure 1. New System to New Sysres from Tape V-33

Step 1 Restore the Distribution Tape to Disk	V-33
Step 2 System Generation Activities	V-33
Step 3 Merge user Program	V-34
Step 4 Copy the history file to the New Sysres	V-34
Step 5 IPL	V-34
Step 6 Personalize the System History	V-35
Step 7 Backup the System	V-35

Procedure 2. New System to New Sysres from DISK V-35

Standalone Procedure	V-35
Restore the Distribution Tape to DISK	V-35
Examples Restore System (Standalone)	V-36, V-37
Prepare for Tapeless Configuration (Component)	V-38
A. Install total Component to Sysres	V-38
Installation FROMTAPE	V-38
Installation FROMDISK	V-39
B. Install total Component to Private Libraries	V-40
1. Install to New Private Libraries	V-40
Install Component FROMTAPE Attach	V-40
Install Component FROMDISK Attach	V-40
2. Install to Existing Private Libraries	V-41
Install Component FROMTAPE Merge	V-41
Install Component FROMDISK Merge	V-42
C. Install Part Component to Sysres	V-42
Step 1. Install Base Part FROMTAPE (or FROMDISK)	V-42, V-43
Step 2. Install Second Part FROMTAPE (or FROMDISK)	V-43
D. Install Part Component to New Private Libraries	V-44
Step 1. Install Base Part FROMTAPE Attach (or FROMDISK)	V-44
Step 2. Install Second Part FROMTAPE Attach (or FROMDISK Merge)	V-44, V-45
E. Install Part Component to Existing Private Libraries	V-45
Step 1. Install Base Part FROMTAPE Merge (or FROMDISK)	V-45, V-46
Step 2. Install Second Part FROMTAPE Merge (or FROMDISK)	V-46, V-47
F. Install a Component in SYSIN Format	V-47
G. Install a Feature to SYSRES	V-47
Step 1. Install the Feature FROMTAPE	V-47
-- DOWNLEVEL PROBLEM	V-48
Step 2. Update Feature Libraries	V-48, V-49
Step 3. Install Updated Feature Libraries	V-49
Step 1. Install the Feature FROMDISK	V-50
Step 2. Update Feature Libraries	V-50
Step 3. Install Updated Feature Libraries	V-50
H. Install a Feature to Private Libraries	V-50
Step 1. Install the Feature FROMTAPE	V-50, V-51
Step 2. Update Feature Libraries	V-51
Step 3. Install Updated Feature Libraries	V-52

Table of Contents (.... Cont'd)

Step 1. Install the Feature FROMDISK	V-52
Step 2. Update Feature Libraries	V-53
Step 3. Install Updated Feature Libraries	V-53
I. Install a Release 34 Component	V-53
<u>Service Activities (JOB EXAMPLES)</u>	
S1. Apply a single PTF	V-53
S2. Apply cumulative PTFs	V-54
S3. Apply corequisite PTFs supplied on cards or cumulative PTF tape.	V-54, V-55, V-56, V-57
S4. Apply, Record, and Remove Local and APAR Fixes	V-57
Correct statement and its requirements.	V-57
S4.1 Corrections to the Core Image Library	V-57
S4.2 Corrections to the Relocatable Library	V-58
S4.3 Corrections to the Source Statement Library (E.macros)	V-58, V-59
S4.4 Corrections to the Source Statement Library (A.macros)	V-59
S4.5 Correct the Invalidation of a Recorded Fix.	V-59, V-60
S.5 Apply PTFs of the DOS/VS Release 34 Format	V-60
• Apply a Single PTF from Card, Magnetic Tape, Disk or Diskette	V-61
• Apply Cumulative PTFs from Magnetic Tape or Disk	V-61, V-62
<u>MSHP Control Statements</u>	
Notational Conventions	V-62, V-63
MSHP Logical Unit Assignments (Table 4 and 4.1)	V-64, V-65
Interrelationship of Function and Detail Control Statements	V-65
Function Control Statements	V-66
ACCEPT	V-66
ARCHIVE	V-67
BACKUP	V-68
COPY	V-69
CORRECT	V-69
CREATE	V-70
DUMP	V-70
INCORPORATE	V-70
INSTALL	V-71
LIST	V-72
LOOKUP	V-72, V-73
PERSONALIZE	V-74
REMOVE	V-75
RESIDENCE	V-75
RESTORE	V-76
RETRACE	V-77
REVOKE	V-77
SELECT	V-78
UNDO	V-79
UPGRADE	V-79, V-80, V-81
Detail Control Statements	
AFFECTS	V-81
ALTER	V-82
DEFINE	V-83, V-84, V-85
DELETE	V-86
INSERT	V-86
PTF	V-86
REJECT	V-87
REPLACE	V-88
VERIFY	V-88

MAINTAIN SYSTEM HISTORY PROGRAM

THE PURPOSE OF MSHP

MSHP, an integral part of the DOS/VSE System Control Programming (DOS/VSE SCP), or VSE/AF provides functions to:

- Install programming support.
- Apply corrections to existing programming support.
- Record installation and service activities in a system history file in order to reflect the current status of your operational system.
- Automatically compare an operational system's history with IBM-supplied information on requirements for installing additional programming support or applying corrections to the installed programming support.
- Print various types of listings based on your system's history.

For an effective system service, it is important to use the functions available through MSHP. Function Control Statements and Detail Control Statements not described in this Handbook are for internal use of IBM Software Support Personnel.

INSTALLATION SUPPORT BY MSHP

IBM program packages are designated as:

- System (for example, VSE/AF)
- Product (for example, System Installation Productivity Offering)
- Component (for example, DOS/VS RPG II)
- Feature (for example, VSE/Power RJE)

You are informed in the transmittal letter of the type of programming support the shipment contains. Proceed with the installation in accordance with the applicable MSHP procedure provided in this Handbook.


THE NEED FOR A SYSTEM HISTORY

For an efficient and successful installation of a program package, it is essential that the history file of your operational system truly reflects the status of the system, and that prerequisite programming support requirements are met.

STORAGE REQUIREMENTS OF MSHP

512K bytes minimum partition size and 90K bytes of partition GETVIS.

MSHP Processing Overview



MSHP (.... Cont'd)

The HISTORY FILES

MSHP uses two types of history files:

- The System History File
- The Auxiliary History File

The system history file is part of the IBM-distributed system and is maintained under the file name IJSYSHF on the logical unit SYSREC. The file should be defined by a permanent entry in the system standard label area:

```
// DLBL IJSYSHF,'VSE.SYSTEM.HISTORY.FILE'99/365
// EXTENT SYSREC,serial-number,1,0,relative track,number of tracks
```

The auxiliary history file is maintained under the file name IJSYS02 on the logical unit SYS002. If an auxiliary history file is carried over from ohne system to another code the following MSHP control statements to have MSHP create label definitons in the label area:

```
DEFine History EXTent=number1:number2 Unit=SYSnnn –
ID='VSE.AUXILIARY.HISTORY.FILE'
```

DESCRIPTION OF NUMBER SYMBOLS:

Throughout installation and service jobs symbols are used for which you must supply the values. These symbols are:

number1 = The number of the start-track/block relative to zero for a private library or a history file.

number2 = the number of tracks/blocks to be reserved for:

- extent in the label definition (in the case of private libraries)
- restoring of libraries (system or private)
- extent for the history file

number3 = the number of tracks/blocks to be allocated for the library directory

Table 1

MSHP Function	Requirements of Logical Unit assignment for MSHP Installation jobs																		
	SYS...																		
	LNK	000	001	002	003	004	005	006	007	008	009	mmm	nnn	CLB	RLB	SLB	PCH	LST	
BACKUP SYSTEM								M						S					M
AUXILIARY				X2								X1		S					
INSTALL FROMTAPE SYSTEM				X2					M			X1		S					M
PERSONALIZE														S					M
RESTORE SYSTEM									M					S					M
AUXILIARY				X2								X1		S					
COPY SYSTEM														S					M
AUXILIARY				X2								X1		S					

M = mandatory
S = mandatory if the logical unit SYSnnn has been specified in a DEFINE HISTORY SYSTEM statement
X1 = mandatory if the logical unit SYSmmm has been specified in a DEFINE HISTORY AUXILIARY statement
X2 = mandatory if the logical unit SYSmmm has NOT been specified in a DEFINE HISTORY AUXILIARY statement
mmm = any number from 000 to 254
nnn = any number from 000 to 254, but not the same as for mm if both mm and nnn are required

Table 2

Device	Rec. Size of Extents for the Hist. File	
	In Cylinders	In Tracks
2314	4	80
3330	2	38
3340	6	72
3350	1	30
	In Blocks	
FBA	900	

Table 3

MSHP (.... Cont'd)

Use of LIBDEF statement

Throughout this chapter, ASSGN statements are used for private libraries. LIBDEF statements may be used instead of ASSGN SYSxLB statements, providing that the MSHP-affected TO and FROM libraries and the first SEARCH library relate to the same library. It is possible, however, to use an assign statement for one library type and a LIBDEF statement for another library type in the same job. For information on the LIBDEF control statement, refer to VSE/Advanced Functions System Management Guide and VSE/Advanced Functions System Control Statements.

MSHP SUPPORT OF CONCATENATED LIBRARIES

During installation of a component or a feature (via INSTALL or INCORPORATE), the 44-Byte file-ID of the libraries, into which the component/feature is installed (SL, RL, CL) are chained to the component entry in the MSHP history file. If the installation is done with the option 'ATTACH' the user-specified ID's from the DEFINE command are taken.

In case of a INSTALL SYSTEM, all components and all libraries will get the default Identifier 'DOS.SYSRES.FILE', or the identifier found in the MSHP DEFINE command of the respective Installation job, which the user may specify.

If the user prefers to use a file-ID like 'VSE.SYSRES.FILE' as applied throughout the Installation examples in this Handbook he has the choice either to:

- change the default ID 'DOS.SYSRES.FILE' with the new RESIDENCE command to 'VSE.SYSRES.FILE' after installation
- or use DEFINE statements with the ID='VSE.SYSRES.FILE' in his installation job.

Note: The user has also to correct/change the file-IDs used in the DLBL Statement of his standard labels.

Restriction: The MSHP Install procedure processes only Backup-tapes of a system or Component(s) which are created with ,normal' DLBL- and Extent-statements in effect for the library(ies) to be backedup.

MSHP (. . . Cont'd)

INSTALLATION ACTIVITIES

Install System Online

Online installation can be done only under the control of an operational DOS/VSE or VSE/AF that includes MSHP and a current system history.

Prepare for Tapeless Configuration (New System)

This procedure may be used to produce, from the IBM-supplied magnetic tape that contains VSE/AF, a disk volume that can then be used to install the system from disk.

```
// JOB RESTORE DISTRIBUTION TAPE
// ASSGN SYS006,cuu           Input unit for distribution tape
// ASSGN SYS005,cuu           Disk pack
// DLBL IJSYRS,'VSE.SYSRES.FILE',99/365,SD
// EXTENT SYSRES,SYSRES,...
// EXEC RESTORE
  ALLOC CL=ccc(tt),RL=ccc(tt),SL=ccc(tt),PL=ccc(tt)
/*
// ASSGN SYS002,cuu           History file space
// EXEC MSHP
RESTORE HIST AUX
DEF HIST AUX EXT=number1:number2  - History file copy on disk
  ID='VSE.SYSTEM.HISTORY.FILE'  UNIT=SYS002
/*
/&
```




Figure 1. Prepare for Tapeles Configurations (NEW SYSTEM)

Save Your Current System History File

It is recommended to keep a copy of the current system history file for future control purposes; you may use the BACKUP or the COPY function of MSHP. The following is an example job.

```
// JOB SAVE HISTORYFILE
// EXEC MSHP
COPY HISTORY SYSTEM AUXILIARY
DEFINE HIST AUX EXT=number1:number2 ID='AUX.HIST.FILE'
/*
/&
```

Obtain an Installation Verification List

To obtain the printout (on SYSLST), execute:

```
// JOB RETRACE
// EXEC MSHP
RETR           If a system overview is desired
RETR COMP     If a retrace on components is desired
RETR FEAT     If a retrace on features is desired
/*
/&
```

MSHP (. . . . Cont'd)

INSTALLATION ACTIVITIES (. . . . Cont'd)

PROCEDURE 1. NEW SYSTEM TO NEW SYSRES FROM TAPE

Step 1. Restore the Distribution Tape to Disk

Mount the IBM-supplied distribution tape on the device assigned to SYS006. Then execute the following job in a partition that is allocated 602K bytes. (Partition + 90 K Bytes GETVIS)

```
// JOB INSTALL NEW SYSTEM
// ASSGN SYS006,cuu           Distribution tape
// ASSGN SYS005,cuu           Disk for new SYSRES
// ASSGN SYS002,cuu           Auxiliary history file
// ASSGN SYS007,UA
// ASSGN SYS008,UA
// ASSGN SYS009,UA
// EXEC MSHP,SIZE=512K
INSTALL SYSTEM FROMTAPE
DEF CL SYS EXT=:number2 DIR=number3
DEF RL SYS EXT=:number2 DIR=number3
DEF SL SYS EXT=:number2 DIR=number3
DEF PL SYS EXT=:number2 DIR=number3
DEF LABELAREA EXT=:number2
DEF HIST AUX EXT=:number1:number2 -
    ID='VSE.AUX.HISTORY.FILE'    U=SYS002
/*
/;&
```

Note: For description of number symbols refer to table 1




Figure 2. INSTALL SYSTEM FROMTAPE ATTACH

On completion of Step 1:

- The system libraries have been restored from the distribution tape to the disk assigned as the new SYSRES volume.
- The history file supplied on the distribution tape has been restored to the auxiliary history file (assigned as SYS002) on the disk assigned as the new SYSRES volume; the history file of your current system now reflects the status of the new system merged with the old system; the components of the old system are flagged as obsolete.

Step 2. System Generation Activities:

This step consists of a number of system generation activities such as:

- Assemble and catalog the SUPERVISOR
- Delete unwanted components (see Note below)
- Assemble and catalog I/O modules

Note:

If a delete procedure deletes only part of a component, that component's entry is not removed from the history file. For details or system generation activities, refer to VSE/AF System Generation.

MSHP (. . . Cont'd)

INSTALLATION ACTIVITIES (. . . Cont'd)

Step 3. Merge user Program

This step may be used to merge user and other programs (for example, licensed IBM programs) from the current system to the new SYSRES.

```
// JOB MERGE RES TO NRS
// ASSGN SYS002,cuu
// DLBL IJSYSRS,'VSE.SYSRES.FILE'
// EXTENT SYS002,VOLIDn,1,0,nnnn,nnnn
// EXEC CORGZ
  MERGE RES,NRS
  COPYC NEW
  COPYR NEW
  COPYS NEW
  COPYP NEW
/*
/ &
```

The COPY NEW Function copies only those members that do not already exist in the receiving Library.




Figure 3. MERGE RES TO NRS AND COPY SYSTEM HISTORY

Step 4. Copy the history file to the NEW SYSRES

The updated system history file from the old pack (RES) is copied to the new SYSRES pack (NRES) and obsolete entries are removed by the following job example:

```
// JOB COPY SYSTEM HISTORY
// ASSGN SYS002,cuu
// EXEC MSHP
  REM OBSOLETE
  COPY HISTORY SYSTEM AUXILIARY
  DEFINE HISTORY AUXILIARY EXTENT=number1:number2 –
    ID='VSE.SYSTEM.HISTORY.FILE' UNIT=SYS002
/*
/ &
```

Step 5.IPL

5.1. IPL from the new system.

5.2. Apply standard labels to the system

If IBM standard labels are not used the following statements should be contained in the label-job:

```
// DLBL IJSYSHF,'VSE.SYSTEM.HISTORY.FILE',99/365,SD (see Note 1)
// EXTENT SYSREC,SYSRES,1,0,number1,number2 (see Note 2)
```

Note 1:

The label information must be identical with the ID specification given in STEP 4.

Note 2:

number 1, number 2 in the EXTENT statement must be identical with number 1:number2 of the extent specified in the DEFINE statement of STEP 4.

5.3. ENTER the command SET RF=CREATE

MSHP (. . . Cont'd)

INSTALLATION ACTIVITIES (. . . Cont'd)

Step 6. Personalize the System History

```
// JOB PERSONAL
// EXEC MSHP
PERS 'Company name' –
ADDR='Location' –
PHONE='Extension' –
PROG='Programmer's name' –
ENV='Environment'
/*
/ &
```

This function updates the newly installed history file header records. The PERSONALIZE function may be used to change any information contained in the header records. MSHP updates the field(s) selected by the PERSONALIZE keyword operands.

Step 7. BACKUP the System

```
// JOB BACKUP
// ASSGN SYS006,cuu                               Tape
// ASSGN SYS005,cuu                               New SYSRES
// DLBL IJSYSRS,'VSE.SYSRES.FILE'
// EXTENT SYS005
// EXEC BACKUP
SA                                                  Standalone restore
/*
/ &
```

For the standalone restore Job, refer to VSE/AF System Generation.

PROCEDURE 2: NEW SYSTEM TO NEW SYSRES FROM DISK

This procedure is identical to procedure 1 except that in Step 1 (as shown in procedure 1) you

- Omit the assignments for SYS005 and SYS006
- Code FROMDISK (instead of FROMTAPE) in the MSHP INSTALL statement.
- Omit the Library definitions for CL, RL, SL, and PL.
- Omit the define statement for the label area.
- In the define statement for the auxiliary history file, use the ID provided on the PID volume or an ID according to you requirements.

STANDALONE PROCEDURE

Restore the Distribution Tape to Disk

The distribution tape contains, besides the system libraries and the system history file, a stand-alone supervisor and various standalone utilities; the logical arrangement is as follows:

- File 1 contains the DSF standalone utility with the functions INIT, INSPECT, REFORMAT, and ANALYZE. These functions are for use in conjunction with CKD devices except for the ANALYZE function which is also for use with FBA devices.
- File 2 contains the VSE/Advanced Functions standalone supervisor for the execution of the VSE/Advanced Functions standalone utilities.
- File 3 contains the standalone utilities:

```
INITDISK      ]
INITEM        ]   for FBA devices
SURFANAL      ]
RESTORE       ]
FASTCOPY      ]   for CKD and FBA devices
```

To restore the library contents of the distribution tape to the initialized disk, use the RESTORE function of DSF.

Mount the IBM supplied distribution tape and perform IPL from this tape. For information on the IPL steps (up to reaching the WAIT state), refer to the applicable IPL procedure in VSE/Advanced Functions Operating Procedures.

MSHP (.... Cont'd)

INSTALLATION ACTIVITIES (.....Cont'd)

When the System has entered the WAIT state:

- IPL again from the distribution tape This loads file 2
- Press END/ENTER/REQ
- Press EOB if you do not want a listing. If you want a listing, specify address and type of printer.
- Press EOB if the printer buffer is not, or is incorrectly loaded.

The system prompts you for the date, then prompts you to specify the function to be executed. Now continue with the RESTORE Example.

Example Restore System

This example shows the prompts and possible responses to the prompts.

```

SPECIFY ONE OF THE FOLLOWING COMMANDS:
FASTCOPY, INITDISK, RESTORE, INITEM, SURFANAL, END
restore
SPECIFY ADDRESS OF INPUT DEVICE CUU
280
SPECIFY TYPE OF INPUT DEVICE XXXXY
3240T9
INVALID TYPE SPECIFICATION, PLEASE REENTER
FOLLOWING VALUES ARE ACCEPTED:
8809 2400T9 2400T7 3410T9 3410T7 3420T9
3420T9
SPECIFY ADDRESS OF SYSRES DISK CUU OR EOB
(PRESS EOB, IF ONLY PRIVATE LIBRARIES ARE TO BE RESTORED)
137
SPECIFY TYPE OF DISK XXXXY
3330
ANY PRIVATE LIBRARY TO BE RESTORED ? YES / NO
no
8R43D TYPE NOVERIFY OR PRESS ENTER FOR WRITE VERIFICATION
noverify
8R58A ORIGINAL ALLOCATION FOR ALL LIBRARIES?
REPLY YES OR NO (END/ENTER MEANS YES)

no
8R01D *** GIVE SYSTEM LIBRARY ALLOCATIONS ***
8R03I DEFAULT ALLOCATION FOR SC 43 (9)
CL=
69(12)
8R03I DEFAULT ALLOCATION FOR SR 64(5)
RL=
85(20)
8R03I DEFAULT ALLOCATION FOR SS 61(2)
SL=
96(03)
8R03I DEFAULT ALLOCATION FOR SP 2(2)
PL=
4(02)
8R48I DEFAULT FILE-ID IS A5746XE9.SYSRES.FILE (PID supplied ID)
8R12D TYPE DESIRED LABEL FOR LIBRARY
LABEL=
8R14I FILE ID = A5746XE9.SYSRES.FILE
8R15D TYPE GO IF ALLOCATION IS CORRECT
go
8R19I EQUAL FILE ID IN VTOC
A5746XE9.SYSRES.FILE
8R20D TYPE DELETE OR GIVE A NEW FILE ID
delete
8R14I FILE ID = A5746XE9.SYSRES.FILE
8R13I EXTENT = TRK 1 – TRK 3267
8R35I RESTORE OF SC LIBRARY IN PROGRESS
8R36I RESTORE HAS BEEN SUCCESSFUL
8R35I RESTORE OF SR LIBRARY IN PROGRESS
8R36I RESTORE HAS BEEN SUCCESSFUL
8R35I RESTORE OF SS LIBRARY IN PROGRESS
8R36I RESTORE HAS BEEN SUCCESSFUL
8R35I RESTORE OF SP LIBRARY IN PROGRESS
8R36I RESTORE HAS BEEN SUCCESSFUL
8R37I *** SYSRES RESTORED ***
8R38I *** RESTORE COMPLETE ***
*** END OF STAND ALONE PROCESSING ***
    
```

MSHP (. . . . Cont'd)

INSTALLATION ACTIVITIES (. . . . Cont'd)

The following steps may be performed after the STANDALONE RESTORE is completed:

- IPL from NEW SYSTEM
- APPLY LABELS30 INCLUDING FJSYSHF'VSE.SYSTEM.HISTORY.FILE'
- ENTER SET RF=CREATE

RESTORE HISTORY FROM DISTRIBUTION TAPE

```
// JOB RESTORE SYS HISTORY
// ASSGN SYS006,nnn                DISTR.TAPE
// EXEC MSHP
RESTORE HISTORY SYSTEM
/*
// MTC RUN,SYS006
/*
/;&
```

PERFORM SYSGEN STEPS

- Delete UNWANTED components
- Assemble and catalog your own SUPVR
- Correct your standard labels
- Build your ASI Procedure(s) and catalog it (them)
- Personalize your SYSTEM HISTORY FILE
- BACKUP your System
- RESTORE your System
- Include User Programs and LP's
- Perform DSERV and LSERV

MSHP (. . . Cont'd)

INSTALLATION ACTIVITIES (. . . Cont'd)

Prepare for Tapeless Configuration (Component)

This procedure may be used to produce, from the IBM-supplied magnetic tape a disk volume that can then be used to install the component from disk.

```
// JOB RESTORE DISTRIBUTION TAPE
// ASSGN SYS006,cuu           Input unit for distribution tape
// ASSGN SYS007,cuu           Output unit for PCL
// ASSGN SYS008,cuu           Output unit for PRL
// ASSGN SYS009,cuu           Output unit for PSL
// ASSGN SYS002,cuu           Auxiliary history file
// EXEC MSHP
RESTORE DTAPE
DEF CLIB PRIV EXT=number1:number2 DIR=number3
DEF RLIB PRIV EXT=number1:number2 DIR=number3
DEF SLIB PRIV EXT=number1:number2 DIR=number3
DEF HIST AUX EXT=number1:number2 U=SYS002
/*
/&
```

} For description of number-symbols
reference table 1




Figure 4. PREPARATION FOR COMP INST.

A. INSTALL TOTAL COMPONENT TO SYSRES

To install from tape, use the following job:

```
// JOB INSTALL COMPONENT FROM TAPE
// ASSGN SYS006,cuu           Distribution tape
// ASSGN SYS007,cuu           Output unit for PCL
// ASSGN SYS008,cuu           Output unit for PRL
// ASSGN SYS009,cuu           Output unit for PSL
// ASSGN SYS002,cuu           Auxiliary history file
// OPTION CATAL
// EXEC MSHP
INST COMP FROMTAPE MERGE
DEF CLIB PRIV EXT=number1:number2 DIR=number3
DEF RLIB PRIV EXT=number1:number2 DIR=number3
DEF SLIB PRIV EXT=number1:number2 DIR=number3
DEF HIST AUX EXT=number1:number2 U=SYS002
/*
/&
```

} For description of number symbols
reference table 1

On completion of this step (and after check and verification procedures are satisfied), the IBM-supplied total component is part of the current system library, and the history file of the total component is part of the current history file.

MSHP (.... Cont'd)

A. INSTALL TOTAL COMPONENT TO SYSRES (.....Cont'd)




Figure 5. INSTALL TOTAL COMPONENT FROMTAPE TO SYSRES

To install from disk, use the following job:

```
// JOB INSTALL COMPONENT FROM DISK
// ASSGN SYS003,cuu
// ASSGN SYS001,cuu
// ASSGN SYS000,cuu
// ASSGN SYS002,cuu
// OPTION CATAL
// EXEC MSHP
INST COMP FROMDISK MERGE
DEF CLIB PRIV ID='pid supplied id'
DEF RLIB PRIV ID='pid supplied id'
DEF SLIB PRIV ID='pid supplied id'
DEF HIST AUX EXT=number1:number2 ID='pid supplied id' U=SYS002
/*
/ &
```

From-unit for CORZG PCL distribution disk
 From-unit for CORZG PRL distribution disk
 From-unit for CORZG PSL distribution disk
 Auxiliary history file distribution disk

On completion of this step the IBM-supplied total component is part of the current system library, and the history file of the total component is part of the current system history file.




Figure 6. INSTALL TOTAL COMPONENT FROMDISK TO SYSRES

MSHP (. . . Cont'd)

B. INSTALL TOTAL COMPONENT TO PRIVATE LIBRARIES

1. INSTALL TO NEW PRIVATE LIBRARIES

To install from tape, use the following job:

```
// JOB INSTALL COMPONENT FROM TAPE
// ASSGN SYS006,cuu           Distribution tape
// ASSGN SYS007,cuu           Output unit for PCL
// ASSGN SYS008,cuu           Output unit for PRL
// ASSGN SYS009,cuu           Output unit for PSL
// ASSGN SYS002,cuu           Auxiliary history file
// EXEC MSHP
INST COMP FROMTAPE ATTACH
DEF CLIB PRIV EXT=number1:number2 DIR=number3 ID='NEW.PCL'
DEF RLIB PRIV EXT=number1:number2 DIR=number3 ID='NEW.PRL'
DEF SLIB PRIV EXT=number1:number2 DIR=number3 ID='NEW.PSL'
DEF HIST AUX EXT=number1:number2 U=SYS002
/*
/ &
```

} For description of number symbols reference table 1




Figure 7. INSTALL TOTAL COMPONENT FROMTAPE TO NEW PRIV. LIBRARIES

To install from disk, use the following job:

```
// JOB INSTALL COMPONENT FROM DISK           Auxiliary history file
// ASSGN SYS002,cuu
// EXEC MSHP
INST COMP FROMDISK ATTACH
DEF CLIB PRIV ID='pid supplied id'
DEF RLIB PRIV ID='pid supplied id'
DEF SLIB PRIV ID='pid supplied id'
DEF HIST AUX EXT=number1:number2 ID='pid supplied id' -
U=SYS002
/*
/ &
```




Figure 8. INSTALL TOTAL COMPONENT FROMDISK WHICH WILL BECOME THE NEW PRIV. LIBRARY

MSHP (. . . Cont'd)

2. INSTALL TO EXISTING PRIVATE LIBRARIES

To install from tape, use the following job:

```
// JOB INSTALL TOTAL COMPONENT FROM TAPE
ASSGN SYSCLB,cuu
// ASSGN SYSRLB,cuu
// ASSGN SYSSLB,cuu
// ASSGN SYS006,cuu
// ASSGN SYS007,cuu
// ASSGN SYS008,cuu
// ASSGN SYS009,cuu
// ASSGN SYS002,cuu
// OPTION CATAL
// EXEC MSHP
INST COMP FROMTAPE MERGE
DEF CLIB PRIV EXT=number1:number2 DIR=number3 ID='MSHP.PRIV.CLIB'
DEF RLIB PRIV EXT=number1:number2 DIR=number3 ID='MSHP.PRIV.SLIB'
/*
ASSGN SYSCLB,UA
/ &
```

Existing private libraries

Distribution tape
Output unit for PCL
Output unit for PRL
Output unit for PSL
Auxiliary history file

For description of number symbols reference table 1

On completion of this step, the component is on the private libraries as defined and the system history file reflects the installation of the component.




Figure 9. INSTALL TOTAL COMPONENT FROMTAPE TO EXISTING PRIV.LIBRARIES

MSHP (... Cont'd)

INSTALL TOTAL COMPONENT TO EXISTING PRIVATE LIBRARIES (...Cont'd)

To install from disk, use the following job:

```
// JOB INSTALL TOTAL COMPONENT FROM DISK
ASSGN SYSCLB,cuu
// ASSGN SYSRLB,cuu
// ASSGN SYSSLB,cuu
// ASSGN SYS003,cuu
// ASSGN SYS001,cuu
// ASSGN SYS000,cuu
// ASSGN SYS002,cuu
// OPTION CATAL
// EXEC MSHP
INST COMP FROMDISK MERGE
DEF CLIB PRIV ID='pid supplied id'
DEF RLIB PRIV ID='pid supplied id'
DEF SLIB PRIV ID='pid supplied id'
DEF HIST AUX EXT=number1:number2 ID='pid.supplied.id' U=SYS002
/*
ASSGN SYSCLB,UA
/;&
```




Figure 10. INSTALL TOTAL COMPONENT FROMDISK TO EXISTING PRIVATE LIBRARIES

C. INSTALL PART COMPONENT TO SYSRES

Step 1. Install Base Part

To install a base part from tape, use the following job:

```
// JOB INSTALL BASE COMPONENT PART FROM TAPE (1)
// ASSGN SYS006,cuu (2) Distribution tape
// ASSGN SYS007,cuu (2) Output unit for PCL
// ASSGN SYS008,cuu (2) Output unit for PRL
// ASSGN SYS009,cuu (2) Output unit for PSL
// ASSGN SYS002,cuu Auxiliary history file
// OPTION CATAL
// EXEC MSHP
INST COMP FROMTAPE MERGE (3)
DEF CLIB PRIV EXT=number1:number2 DIR=number3
DEF RLIB PRIV EXT=number1:number2 DIR=number3
DEF SLIB PRIV EXT=number1:number2 DIR=number3
DEF HIST AUX EXT=number1:number2 U=SYS002
/*
/;&
```

For description of number symbols reference table 1

Note1: Refer to Figure 5: INSTALL TOTAL COMPONENT FROMTAPE TO SYSRES

MSHP (. . . Cont'd)

C. INSTALL PART COMPONENT TO SYSRES (. . . Cont'd)

To install a base part from disk, change the above job as follows:

- Change in statement (1) the words "FROM TAPE" to read "FROM DISK."
- Omit the assignments indicated by (2).
- After the // JOB statement, include the statements:

// ASSGN SYS003,cuu		From-unit CORGZ PCL
// ASSGN SYS000,cuu		From-unit CORGZ PSL
// ASSGN SYS001,cuu		From-unit CORGZ PRL
- Change in statement (3) the word "FROMTAPE" to read "FROMDISK".
- Omit DIR=number3 in the library definition statements.

Note 2: Refer to Figure 6: INSTALL TOTAL COMPONENT FROMDISK TO SYSRES

Step 2. Install Second Part

To install a second part from tape, use the following job:

```
// JOB INSTALL SECOND COMPONENT PART FROM TAPE (1)
// ASSGN SYS006,cuu (2)           Distribution tape
// ASSGN SYS008,cuu (2)           Output unit for PRL
// ASSGN SYS009,cuu (2)           Output Unit for PSL
// ASSGN SYS002,cuu              Auxiliary history file
// OPTION CATAL
// EXEC MSHP
INST FEATURE FROMTAPE MERGE (3)
DEF RLIB PRIV EXT=number1:number2 DIR=number3
DEF SLIB PRIV EXT=number1:number2 DIR=number3
DEF HIST AUX EXT=number1:number2 U=SYS002
/*
/;&
```

} See Note 2.




Figure 11. INSTALL SECOND COMP. PART FROMTAPE TO SYSRES

To install a second part from disk, use the same job as in Step 2 except for the following changes:

- Replace statement (1) by:


```
// JOB INSTALL SEC COMP PART FROM DISK
```
- Omit the assignments indicated by (2).
- After the // JOB statement, include the statements:

// ASSGN SYS000,cuu	From-unit CORGZ PSL
// ASSGN SYS001,cuu	From-unit CORGZ PRL
- Replace statement (3) by:


```
INSTALL FEATURE FROMDISK MERGE
```
- Omit DIR=number3 in the library definition statements.

} See figure 11 above

MSHP (. . . Cont'd)

D. INSTALL PART COMPONENT TO NEW PRIVATE LIBRARIES

Step 1. Install Base Part

To install a base part from tape, use the following job:

```
// JOB INSTALL BASE COMPONENT PART FROM TAPE
// ASSGN SYS006,cuu           Distribution tape
// ASSGN SYS007,cuu           Output unit for PCL
// ASSGN SYS008,cuu           Output unit for PRL
// ASSGN SYS009,cuu           Output unit for PSL
// ASSGN SYS002,cuu           Auxiliary history file
// EXEC MSHP
INST COMP FROMTAPE ATTACH
DEF CLIB PRIV EXT=number1:number2 DIR=number3 ID='NEW.PCL'
DEF RLIB PRIV EXT=number1:number2 DIR=number3 ID='NEW.PRL'
DEF SLIB PRIV EXT=number1:number2 DIR=number3 ID='NEW.PSL'
DEF HIST AUX EXT=number1:number2 U=SYS002
/*
/;&
```

} See Note 2.

Note1: Refer to Figure 7: INSTALL TOTAL COMPONENT FROMTAPE TO NEW PRIV.LIBRARIES

Note2: For description of number symbols refer to table 1

To install a base part from disk, use the following job:

```
// JOB INSTALL BASE COMPONENT PART FROM DISK
// ASSGN SYS002,cuu           Auxiliary history file
// EXEC MSHP
INST COMP FROMDISK ATTACH
DEF CLIB PRIV ID='pid supplied id'
DEF RLIB PRIV ID='pid supplied id'
DEF SLIB PRIV ID='pid supplied id'
DEF HIST AUX EXT=number1:number2 ID='pid supplied id' U=SYS002
/*
/;&
```

Note: Refer to Figure 8: INSTALL TOTAL COMP FROMDISK THAT BECOMES THE NEW PRIV.LIBR.

Step 2. Install Second Part

To install a second part from tape, use the following job:

```
// JOB INSTALL SECOND COMPONENT PART FROM TAPE (1)
// ASSGN SYS006,cuu (2)           Distribution tape
// ASSGN SYS008,cuu (2)           Output unit for PRL
// ASSGN SYS009,cuu (2)           Output unit for PSL
// ASSGN SYSRSLB,cuu
// ASSGN SYSSLB,cuu
// DLBL IJSYRSL,'NEW.PRL'
// EXTENT SYSRSLB,,1,0,number1,number2
// DLBL IJSYSSL,'NEW.PSL'
// EXTENT SYSSLB,,1,0,number1,number2
// DLBL IJSYSCL,'NEW.PCL'
// EXTENT SYSCLB,,1,0,number1,number2
ASSGN SYSCLB,cuu
// ASSGN SYS002,cuu           Auxiliary history file
// OPTION CATAL
// EXEC MSHP
INST FEATURE FROMTAPE MERGE (3)
DEF RLIB PRIV EXT=number1:number2 DIR=number3 ID='MSHP.PRL'
DEF SLIB PRIV EXT=number1:number2 DIR=number3 ID='MSHP.PSL'
DEF HIST AUX EXT=number1:number2 U=SYS002
/*
/;&
```

} Same as in the define statements in Step 1.

} For description of number symbols reference table 1

MSHP (.... Cont'd)

INSTALL PART COMPONENT TO NEW PRIVATE LIBRARIES (....Cont'd)




Figure 12. INSTALL SECOND PART FROMTAPE TO NEW PRIVATE LIBRARIES

To install a second part from disk, use the same job as in Step 2 except for the following changes:

- Replace statement (1) by:
// JOB INSTALL SEC COMP PART FROM DISK
- Omit the assignments indicated by (2).
- After the ASSGN SYSCLB,cuu statement, include the following statements for the from-libraries for CORGZ:
// ASSGN SYS000,cuu
// ASSGN SYS001,cuu
- Replace statement (3) by:
INSTALL FEATURE FROMDISK MERGE
- Omit DIR=number3 in the library define statements.

E. INSTALL PART COMPONENT TO EXISTING PRIVATE LIBRARIES

Step 1. Install Base Part

To install a base part from tape, use the following job:

```
// JOB INSTALL BASE COMPONENT PART FROM TAPE (1)
// ASSGN SYS006,cuu      (2)      Distribution tape
// ASSGN SYS007,cuu      (2)      Output unit for PCL
// ASSGN SYS008,cuu      (2)      Output unit for PRL
// ASSGN SYS009,cuu      (2)      Output unit for PSL
ASSGN SYSCLB,cuu
// ASSGN SYSRLB,cuu      ]      Target private libraries
// ASSGN SYSSLB,cuu
// ASSGN SYS002,cuu      Auxiliary history file
// OPTION CATAL
// EXEC MSHP
INST COMP FROMTAPE MERGE      (3)
DEF CLIB PRIV EXT=number1:number2 DIR=number3 ID='MSHP.FCL'
DEF RLIB PRIV EXT=number1:number2 DIR=number3 ID='MSHP.PRL'
DEF SLIB PRIV EXT=number1:number2 DIR=number3 ID='MSHP.PSL'
DEF HIST AUX EXT=number1:number2 U=SYS002
/*
/ &
```

see table 1 for description of number symbols

Note1: Refer to Figure 9: INSTALL TOTAL COMPONENT FROMTAPE TO EXISTING PRIVATE LIBRARIES

MSHP (... Cont'd)

E. INSTALL PART COMPONENT TO EXISTING PRIVATE LIBRARIES (...Cont'd)

To install a base part from disk, use the same job as in Step 1 except for the following changes:

- Change in statement (1) the words "FROM TAPE" to read "FROM DISK"
- Omit the assignments indicated by (2).
- After the assign statements for the target private libraries, include the following statements for the from-libraries:

```
// ASSGN SYS003,cuu
// ASSGN SYS000,cuu
// ASSGN SYS001,cuu
```
- Change in statement (3) the word "FROMTAPE" to read "FROMDISK."
- Omit DIR=number3 in the library definition statements.

It is assumed that standard labels are applied for the private libraries.

Note2: Refer to Figure 10: INSTALL TOTAL COMPONENT FROMDISK TO EXISTING PRIVATE LIBRARIES

Step 2. Install Second Part

To install a second part from tape, use the following job:

```
// JOB INSTALL SECOND COMPONENT PART FROM TYPE (1)
// ASSGN SYS006,cuu (2)           Distribution tape
// ASSGN SYS008,cuu (2)           Output unit for PRL
// ASSGN SYS009,cuu (2)           Output unit for PSL
ASSGN SYSCLB,cuu
// ASSGN SYSRLB,cuu              Target private libraries
// ASSGN SYSSLB,cuu              Auxiliary history file
// ASSGN SYS002,cuu
// OPTION CATAL
// EXEC MSHP
INST FEATURE FROMTAPE MERGE      (3)
DEF RLIB PRIV EXT=number1:number2 DIR=number3 ID='MSHP.PRL'
DEF SLIB PRIV EXT=number1:number2 DIR=number3 ID='MSHP.PSL'
DEF HIST AUX EXT=number1:number2 U=SYS002
/*
/&
```

see table 1 for description of nuber symbols




Figure 13. INSTALL SECOND COMP.PART FORMTAPE TO EXISTING PRIV.LIBRARIES

MSHP (. . . Cont'd)

INSTALL PART COMPONENT TO EXISTING PRIVATE LIBRARIES (....Cont'd)

To install a second part from disk, use the same job as in Step 2 except for the following changes:

- Replace statement (1) by:
// JOB INSTALL SEC COMP PART FROM DISK
- Omit the assignments indicated by (2).
- After the assign statements for the target private libraries, include the following statements for the from-libraries:
// ASSGN SYS000,cuu
// ASSGN SYS001,cuu
- Replace statement (3) by:
INSTALL FEATURE FROMDISK MERGE
- Omit DIR=number3 in the library define statements.

F. INSTALL A COMPONENT IN SYSIN FORMAT (from Tape or Disk)

Step 1. Deblock

```
// JOB DEBLOCK TAPE
* Mount the input and output tape
// ASSGN SYS004,cuu           Input tape
// ASSGN SYS005,cuu           Output tape
// EXEC OBJMAINT
•/ LIST PARM=JOB             List jobs on input tape (optional)
•/ DEBLOCK                   Deblock input tape to SYSIN format
/*
/ &
```

Step 2. Execute the SYSIN Job

```
// ASSGN SYSIN,cuu           "Tape" for install from tape
                             "Disk" for install from disk
```

G. INSTALL A FEATURE TO SYSRES

The MSHP function INSTALL FEATURE is used to install IBM program packages designated as a feature.

The following procedures apply when installing a feature from tape or disk to SYSRES. When installing a feature, either of the MSHP functions MERGE or ATTACH may be used; however, if the feature contains transient modules, MERGE should be used.

To install from tape, use the following jobs:

Step 1. Install the Feature

```
// JOB INSTALL FEATURE FROM TAPE
// ASSGN SYS006,cuu           Distribution tape
// ASSGN SYS007,cuu           Output unit for PCL
// ASSGN SYS008,cuu           Output unit for PRL
// ASSGN SYS009,cuu           Output unit for PSL
// ASSGN SYS002,cuu           Auxiliary history file
// OPTION CATAL
// EXEC MSHP
INST FEAT FROMTAPE MERGE
DEF CLIB PRIV EXT=number1:number2 DIR=number3 ID='MSHP.PRIV.CLIB'
DEF RLIB PRIV EXT=number1:number2 DIR=number3 ID='MSHP.PRIV.RLIB'
DEF SLIB PRIV EXT=number1:number2 DIR=number3 ID='MSHP.PRIV.SLIB'
DEF HIST AUX EXT=number1:number 2 -
ID='VSE.AUXILIARY.HISTORY.FILE'   U=SYS002
/*
/ &
```

} See table 1
for descrip-
tion of
number
symbols

MSHP (. . . Cont'd)

INSTALL A FEATURE TO SYSRES (....Cont'd)




Figure 14. INSTALL A FEATURE TO SYSRES

DOWNLEVEL PROBLEM. If a downlevel problem has occurred, MSHP does not merge the libraries and the history file to your operational system; instead, MSHP informs you (by means of a printout) which modules are affected and which PTFs (program temporary fixes) are required. In this case, provide the equivalent PTFs for the feature and apply these PTFs to the restored libraries as shown in Step 2 below; then continue with Step 3.

Step 2. Update Feature Libraries

Apply the PTFs required to resolve the "downlevel" problem that became apparent in Step 1. Note that the library definitions and the history ID in this step must be identical to Step 1.

```
// JOB SELECT PTF's
// ASSGN SYS002,cuu           Restored auxiliary history
// ASSGN SYS001,cuu           MSHP workfile
// ASSGN SYS003,cuu           MSHP workfile
// ASSGN SYS004,cuu           Feature PTF tape
// ASSGN SYSRLB,cuu
// ASSGN SYSSLB,cuu
// DLBL IJSYSRL,'MSHP.PRIV'RLIB'
// EXTENT SYSRLB,,1,0,number1,number2   Restored RLB
// DLBL IJSYSSL,'MSHP.PRIV.SLIB'
// EXTENT SYSSLB,,1,0,number1,number2   Restored SLB
// OPTION CATAL
// EXEC MSHP
SELECT PTF DLIB
DEFINE HIST DLIB EXT=number1:number2 -
      ID='VSE.AUXILIARY.HISTORY.FILE' -
      UNIT=SYS002
PTF UDnnnnn
PTF UDnnnnn
PTF UDnnnnn
/*
/ &
```

On completion of this step, the feature libraries have been updated with the required PTFs.

MSHP (. . . Cont'd)

INSTALL A FEATURE TO SYSRES (....Cont'd)




Figure 15. UPDATE FEATURE LIBRARY

Step 3. Install Updated Feature Libraries

This step installs the feature libraries you updated in Step 2.

Note that the library and history definitions in this step must be identical to Step 1.

```
// JOB INSTALL FEATURE FROM DISK
// ASSGN SYS003,cuu           From-unit for CORGZ PCL
// ASSGN SYS001,cuu           From-unit for CORGZ PRL
// ASSGN SYS000,cuu           From-unit for CORGZ PSL
// ASSGN SYS002,cuu           Auxiliary history file
// OPTION CATAL
// EXEC MSHP
INST FEAT FROMDISK MERGE
DEF CLIB PRIV EXT=number1:number2 ID='MSHP.PRIV.CLIB'
DEF RLIB PRIV EXT=number1:number2 ID='MSHP.PRIV.RLIB'
DEF SLIB PRIV EXT=number1:number2 ID='MSHP.PRIV.SLIB'
DEF HIST AUX EXT=number1:number2 ID='VSE.AUXILIARY.HISTORY.FILE' K=SYS002
/*
/8
```

See Note

Note: For description of number symbols refer to table 1

On completion of this step, the feature has been successfully merged with the libraries of your operational system.




Figure 16. INSTALL UPDATED FEATURE LIBRARIES (FROMDISK) TO SYSRES

MSHP (. . . Cont'd)

INSTALL A FEATURE TO SYSRES (.... Cont'd)

Step 1. Install the Feature FROMDISK

```
// JOB INSTALL FEATURE FROM DISK
// ASSGN SYS003,cuu           From-unit for CORGZ PCL
// ASSGN SYS001,cuu           From-unit for CORGZ PRL
// ASSGN SYS000,cuu           From-unit for CORGZ PSL
// ASSGN SYS002,cuu           Auxiliary history file
// OPTION CATAL
// EXEC MSHP
INST FEAT FROMDISK MERGE
DEF CLIB PRIV EXT=number1:number2 ID='MSHP.PRIV.CLIB'
DEF RLIB PRIV EXT=number1:number2 ID='MSHP.PRIV.RLIB'
DEF SLIB PRIV EXT=number1:number2 ID='MSHP.PRIV.SLIB'
DEF HIST AUX EXT=number1:number2 -
    ID='VSE.AUXILIARY.HISTORY.FILE' U=SYS002
/*
/;&
```

ID given at
time of
restore

See table 1
for descrip-
tion of
number
symbols

On completion of Step 1, and providing a downlevel problem has not occurred, the installation of the feature is completed. Refer to Figure 16 for reference.

DOWNLEVEL PROBLEM. SEE DESCRIPTION BELOW FIGURE 14: INSTALL A FEATURE TO SYSRES.

Step 2. Update Feature Libraries

Use the job given for Step 2 in the procedure "To install from tape."

Note: Refer to Figure 15 for reference.

Step 3. Install Updated Feature Libraries

Use the job given for Step 3 in the procedure "To install from tape."

Note: Refer to Figure 16 for reference.

H. INSTALL A FEATURE TO PRIVATE LIBRARIES

To install from tape, execute the following jobs:

Step 1. Install the Feature

```
// JOB INSTALL FEATURE FROM TAPE
// ASSGN SYS006,cuu           Distribution tape
// ASSGN SYS007,cuu           ]
// ASSGN SYS008,cuu           ] see Note 1
// ASSGN SYS009,cuu           ]
ASSGN SYSCLB,cuu              ]
// ASSGN SYSRLB,cuu           ] Target private libraries
// ASSGN SYSSLB,cuu           ]
// ASSGN SYS002,cuu           Auxiliary history file
// OPTION CATAL
// EXEC MSHP
INSTALL FEATURE FROMTAPE MERGE
DEF CLIB PRIV EXT=number1:number2 DIR=number3 ID='MSHP.PRIV.CLIB'
DEF RLIB PRIV EXT=number1:number2 DIR=number3 ID='MSHP.PRIV.RLIB'
DEF SLIB PRIV EXT=number1:number2 DIR=number3 ID='MSHP.PRIV.SLIB'
DEF HIST AUX EXT=number1:number2 -
    ID='VSE.AUXILIARY.HISTORY.FILE' U=SYS002
/*
/;&
```

See table 1
for descrip-
tion of
number
symbols

Note 1: The extents must be different to the extents of existing private libraries (the target private libraries).

MSHP (... Cont'd)

INSTALL A FEATURE TO SYSRES (... Cont'd)




Figure 17. INSTALL FEATURE FROMTAPE TO PRIVATE LIBRARIES

INSTALL A FEATURE TO PRIVATE LIBRARIES (... Cont'd)

Step 2. Update Feature Libraries

Apply the PTFs required to resolve the "downlevel" problem that became apparent in Step 1. READ DOWNLEVEL DESCRIPTION BELOW FIGURE 14.

Note that the library and history definitions in this step must be identical to those of Step 1.

```
// JOB SELECT PTFs
// ASSGN SYS002,cuu           Restored auxiliary history
// ASSGN SYS001,cuu           MSHP workfile
// ASSGN SYS003,cuu           MSHP workfile
// ASSGN SYS004,cuu           Feature PTF tape
// ASSGN SYSRLB,cuu
// ASSGN SYSSSLB,cuu
// DLBL IJSYSL,'MSHP.PRIV.CLIB'
// EXTENT SYSCLB,,1,0,number1,number2   Restored CLB
ASSGN SYSCLB,cuu
// DLBL IJSYSL,'MSHP.PRIV.RLIB'
// EXTENT SYSRLB,,1,0,number1,number2   Restored RLB
// DLBL IJSYSSL,'MSHP.PRIV.SLIB'
// EXTENT SYSSSLB,,1,0,number1,number2   Restored SLB
// OPTION CATAL
// EXEC MSHP
SELECT PTF DLIB
DEFINE HIST DLIB EXT=number1:number2 -
      ID='VSE.AUXILIARY.HISTORY.FILE' -
      UNIT=SYS002
PTF UDnnnnn
PTF UDnnnnn
PTF UDnnnnn
PTF UDnnnnn
/*
/ &
```

On completion of this step, the feature libraries have been updated with the required PTFs.

Note: Refer to Figure 15 for reference

MSHP (... Cont'd)

INSTALL A FEATURE TO PRIVATE LIBRARIES (. . . Cont'd)

Step 3. Install Updated Feature Libraries

This step installs the feature libraries you updated in Step 2.

Note that the library and history definitions in this step must be identical to those of Step 1.

```
// JOB INSTALL FEATURE FROM DISK
// ASSGN SYS003
// ASSGN SYS001,cuu
// ASSGN SYS000,cuu
// ASSGN SYS002,cuu
ASSGN SYSCLB
// ASSGN SYSRLB
// ASSGN SYSSLB
// OPTION CATAL
// EXEC MSHP
INST FEAT FROMDISK MERGE
DEF CLIB PRIV EXT=number1:number2 ID='MSHP.PRIV.RLIB'
DEF RLIB PRIV EXT=number1:number2 ID='MSHP.PRIV.RLIB'
DEF SLIB PRIV EXT=number1:number2 ID='MSHP.PRIV.SLIB'
DEF HIST AUX EXT=number1:number2 ID='VSE.AUXILIARY.HISTORY.FILE'
/*
/ &
```

From-unit for CORGZ PCL
From-unit for CORGZ PRL
From-unit for CORGZ PSL
Auxiliary history file

Target private libraries

see table 1 for description of number symbols




Figure 18. INSTALL UPDATED FEATURE LIBRARIES (FROMDISK) TO PRIV.LIB.

To install from disk, use the following jobs:

Step 1. Install the Feature

```
// JOB INSTALL FEATURE FROM DISK
ASSGN SYSCLB,cuu
// ASSGN SYSRLB,cuu
// ASSGN SYSSLB,cuu
// ASSGN SYS003,cuu
// ASSGN SYS000,cuu
// ASSGN SYS001,cuu
// ASSGN SYS002,cuu
// OPTION CATAL
// EXEC MSHP
INST FEAT FROMDISK MERGE
DEF CLIB PRIV EXT=number1:number2 ID='MSHP.PRIV.RLIB'
DEF RLIB PRIV EXT=number1:number2 ID='MSHP.PRIV.RLIB'
DEF SLIB PRIV EXT=number1:number2 ID='MSHP.PRIV.SLIB'
DEF HIST AUX EXT=number1:number2 ID='VSE.AUXILIARY.HISTORY.FILE' U=SYS002
/*
/ &
```

Target private libraries

From-libraries for CORGZ

Auxiliary history file

See table 1 for description of number symbols

Note: Refer to Figure 18 for reference

MSHP (.... Cont'd)

INSTALL A FEATURE TO PRIVATE LIBRARIES (.... Cont'd)

Step 2. Update Feature Libraries

Use the job given for Step 2 in the procedure "To install from tape."

Step 3. Install Updated Feature Libraries

Use the job given for Step 3 in the procedure "To install from tape."

I. INSTALL A RELEASE 34 COMPONENT

If a distribution tape/disk does not include MSHP support for installing the component, proceed according to the installation instructions available with the product.

For an up-to-date history file an MSHP archive job should be submitted similar to the following example:

```
// JOB NOTIFY HISTORY
// EXEC MSHP
ARCHIVE 5746-TS-100 REL=01.0
/*
/ &
```

SERVICE ACTIVITIES

S1.APPLY A SINGLE PTF

A single PTF consists of a single VSE job supplied by IBM in SYSIN format on magnetic tape or diskette or as a deck of cards.

To apply a single PTF, place the applicable control statements ahead of the job stream supplied with the PTF and execute the job. On completion of the job, the PTF is applied to your operational system, and this application is reflected in your system history file. The control statements are:

```
// DLBL IJSYSIN,'file-ID',codes
// EXTENT SYSIN, serial-number
ASSGN SYSIN,cuu
```

The Following are Job Examples of Single PTF Applications:

```
// JOB UD13854
// PAUSE EOB OR CANCEL
// OPTION CATAL
// EXEC MSHP
APPLY 5745 - SC - VSM:UD13854 REL=35
RESOLVES APARS = DY13415
AFFECTS MODULS = IKQLAB
OCCUPIES CLIB = 311 RLIB = 10
INVOLVES LINK = IKQVSMK
DATA
TXT
.
.
END
/S
/*
/ &
```

Single PTF Application of a Backout PTF generated with the REVOKE:ble Option:

```
// JOB UD13854 MSHP REVOKE PTF
// PAUSE ASSGN LIBRARIES IF NEEDED
// OPTION CATAL
// EXEC MSHP
REVOKE 5745 SC-VSM:UD13854
DATA
TXT
.
.
END
/S
/*
/ &
```

MSHP (.... Cont'd)

SERVICE ACTIVITIES (. . . Cont'd)

S2. APPLY CUMULATIVE PTFs.

A cumulative PTF file consists of two or more single PTFs in blocked format on tape, disk, or diskette.

Step 1. List Cover Letter

Cover letter information is given in specific files of the distributed material. Refer to the transmittal letter to find out which file applies and specify as shown below.

```
// JOB PRINT COVERLETTER
// ASSGN SYS004,cuu           Cumulative tape
// MTC FSF,SYS004,n         n is the sequence number of the cover-letter minus1
// EXEC MSHP
LIST PTFFILE STATEMENTS SEPARATE
PTF UD12740
PTF UD13805
...
...
...
PTF UDnnnnn
/*
/;&
```

Step 2. Apply PTFs

```
// JOB SELECT PTFs FROM TAPE
// ASSGN SYSPCH,TAPE
// ASSGN SYS003,cuu         MSHP workfile
// ASSGN SYS001,cuu         MSHP workfile
// ASSGN SYS004,cuu         Cumulative PTF tape
// MTC FSF,SYS004,n         see Note 1
// OPTION CATAL
// EXEC MSHP
SELECT PTF APPLY REVOKABLE   see Note 2
PTF UD12740
PTF UD13854                  see Note 3
PTF UDnnnnn
/*
/;&
```

Note 1: This statement positions the tape at the pertinent file.

Note 2: The default is IRREVOKABLE.

Note 3: If one or more of the PTFs require corequisite PTFs, refer to the procedure "Apply Corequisite PTFs."

S3. APPLY COREQUISITE PTFs

The following procedures show how to apply corequisite PTFs from card and from a cumulative PTF tape.

Note: For the creation of private libraries, please refer to MSHP USER'S GUIDE or VSE System Management Guide.

Step 2 writes the two corequisite PTFs into the private libraries, and Step 3 applies the corequisite PTFs to your system.

Step 1. Copy History File to Auxiliary History

```
// JOB COPY HIST TO AUX
// ASSGN SYSnnn,cuu         Auxiliary History File
// EXEC MSHP
COPY HIST SYS AUX
DEF HIST AUX EXT=number1:number2 -
ID='VSE.AUXILIARY.HISTORY.FILE' -
UNIT=SYSnnn
/*
/;&
```

MSHP (.... Cont'd)

SERVICE ACTIVITIES (. . . . Cont'd)

Step 2. First and Second Corequisite PTF Supplied on Cards

This step writes the two corequisite PTFs into the private libraries.

```
// JOB SELECT COREQUISITE PTF
// ASSGN SYS001,cuu           MSHP workfile
// ASSGN SYS003,cuu           MSHP workfile
// ASSGN SYS004,cuu           Card Reader to apply PTFs From
// ASSGN SYSnnn,cuu           Auxiliary history file defined in Step 1
// ASSGN SYSRLB,cuu
// ASSGN SYSSLB,cuu
// DLBL IJSYSL,'MSHP.PRIV.CLIB'
// EXTENT SYSCLB,,,number1,number2
ASSGN SYSCLB,cuu
// DLBL IJSYSL,'MSHP.PRIV.RLIB'
// EXTENT SYSRLB,,,number1,number2
// DLBL IJSYSL,'MSHP.PRIV.SLIB'
// EXTENT SYSSLB,,,number1,number2
// OPTION CATAL
// EXEC MSHP
SELECT PTF DLIB
PTF UDnnnnn                  ] Specify the PTF numbers to
PTF UDnnnnn                  ] be selected
DEF HIST SYS EXT=number1:number2 -
ID='VSE.AUXILIARY.HISTORY.FILE' - Auxiliary history file
UNIT=SYSnnn

/* ] Insert card decks of selected PTF,s
/* ] Terminate the job by these additional cards
/&
```




Figure 19. FIRST AND SECOND COREQUISITE PTF APPLICATION FROM CARD

Step 3. Apply the PTFs

This step applies the corequisite PTFs to the system by using the UPGRADE FROMDISK function.

```
// JOB APGRADE FROM DISK
// ASSGN SYS003,cuu           From-unit for CORGZ PCL
// ASSGN SYS001,cuu           From-unit for CORGZ PRL
// ASSGN SYS000,cuu           From-unit for CORGZ PSL
// ASSGN SYSnnn,cuu           Auxiliary history file (see Note 1)
// OPTION CATAL
// EXEC MSHP
UPGR FROMDISK FORCELINK
DEF CLIB PRIV EXT=number1:number2 ID='MSHP.PRIV.CLIB'
DEF RLIB PRIV EXT=number1:number2 ID='MSHP.PRIV.RLIB' ] see Note 2
DEF SLIB PRIV EXT=number1:number2 ID='MSHP.PRIV.SLIB' ]
DEF HIST AUX EXT=number1:number2 -
ID='VSE.AUXILIARY.HISTORY.FILE' - ] see Note 1
UNIT=SYSnnn

/*
/&
```

MSHP (.... Cont'd)

SERVICE ACTIVITIES (. . . Cont'd)

Note 1:

The specified logical units must be identical; the physical unit must be the one used in Step 1 to accommodate the auxiliary history file. The EXT= and ID= specifications used in the DEF statement must be the same as those used in the DEF statement for Step 1.

Note 2:

The EXT= and ID= specifications of the DEF statements for CLIB, RLIB, and SLIB must be identical to the DLBL and extent information of Step 2.

If no library space is occupied by a PTF, the extent for the respective library should be coded as EXT=0:0.




Figure 20. UPGRADE FROMDISK FORCELINK

Note 3:

UPGRADE applies the contents of corequisite updated private libraries to the operational system. The system history file is updated accordingly.

TO APPLY FROM CUMULATIVE PTF TAPE

Step 1. Copy History File to Auxiliary History

Same as in Step 1 of corequisite PTF application from Card.

Step 2. First Corequisite PTF

```
// JOB SELECT COREQUISITE PTF
// ASSGN SYS001,cuu           MSHP workfile
// ASSGN SYS003,cuu           MSHP workfile
// ASSGN SYS004,cuu           PTF tape
// ASSGN SYSnnn,cuu          Temporary (auxiliary) system history
// ASSGN SYSRLB,cuu
// ASSGN SYSSLB,cuu
// DLBL IJSYSL,'MSHP.PRIV.CLIB'
// EXTENT SYSCLB,,,number1,number2
ASSGN SYSCLB,cuu
// DLBL IJSYSL,'MSHP.PRIV.RLIB'
// EXTENT SYSRLB,,1,0,number1,number2
// DLBL IJSYSSL,'MSHP.PRIV.SLIB'
// EXTENT SYSSLB,,1,0,number1,number2
// OPTION CATAL
// EXEC MSHP
SELECT PTF DLIB IRR
PTF UDnnnn
DEF HIST SYS EXT=number1:number2 -
    ID='VSE.AUXILIARY.HISTORY.FILE' -
    UNIT=SYSnnn
/*
/ &
```

Step 3. Second Corequisite PTF

Apply the second corequisite PTF in the same way as shown in Step 2. Note, the EXT= and the ID= of the DEF HIST SYS statement must be identical to that in Step 1.

Note: Refer to Figure 19 for reference, SYS004 must be assigned to the respective tape unit for corequisite PTF application.

MSHP (.... Cont'd)

SERVICE ACTIVITIES (. . . Cont'd)

S' 4. Apply the PTFs

Same as in Step 3 of corequisite PTF application from card

S4. APPLY, RECORD, AND REMOVE LOCAL AND APAR FIXES

A local fix or APAR fix is a correction to a phase, module, and/or source statement book applied at a specific installation to resolve a problem.

MSHP supports the application and automatic recording of local and APAR fixes; it also allows to remove applied fixes.

- **CORrect** applies a local or APAR Fix
- **UNdo** reverts to the system status before fix application, if the fix was initiated with REVokable.

A local or APAR fix can only be applied a second time, changed or unchanged, by removing its history entry or using the UNdo control statement.

CORrect statement and its requirements

- mandatory: one separate **AFFects** statement for each phase, module, and book.
- optional: **ALTER, DEFINE HISTORY, DELETE, INSERT, INVOLVES, REPLACE, RESOLVES'COMMENT', VERIFY.**
- if used:
 - **DEFine History** must follow directly **CORrect**.
 - **Alter, DELete, INSert, REPlace, and VERify** must be coded in conjunction with the **AFFects** statement.
 - **Alter** must follow directly **AFFects**
 - the other statements may follow in any sequence.
 - **AFFects, INVolves, and RESolves** may be submitted after **CORrect** in any sequence.
 - **RESolves** may contain comments only.
 - **ALTER** relates to Core Image and Relocatable Library fixes.
 - **INVolves** relates to Relocatable Module fixes.
 - **DELete, INSert, REPlace and VERify** relate to corrections of the Source Statement Library.

Workfiles needed

For the function **CORRECT** and **UNDO** of phases without expansion no workfiles need to be assigned. For the functions **CORRECT** and **UNDO** of phases, which will be expanded, and modules, **SYS001** and **SYS004** are required as workfiles with the Filenames **IJSYS01** and **IJSYS04**. For corrections to the source statement library, **SYS001, SYS002, and SYS003** are required as **ASSEMBLER** workfiles, and a **SYS004** assignment is needed by **MSHP** as workfile for the **ESERV** program.

S.4.1 CORRECTIONS TO THE CORE IMAGE LIBRARY

In the following example a local or APAR fix is applied to a specific phase in the core image library.

JOB EXAMPLE

```
// JOB CORRECT PHASE
// OPTION CATAL
// EXEC MSHP
CORRECT component:apar-number
AFFECTS PHASES=phase-name
ALTER address old-text:new-text
RESOLVES 'comment'
/*
/ &
```

FIX EXAMPLE

```
// JOB CORRECT IPWSSOT
// OPTION CATAL
// EXEC MSHP
CORRECT 5745-SC-PWR-DY21001
AFFECTS PHASES=IPW$$OT
ALTER F0 9200B0F8:92F180F8
RESOLVES'ERROR ON TAPE OPEN'
/*
/ &
```

The following statements can be used to remove the local or APAR Fix.

JOB EXAMPLE

```
// JOB UNDO FIX
// OPTION CATAL
// EXEC MSHP
UNDO component:apar-number
/*
/ &
```

FIX EXAMPLE

```
// JOB UNDO FIX
// OPTION CATAL
// EXEC MSHP
UNDO 5745-SC-PWR-DY21001
/*
/ &
```

MSHP (.... Cont'd)

SERVICE ACTIVITIES (. . . Cont'd)

S.4.2 CORRECTIONS TO THE RELOCATABLE LIBRARY

In the following example a local or APARfix is applied to a specific module in the relocatable library. The module size is expanded by the size-increment to accommodate the correction. For Assignment see Workfiles needed on page V-58.

<u>JOB EXAMPLE</u>	<u>FIX EXAMPLE</u>
// JOB CORRECT MODULE	// JOB CORRECT MODULE
// OPTION CATAL	// OPTION CATAL
// EXEC MSHP	// EXEC MSHP
CORRECT component:apar-number	COR 5745-SC-UTL:DY19227
AFFECTS MODULES=module-name	
EXPAND=size-increment	AFF MOD=IJBWIND1 EXP=0100
ALTER address old-text:new-text	AL2034 47F0F8:47F0F0
RESOLVES 'comment'	RES'INIT DISK ERROR'
INVOLVES LINK=link-book	INV LINK=IJBWIND
/*	/*
/&	/&

The following statements can be used to remove the local or APAR fix

<u>JOB EXAMPLE</u>	<u>Coding Example</u>
// JOB UNDO FIX	// JOB UNDO FIX
// OPTION CATAL	// OPTION CATAL
// EXEC MSHP	// EXEC MSHP
UNDO Component:apar-number	UNDO 5745-SC-UTL:DY19227
/*	/*
/&	/&

S4.3 CORRECTIONS TO THE SOURCE STATEMENT LIBRARY (E.MACROS)

The following statements show examples of Local or APAR fix application to E-type macros.

Note that inserts and replacements must be delimited by /\$. See Note below.

```
// JOB CORRECT E.MACRO
// PAUSE
// OPTION CATAL
// EXEC MSHP
CORRECT component:apar-number
RESOLVES 'comment'
AFFECTS MACROS=macro-name
VERIFY verify-line
    AIF (K<- PHASE LEB). FOUR
INSERT after-line
    AGO . STOP
/$
INSERT after-line
    .STOP ANOP
/$
CORRECT component:apar number
RESOLVES 'comment'
AFFECTS MACROS=macro-name
REPLACE: to-line+rel
    *RETURN ANOP
/$
AFFECTS MACROS=macro name
DELETE: to line
/*
// CLOSE SYSPCH,UA
/&
```

Note: Assign SYSPCH to tape and verify that the Assignments according to the chapter: Workfiles needed, on page V-58, are satisfied.

MSHP (.... Cont'd)

SERVICE ACTIVITIES (. . . .Cont'd)

FIX EXAMPLE

```
// JOB CORRECT E. MACRO
// PAUSE ASSGN SYSPCH TO TAPE FOR BACKOUT JOB CREATION
// OPTION CATAL
// EXEC MSHP
CORRECT 5745-SC-SUP: UD17291
RESOLVES 'COMMENT TO BE INSERTED INTO THE HISTORY'
AFFECTS MACROS= CDLOAD
VERIFY 007100
    AIF (K PHASE LE8) FOUR
INSERT 7100
    AGO .STOP
/$
INSERT 9100
• STOP ANOP
/$
CORRECT 5745-SC-SUP:DY18456
RESOLVES 'COMMENT'
AFFECTS MACROS=SETL
REPLACE:300000+21
*RETURN ANOP
/$
AFFECTS MACROS=SECHECK
DELETE: 071500
/*
//CLOSE SYSPCH,UA
/&
```

To remove one with the default option REVOKABLE applied fix run the BACKOUT job produced by MSHP on the unit assigned as SYSPCH.

S 4.4 CORRECTIONS TO THE SOURCE STATEMENT LIBRARY (A.MACROS)

The following statements show examples of local or APAR fix application to A-type macros.

CODING EXAMPLE

```
// JOB CORRECT A.MACRO
// PAUSE
// OPTION CATAL
// EXEC MSHP
CORRECT 5746-XX-100:DA73336
AFFECTS MACROS=DLZCKOPT SUBLIB=A    Note: SUBLIB A must be specified
DELETE:000700
INSERT 450
    LCLB B(9) NGP
B(9) SETB (PIO(P))
/$
/*
// CLOSE SYSPCH,UA
/&
```

To remove an with the default option REVOKABLE applied fix, run the BACKOUT job produced by MSHP on the unit assigned as SYSPCH.

S 4.5 CORRECT THE INVALIDATION OF A RECORDED FIX

During application of a PTF that is allowed to overwrite part of a local or APAR fix the messages M205I und M263A will appear.

```
M205 I PTFUDXXXXX WOULD OVERLAY PART OF LOCAL/APAR FIX UTXXXXXIN
M205 I COMPONENT 5745XXXXX
M263A APPLICATION OF PTF UDXXXXXX WILL ALTER LOCAL/APAR FIX ENTER APPLY
M263A TO CONTINUE AND INVALIDATE THE LOCAL/APAR FIX OR REJECT TO QUIT.
```

MSHP (.... Cont'd)

SERVICE ACTIVITIES (...Cont'd)

The invalidated part can be reapplied with a job like the following example:

```
// JOB CORRECT THE INVALIDATED PART
// EXEC MSHP
CORRECT 5745-SC-PWR: UT 98989
AFFECTS MODULE=IJBIND
ALTER 000020 47F0:47F8
RETRACE APAR
/*
/ &
```

Note 1: All the necessary information you will get via a RETR APAR. The APAR number you will get during the PTF application (that will invalidate part of the local or APAR fix), with MSG M2051.

Use RSERV (CSERV,SSERV) information to find, whether the ALTER information in the RETR APAR is still valid or coding is changed by PTF module replacement.

For removing the still valid part and therefore the entire local or APARfix (which was invalidated during PTF application) you may use a job like the following example:

```
// JOB UNDO THE VALID PART
// OPTION CATAL
// EXEC MSHP
UNDO 5745-SC-PWR: UT98989
RETR APAR
/*
/ &
```

Note 2
Note 3

Note 2:

The APAR number again you will get during that specific PTF application by MSG M2051.

Note 3:

With the RETR APAR you can check whether or not the whole local or APAR fix has been removed.

S 5. APPLY PTFs OF THE DOS/VSE RELEASE 34 FORMAT

PTFs relating to components of the DOS/VSE Release 34 level are distributed in the "DOS/VSE Release 34 format"; the following is an example of this format for the COBOL component.

```
// JOB UP14347
* COMP 5746-CB-100
* NPRES NONE
* PRE NONE
* COREQ NONE
* SUP UP13249
* APPL REL 2.5
* APARS FIXED PP66765 PP67704
* MOD/MACRO AFFECTED ILACBL00 ILACBL01
* ENVIRONMENT DOS/VSE, DOS/VSE
* BLOCKS CL=612, RL=2060, SL=100
// ENTER EOB OR CANCEL
// EXEC MAINT
CATALR ILACBL00,02.5
...
CATALS ...
...
/*
// OPTION CATAL
INCLUDE
...
// EXEC LNKEDT
/ &
```

"DOS/VSE Release 34 format" PTFs can be applied (under the control of MSHP) to VSE/Advanced Functions. "DOS/VSE Release 34 format" PTFs are numbered as Nnnnnn whereas "current format" PTFs are numbered as UDnnnnn.

The following shows how to apply single und cumulative PTFs of the "DOS/VSE Release 34 format" to VSE/Advanced Functions.

Note: If the PTF to be applied to a specific component includes a prerequisite or corequisite PTF that has already been applied to the system but not to the same specific component, then the application of the PTF fails due to requirements not met; message M1511 is issued. In such a case, eliminate the requirement statement and rerun the application job. Message M1511 is also issued if the pre- or corequisite PTF(s) have not been installed; in this case, correct the situation before applying the PTF.

MSHP (.... Cont'd)

SERVICE ACTIVITIES (. . . Cont'd)

To Apply a Single PTF from Card, Magnetic Tape, Disk or Diskette

Single PTFs may be supplied on card, magnetic tape, disk, or diskette. The job streams to apply a single PTF are as follows.

Apply from Card

```
// JOB APPLY R34 PTF
// ASSGN SYS001,cuu           MSHP workfile
// ASSGN SYS003,cuu           MSHP workfile
// ASSGN SYSPCH,cuu           Output for REVOKABLE
// ASSGN SYS004,cuu           Input from card reader
// OPTION CATAL
// EXEC MSHP
ACCEPT OLDPTF APPLY REVOKABLE
/*                               Terminating MSHP control statements
/*
// JOB Nnnnnn                  }
                                Release 34 MSHP format
                                single PTF job cards

/*
/;&
/*
/;&                               Terminating input for SYS004
                                Terminating MSHP job
```

Apply from Magnetic Tape

```
// JOB SELECT R34 PTF's
// ASSGN SYS002,cuu           MSHP workfile
// ASSGN SYS003,cuu           MSHP workfile
// ASSGN SYSPCH,cuu
// ASSGN SYS004,cuu           Cumulative PTF tape
// MTC FSF, SYS004,n           If required
// OPTION CATAL
// EXEC MSHP
SELECT PTF APPLY REVOKABLE
PTF N12345
/*
/;&
```

Apply from Disk or Diskette

The job stream is the same as that for "Apply from Magnetic Tape" above, except that:

- SYS004 is assigned to the disk or diskette I/O unit.
- DLBL and EXTENT statements must be given.

To Apply Cumulative PTFs from Magnetic Tape or Disk

Cumulative PTFs may be supplied on magnetic tape or on disk. The job streams to select PTFs and to apply the selected PTFs are as follows.

Apply from Magnetit Tape

```
// JOB SELECT
// ASSGN SYS001,cuu           MSHP work file
// ASSGN SYS003,cuu           MSHP work file
// ASSGN SYS004,cuu           Cumulative PTF tape
// MTC FSF, SYS004,n           If required
// OPTION CATAL
// EXEC MSHP
SELECT PTF APPLY
PTF N78910
.
.
/*
/;&
```

MSHP (.... Cont'd)

SERVICE ACTIVITIES (. . . . Cont'd)

```

┌───────────┐
│ Apply from Disk │
└───────────┘

// JOB SELECT
// ASSGN SYS001, cuu           MSHP work file
// ASSGN SYS003, cuu           MSHP work file
// ASSGN SYS004, cuu           PTF disk file
// DLBL ...                    } Description of the
// EXTENT ...                   } PTF file on disk
// OPTION CATAL
// EXEC MSHP
SELECT PTF APPLY
PTF N78910
.
.
/*
/ &
    
```

NOTATIONAL CONVENTIONS

The syntax of both the function and detail control statements is represented as path diagrams as explained below:

- The structure of a given statement is derived from its diagram by following the line from left to right, and from top to bottom. The entries given in the diagram (for example, RELease = release-number-list) are selected according to the MSHP services required, and are then coded as described in the explanatory text for the given entry.

At points of branching path lines, a choice must (or may) be made to select one, two or more keywords.

In a set of alternatives, one alternative may be shown inside a line of bullets, for example: ...IRRevokable...

This indicates the default used by MSHP if none of the alternatives in the set is coded.


- In the diagram (and text), words given in all lower-case letters are symbolic; they must be replaced by user-supplied values as detailed in the discussions for the pertinent keywords.
- Some of the all lower-case letter words (see above) end with the suffix 'list'. For example: release number-list
'list' means, that the symbolic word must be enclosed in parentheses (see above). The multiple code units must be separated in one of the following ways:

- By one or more blanks, or
- By a comment, or
- By a comma (which in turn may be surrounded by one or more blanks, or comments)

Commas and blanks as separators may be intermixed in a given 'list'.

- In the diagrams, the path lines can be considered as instruction to code:
 - One or more blanks, or
 - One or more comments, or
 - One comma
- The equal sign (=), plus sign (+), colon (:), and single apostrophes (' ') in the diagrams must be coded as shown. The (+) sign must not be preceded and followed by a blank.
- The diagrams show the terminating semicolon (;) for each statement. However, it is needed only, if a statement is to be followed by another statement on the same line. (For details, and for the continuation capability see the Rules for Coding MSHP Statements in the MSHP User's Guide)

As an example, the following shows the path diagram of the Apply statement.



MSHP CONTROL STATEMENTS

NOTATIONAL CONVENTIONS (. . . . Cont'd)

Comments:

- (1) APply is the sample command verb of the statement.
- (2) This is a part of the statement's total path line; this part indicates that you can code, between 'APply' and 'component', one or more blanks, one or more comments, or one comma.
- (3) 'component' and 'ptf-number' are symbolic word that must be coded according to the details given in the discussion of the statement.
- (4) 'RELease' is a keyword.
- (5) 'release-number-list' is a symbolic word; when coded, it gives the specification relating to the keyword 'RELease'. Code the symbolic word according to the discussion of the statement. 'list' in the symbolic word means that for 'release-number' up to 100 release identifications may be specified.
- (6) The points indicate continuation of the path line; they must not be coded.
- (7) The bullets are part of the total path line and indicate the default. In this example, the default is 'IRRevokable'.
- (8) This is the terminator of the statement; it must be coded if the statement is to be followed by another statement on the same input line.
- (9) The colon, equal, and plus signs, and the single apostrophes if enclosing a symbolic word must always be coded.

MSHP CONTROL STATEMENTS (..... Cont'd)

Function	SYS...																		
	LNK	000	001	002	003	004	005	006	007	008	009	nnn	mmm	CLB	RLB	SLB	PCH	LST	
ACCEPT REVOKABLE	M		M		M	M1							S		O	O	O		M
ARCHIVE													S						M
BACKUP SYSTEM AUXILIARY								M					S						M
COPY				X2									S	X1					M
CORRECT	L1		L1 C1 C2	C1	C1	C1 C2							S		O	O	O	C1	M
CREATE SYSTEM AUXILIARY				X2									S						M
DUMP SYSTEM AUXILIARY				X2									S	X1					M
INCORPORATE	M		M										S		O	O	O		M
INSTALL FROMTAPE SYSTEM COMPONENT				X2				M					S	X1					M
INSTALL FROMTAPE SYSTEM FEATURE PRODUCT MERGE									M										
INSTALL FROMTAPE SYSTEM FEATURE PRODUCT MERGE										M									
INSTALL FROMTAPE SYSTEM FEATURE PRODUCT MERGE																			
INSTALL FROMDISK SYSTEM COMPONENT				X2									S	X1					M
INSTALL FROMDISK SYSTEM FEATURE PRODUCT MERGE								M											
INSTALL FROMDISK SYSTEM FEATURE PRODUCT MERGE																			
INSTALL FROMDISK SYSTEM FEATURE PRODUCT MERGE	M		M												O	O	O		
LIST					M														M
LOOKUP													S						M
PERSONALIZE													S						M
REMOVE													S						M
RESIDENCE													S						M
RESTORE SYSTEM AUXILIARY DTAPE				X2 X2					M				S						M
REVOKE	M		M										S		O	O	O		M
SELECT REVOKABLE	M		M		M	M2							S		O	O	O	M	M
UNDO	L1		L1 C1 C2	C1	C1	C1 C2							S		O	O	O	C1	M
UPGRADE FROMTAPE WHOLEJOB CONCLUDE (Note) REVOKABLE	M			X2					M	M	M	M	S	X1	O	O	O		M
UPGRADE FROMDISK WHOLEJOB CONCLUDE (Note) REVOKABLE	M		X2						E				S	X1	O	O	O		M
UPGRADE FROMDISK WHOLEJOB CONCLUDE (Note) REVOKABLE			M	M															E
UPGRADE FROMDISK WHOLEJOB CONCLUDE (Note) REVOKABLE									E										E

Table 4: MSHP Logical Unit Assignments (Explanation See Table 4-1)

MSHP CONTROL STATEMENTS (.... Cont'd)

O	= optional
M	= mandatory
M1	= if tape, unblocked
M2	= if tape, blocked
S	= mandatory if the corresponding logical unit SYSnnn has been specified in a DEFINE HISTORY SYSTEM statement
X1	= mandatory if the corresponding logical unit SYSmmm has been specified in a DEFINE HISTORY AUXILIARY statement
X2	= mandatory if the corresponding logical unit SYSmmm has NOT been specified in a DEFINE HISTORY AUXILIARY ... statement
E	= at least one of the assignments marked E is required
L1	= if linking of the affected module is required
C1	= if corrections to macros are involved
C2	= if corrections to phases, which will be expanded, and/or modules are involved
mmm	= any number from 0 to 255
nnn	= any number from 0 to 255, but not the same as for mmm if both mmm and nnn are required

Note: If no DETAIL control statement 'DEFINE HISTORY AUXILIARY' has been specified

Table 4-1: Explanations to MSHP Logical Unit Assignments (Table 4)

Function Control Statement	Detail Control Statement *																	
	AFF	AL	COMPR	DATA	DEF	DEL	IN	INV	OCC	OR	PTF	REJ	REP	REQ	RES	SUP	VER	
ACccept					X													
ARChive (Component)					X			X		X					X			
ARChive (Feature)			X		X			X	X	X					X			
ARChive (PTF)	X				X			X	X	X					X	X	X	
ARChive (Local fix)	X	X			X	X	X						X		X			
BACKup					X													
COpy					X													
CORect	X	X			X	X	X	X						X		X		X
CReate					X													
DUMP					X													
INCorporate				X	X			X	X	X					X			
INSTall					X													
LIST					X													
LIST (PTF)					X							X						
Lookup					X													
PERsonalize					X													
REMOve					X													
RESidence					X													
RESTore					X													
RETRace					X													
REVOke				X														
SELect												X						
UNdo				X	X													
UPgrade					X								X					


* Detail control statement verbs are shown abbreviated.
X shows the (mandatory and optional) interrelationship between statements.

Table 5: Interrelationship of Function and Detail Control Statements -- Overview

MSHP CONTROL STATEMENTS (. . . Cont'd)

Function Control Statement	Keyword Operands
ARCHive	<pre> graph TD feature --- component component --- RELEASE[RELEASE = release-number] component --- PTF[PTF = ptf-number] component --- APAR[APAR = apar-number] RELEASE --- SOFTreject[SOFTreject] APAR --- RELEASE2[RELEASE = release-number] </pre>
<p>APPLICATION/EXPLANATION</p>	
<p>The ARCHIVE statement is provided for IBM internal use and is used to make entries in the system history file that accompanies IBM-provided programming support. The entries that can be made are for:</p>	
<ul style="list-style-type: none"> <li style="display: inline-block; width: 45%;">• Features <li style="display: inline-block; width: 45%;">• PTFs <li style="display: inline-block; width: 45%;">• Components <li style="display: inline-block; width: 45%;">• Local or APAR fixes 	
<p>Related Detail Control Statements:</p>	
<p>Mandatory if ARCHive component PTF is specified:</p>	
<ul style="list-style-type: none"> <li style="display: inline-block; width: 30%;">• AFFects <li style="display: inline-block; width: 30%;">• OCCupies <li style="display: inline-block; width: 30%;">• RESolves 	
<p>Mandatory if ARCHive component APAR is specified:</p>	
<ul style="list-style-type: none"> <li style="display: inline-block; width: 30%;">• AFFects 	
<p>Optional if ARCHive feature is specified:</p>	
<ul style="list-style-type: none"> <li style="display: inline-block; width: 20%;">• COMPrises <li style="display: inline-block; width: 20%;">• DEFine <li style="display: inline-block; width: 20%;">• INVolves <li style="display: inline-block; width: 20%;">• OCCupies <li style="display: inline-block; width: 20%;">• REQUIRES 	
<p>Optional if ARCHive component is specified:</p>	
<ul style="list-style-type: none"> <li style="display: inline-block; width: 20%;">• DEFine <li style="display: inline-block; width: 20%;">• INVolves <li style="display: inline-block; width: 20%;">• REQUIRES 	
<p>Optional if ARCHive component PTF is specified:</p>	
<ul style="list-style-type: none"> <li style="display: inline-block; width: 20%;">• DEFine <li style="display: inline-block; width: 20%;">• INVolves <li style="display: inline-block; width: 20%;">• REQUIRES <li style="display: inline-block; width: 20%;">• SUPersedes 	
<p>Optional if ARCHive component APAR is specified:</p>	
<ul style="list-style-type: none"> <li style="display: inline-block; width: 15%;">• ALTer <li style="display: inline-block; width: 15%;">• DEFine <li style="display: inline-block; width: 15%;">• DELete <li style="display: inline-block; width: 15%;">• INsert <li style="display: inline-block; width: 15%;">• REPlace <li style="display: inline-block; width: 15%;">• RESolves 	
<p>feature</p>	<p>Specifies that an entry for a feature is to be made in the system history file, and details which one.</p> <p>A feature id can also be used to specify the precise release level of the program package that is to be archived.</p> <p>The feature id consists of three alphanumeric characters.</p>
<p>component</p>	<p>Specifies that, providing the statement does not include PTF= or APAR= specifications, an entry in the system history file is to be made for a component, and the component's identification. Otherwise, "component" identifies the component to which the PTF or local fix (to be ARCHived) is applicable.</p> <p>Component is a string of 11 characters, according to the following example: 5745-SC-JCL</p>
<p>RELease</p>	<p>Identifies the level of the release, maintenance, or version of a component, PTF, Local or APAR fix.</p>

MSHP CONTROL STATEMENTS (. . . Cont'd)

APPLICATION/EXPLANATION (...Cont'd)	
release-number	Specifies the release number to which the component, PTF, Local Fix, or APAR fix is applicable.
SOFTreject	Specifies that a PTF Application/Revokation for that component can be forced by the user, even if it partially overwrites a local fix or APAR correction. For components, which are archived without this option, all PTFs overwriting partially Local or APAR fixes will be rejected automatically.
PTF	Identifies the PTFs for which an entry is to be made in the history file.
ptf-number	Specifies the number of the PTF(s), for which a history file entry is to be made. ptf-number is a string of 6 or 7 characters, the first one or two being alphabetic the remaining five being digits. For example: N12345 UD12345
APAR	Identifies that an entry in the system history file is to be made for a local fix
apar-number	Specifies under which number the local fix is to be recorded in the system history file. apar-number is a string of 6 or 7 characters: one or two alphabetic, followed by five digits.
Function Control Statement	Keyword Operands
BACKup	History  ;
APPLICATION/EXPLANATION	
The BACKUP statement requests MSHP to copy a history file located on disk onto magnetic tape.	
SYSPCH or tape must be assigned to SYS006.	
Related Detail Control Statements:	
Mandatory: none	Optional: DEFine
History	Identifies this backup as a 'history file' backup.
SYSTEM	Specifies that the history file, that will be copied to tape, is the one with the file name IJSYSHF (which normally is the system history file).
AUXiliary	Specifies that the file with the file name IJSYS02 is the history file, and that the file is to be copied to tape. If the file IJSYS02 is not a history file, the job will be canceled (most likely with an "invalid length" IOCS error).

MSHP CONTROL STATEMENTS (.... Cont'd)

Function Control Statements	Keyword Operands
INSTall	
<p>APPLICATION/EXPLANATION</p>	
<p>The INSTall statement requests MSHP to install a "system", one or more "components", one or more "features", or "products".</p>	
<p>Negative "requirements" ("NOT=") are always checked against the system history file.</p>	
<p>Checks for pre-requisite and co-requisite PTFs are performed against the operational system's history file and the distribution history file as well.</p>	
<p>Checks for "PRE=" and "CO=" requirements for components and/or features depend on the INSTall function being executed. The checks go against the system history or against the distribution history file, or against both.</p>	
<p>Related Detail Control Statements:</p>	
<p>Mandatory: DEFine libraries (see Note 1) Optional: DEFine History</p>	
<p>Note 1:</p>	
<p>With INSTall SYStem, the libraries defined must be of the type SYStem. For all other INSTall functions, they must be of the type PRIVate.</p>	
SYStem	<p>Specifies that a system is to be installed. Restrictions: For restoring the distribution tape (see option FROMTape, the libraries in the DEFine statement must be of the type SYStem. With INSTall SYStem, MERge must not be specified, instead, the option ATTach must be used. Default: With INSTall SYStem, ATTach is the default.</p>
COMPOnentS	<p>Specifies that the component(s) from the distribution libraries are to be installed. Default: With INSTall COMPOnentS, ATTach is the default. Restrictions: Same as described under 'PRoDUct'.</p>
FEATureS	<p>Specifies that one or more features from the distribution libraries are to be installed. Default: With INSTall FEATureS, MERge is the default. Restrictions: Same as described under 'PRoDUct'.</p>
PRoDUct	<p>Specifies that the component(s) and feature(s) composing a complete executable version of a program package are to be installed from the distribution libraries. Default: With INSTall PRoDUct, ATTach is the default. Restrictions: For restoring the distribution tape (see option FROMTape below), the libraries defined in the DEFine statement must be of the type PRIVate.</p>
FROMTape	<p>Specifies that the installation source is the distribution tape assigned as SYS006. The library backups on the tape are restored by the INSTall function as private or system libraries, as specified in the DEFine statement. If the libraries are to be restored as system libraries, SYS005 must be assigned to the disk onto which the libraries are to go. If they are to be restored as private libraries, the following assignments must be effective: SYS007 for PRIVate CLib SYS008 for PRIVate RLib SYS009 for PRIVate SLib</p>
FROMDisk	<p>FROMDisk must be specified to support the INSTall function for a system configuration without magnetic tape facility.</p>
MERge	<p>Specifies that the restored modules, macros, and/or phases are to be copied to the system libraries, or to the assigned private libraries (if any). For the merge from disk, the following assignments must be effective for the restored libraries: SYS000 for SLib SYS001 for RLib SYS003 for CLib Restriction: This option must not be specified with INSTall SYStem.</p>
ATTach	<p>Specifies that the MSHP INSTall function ends with a message informing the user that the libraries can now be used in this system. Its use may simply be to assign the libraries as private libraries.</p>

MSHP CONTROL STATEMENTS (.... Cont'd)

APPLICATION/EXPLANATION (. . . Cont'd)	
	component is a string of 11 characters, according to the example: 5745-SC-JCL.
PTF	Indicates that for the given ptf-number, the history information is to be displayed.
ptf-number	Specifies the PTF number for which information is to be displayed. ptf-number is a string of 6 or 7 characters, the first one or two being alphabetic the remaining five being digits. For example: N12345 UD12345
APAR	Indicates that for the given apar-number, the history information is to be displayed.
apar-number	Specifies the APAR number for which information is to be displayed. apar-number is a string of 6 or 7 characters: one or two alphabets, followed by five digits.
PHase	Indicates that for the given phase-number the information is to be displayed.
phase-name	Specifies the phase name for which information is to be displayed. phase-name is a string of one to eight alphameric characters: 0-9, A-Z, #, \$, and @
MODule	Indicates that for the given module-name information is to be displayed from the system history file.
module-name	Specifies the module-name for which information is to be displayed. module-name is a string of one to eight alphameric characters: 0-9, A-Z, #, \$, and @
FEAture	Indicates that for the given feature-id the following information is to be displayed: <ul style="list-style-type: none"> • feature-id • date of installation
feature-id	Specifies the feature for which information is to be displayed. feature-id is a string of three alphameric characters.
MACro	Indicates that for the given macro-name the information is to be displayed from the history file:
macro-name	Specifies the macro-name for which information is to be displayed. macro-name is a string of one to eight alphameric characters: 0-9, A-Z, #, \$, and @ the first character must be alphabetic: A-Z, #, \$, or @
SUBlib	Identifies that the given sublibrary (see below) contains the source statement book. Default: If omitted, it is assumed that information is to be displayed for an E-type macro.
sublibrary	Specifies the sublibrary of the source statement library in which the macro is cataloged. sublibrary is one alphabetic character (A-Z).

MSHP CONTROL STATEMENTS (.... Cont'd)

Function Control Statement	Keyword Operands
PERsonalize	<pre> 'customer-name' ADDRESS = 'customer-address' PHONE = 'phone-number' PROGRAMMER = 'programmer-name' ENVIRONMENT = 'description' ; </pre>
APPLICATION/EXPLANATION	
<p>The PERsonalize statement is used to identify the history file and relate it to a specific user. Changes can be made by re-coding the statement.</p> <p>Restrictions: Specification of PERsonalize without at least one operand is invalid. If the history file has not been specified before, specification of "customer-name" and "customer-address" is mandatory.</p>	
Related Detail Control Statements:	
Mandatory: none	Optional: DEFine History
'customer-name'	<p>Specifies the user's name.</p> <p>customer-name is a string (enclosed in quotes) of one to twenty characters (not counting the quotes). (See Note)</p>
ADDRESS	Specifies that the given customer-address (see below) is to be entered.
'customer-address'	<p>Specifies the customer's address.</p> <p>customer-address is a string (enclosed in quotes) of one to 45 characters (not counting the quotes). (Restriction: see Note below)</p>
PHONE	Specifies that the given phone-number (see below) is to be entered.
'phone-number'	<p>Specifies the customer's telephone number.</p> <p>If a null string is specified, a previously specified number is erased.</p> <p>phone-number is a string (enclosed in quotes) of one to 17 characters (not counting the quotes).</p>
Note:	<p><u>Restriction:</u> If the history file has not been personalized before, specification of customer-address is mandatory.</p>
PROGRAMMER	Specifies that the given programmer-name (see below) is to be entered.
'programmer-name'	<p>Specifies the programmer's name. If a null string is specified, a previously specified name is erased.</p> <p>programmer name is a string (enclosed in quotes) of one to 24 characters (not counting the quotes).</p> <p>A null string (two consecutive quotes) is accepted.</p>
ENVIRONMENT	Specifies that the given description (see below) is to be entered.
'description'	<p>Specifies the environment description (for example, the release level). If a null string is specified, a previously specified name is erased.</p> <p>description is a string enclosed in quotes of 1 to 62 characters (not counting the quotes).</p> <p>A null string (two consecutive quotes) is accepted.</p>


MSHP CONTROL STATEMENTS (... Cont'd)

APPLICATION/EXPLANATION (...cont'd)	
Related Detail Control Statements:	
Mandatory: none	Optional: DEFine History System
COMPonent	Specifies that the named component is a member of the respective library or libraries
component-list	Specifies the components of the named library, and is a string of 11 characters according to the example: 5745-SC-JCL
ALL	Identifies that all components recorded in the system history file reside in the named library or libraries.
NOW	Identifies that the current name of the service library or libraries in which the specified component(s) reside(s) is to be replaced by the name as specified in CLib/RLib/SLib.
ALSO	Identifies that part of the specified component(s) reside(s) in another set of libraries (CLib/RLib/SLib); that is, in a set other than that named originally. This allows to split a component and to accommodate its parts in different sets of libraries.
CLib RLib SLib	Identifies that, for the core image, relocatable, and/or the source statement library in which the specified component(s) reside(s), the name is to be changed (NOW) or the name is to be added (ALSO) as specified in "name" (see below).
name	Restriction: At least one xLib=name specification must be given. Specifies the service library name that is to be recorded in the system history file for the specified component(s). A maximum of 44 characters enclosed in quotes is allowed.
Function Control Statement	Keyword Operands
RESTore	<p>The diagram shows the syntax for the RESTore statement. It starts with the keyword 'RESTore' followed by a line separator. The first operand is 'History', which is enclosed in a box. The second operand is 'SYStem', represented by a series of dots, also enclosed in a box. The third operand is 'AUXiliary', which is enclosed in a box. The fourth operand is 'Dtape'. The statement ends with a semicolon. Lines connect the labels 'History', 'Dtape', 'SYStem', and 'AUXiliary' to their respective positions in the syntax diagram.</p>
APPLICATION/EXPLANATION	
The RESTore statement requests MSHP to write a history file located on magnetic tape onto disk. The tape must be assigned to SYS006 and, for processing, must be positioned to the file containing the history file.	
The RESTore Dtape function is normally restricted to copying private libraries. The libraries to be restored must be defined with the appropriate DEFine statements. The tape must be assigned as SYS006 and, for processing, must be positioned to the first file.	
Related Detail Control Statements:	
Mandatory: DEFine library if RESTore Dtape	Optional: DEFine History
History	Identifies this restore operation as an MSHP operation.
SYStem	Specifies that the history file is to be copied to a disk file with the file name: IJSYSHF
AUXiliary	Specifies that the history file is to be copied to a disk file with the file name: IJSYS02

MSHP CONTROL STATEMENTS (.... Cont'd)

APPLICATION/EXPLANATION (.... cont'd)	
Related Detail Control Statements	
Mandatory: DATA Optional: none	
component	Identifies the component from which an applied PTF is to be revoked (recalled), and is a string of 11 characters according to the example: 5745-SC-JCL.
ptf-number	Identifies the PTF that is to be revoked. The number to be specified is that of the originally applied PTF. ptf-number is a string of 6 or 7 characters according to the example: UD12345 (N12345)
NODLIBbuild	Suppresses the DLIBbuild option (see below). NODLIBbuild is the default and thus is not generated by MSHP on backout PTFs.
DLIBbuild	The DLIBbuild option is generated for backout of PTFs that had corequisite PTFs. The DLIBbuild option, if specified, has the effect that the user is cautioned by a message to also REVOKE the corequisite PTFs. Furthermore, MSHP verifies that the libraries involved in applying the backout PTF are assigned as private libraries, so that the running system does not become non-operational by REVOKING one PTF of a series of corequisites.

Function Control Statement	Keyword Operands
----------------------------	------------------



APPLICATION/EXPLANATION	
The SELECT statement is used to select individual PTFs from a cumulative PTF file (filename: PTF). Entries are made in the system history file for all the PTFs selected.	
The device the SElect function reads the cumulative PTF file from must be assigned to SYS004.	
The modules and/or macros of the selected PTFs are catalogued into the corresponding libraries (system or private, if assigned). Linkedit according to "linkbooks" contained in the selected PTF are only done, if the option 'APply' is specified. If 'APply' is specified, OPTION CATAL must be in effect and must have been coded in the job invoking MSHP with the SElect function.	
The SElect function can also be utilized to "revoke" individual PTFs.	
Selection of Release 34 format PTFs	
The cumulative PTF file may contain DOS/VSE MSHP-format PTFs and PTFs of the Release 34-MSHP-format. For the Release 34-MSHP-format PTFs, MSHP takes history information from JCL comment statements and builds the necessary MSHP control statements.	
Restrictions:	
<ul style="list-style-type: none"> ● The number of APARS fixed must not exceed 255. ● The PTF must not have more than 72 requisites (PRE, CO and NOT). ● At most 32 PTFs can be superseded. ● The selected PTF may not be applicable to more than six releases. 	
Related Detail Control Statements:	
Mandatory: PTF Optional: none	
PTFfile	Distinguishes the selecting of PTFs from the cumulative PTF file from other select operations.
APply	Specifies that the selected PTFs are to be applied to the system. Default: The keyword APply may be omitted when option DLIBbuild is specified (see below). The omission of APply indicates that the modules and/or macros of the selected PTFs are to be catalogued into the corresponding libraries (as in the case when APply is specified) but that linkedit according to the statement INVolves LINK=link-book-list are not to be performed.
IRRevokable	Specifies that when applying the PTF, no backout PTF is generated. That is, the PTF cannot be revoked (the status before the application of the PTF cannot be recreated).

MSHP CONTROL STATEMENTS (.... Cont'd)

APPLICATION/EXPLANATION (. . . Cont'd)

Restrictions: The UPGrade function can only be performed when MSHP is executed in the background partition.

Foreground partitions must be inactive if a library space problem is being resolved by means of condense and FCOPY runs (see CONCLude below).

Related Detail Control Statements:

Mandatory: DEFine

Optional: REJect

OLDsystem	Specifies that the history information about the PTFs applied by the UPGrade function is to be inserted in the operational system's history file.
NEWsystem	Specifies that the whole system history file of the current operational system be merged to the MSHP-created auxiliary history file. These merged files, then can become the history file of a new (operational) system. The auxiliary history file created by MSHP is the restored history file that accompanied the upgrade library package, from which MSHP has removed all entries relating to PTFs that have to be rejected.
ALL	Specifies that all PTFs contained in the upgrade library are applied to the current operational system. Excluded from this application are PTFs that don't satisfy the conditions requested by MSHP. The exceptions are listed in the MSHP USER.s GUIDE under the same option (keyword operand).
EXcept	Identifies that PTFs for the components named in the exception-list (see below) are not to be applied. (The EXcept option is used to exclude whole components from preventive system service, whereas the REJect detail control statement excludes individual PTFs.)
Exception-list	Specifies the components to be excepted from preventive maintenance. exception is a string of 11 characters according to the example: 5745-SC-JCL.
COMPonent	Identifies that the components named in the component-list (see below) are to be included in the preventive system service.
component-list	Specifies the components to be included in the preventive system service. If specified, only the components named are candidates for preventive system service. PTFs for all components not named are rejected. A component may be named for preventive system service in this option, even though there might not be a PTF for it in the PTF upgrade libraries. Component is a string of 11 characters according to the example: 5745-SC-JCL.
IRRevokable	Specifies that no backout PTFs will be generated for the PTFs applied during preventive system service.
REVokable	Requests backout PTFs to be generated for all PTFs applied. The backout PTFs are MSHP jobs with the REVoke function control statement included. If SYS006 is assigned to a tape drive, the backout PTFs are written in blocked format to this tape unit. Otherwise, the backout PTFs are written unblocked to SYSPCH. (See Note below for SYS006 tape drive assignment)
FROMTape	Specifies that the upgrade libraries and the distribution history file are to be restored. The tape containing the upgrade libraries must be mounted on a tape drive that is assigned as SYS006. MSHP restores the libraries as defined in the DEFine detail control statement; the libraries defined must be of the type PRIVate with the following assignments effective: SYS007 for private CLIB SYS008 for private RLIB SYS009 for private SLIB MSHP restores the distribution history file from tape to an auxiliary history file. An assignment for the auxiliary history file as SYS002 or as specified in the Unit-SYSnnn parameter of the DEFine statement must be effective in any case. From the auxiliary history file all PTF entries are removed for PTFs to be rejected. Note: The same tape drive from which the upgrade libraries distribution tape was read.

MSHP CONTROL STATEMENTS (.... Cont'd)

APPLICATION/EXPLANATION (. . . Cont'd)	
FROMDisk	<p>When this option is coded, MSHP assumes that the distribution PTF upgrade libraries and the corresponding history file have been restored previously. DEFine detail control statements are now needed to make known to MSHP where the restored libraries and AUXiliary history file are. (The DEFines for the libraries must not specify a directory size.)</p> <p>Assignments for the restored libraries and the auxiliary history file must be effective as follows: SYS000 for SLIB SYS001 for RLIB SYS003 for CLIB</p> <p>For the auxiliary history file, the assignment must be SYS002, or as specified in the Unit=SYSnnn parameter of the DEFine statement.</p>
WHOLEjob	Specifies that restoring the libraries and applying the PTFs is to be done in one continuous job.
CONclude	Specifies that MSHP checks the target libraries for sufficient space before merging the PTF phases, modules, and/or macros from the restored PTF upgrade libraries, or before link-editing. For details refer to MSHP User's Guide.
NODLIBbuild	Suppresses the DLIBbuild option (see below).
DLIBbuild	<p>Specifies that two PTF application libraries (which are interdependent through corequisite PTFs) are to be merged.</p> <p>This function makes application of PTFs acceptable, even if their corequisites are not yet installed, or are not on the same upgrade library. (A warning message is issued, nevertheless.) The libraries involved in applying the PTF are verified to be private libraries. Backout PTFs for such PTFs are generated with the DLIBbuild option in the REVoke statement.</p>
FORCElink	Specifies that all components upgraded with PTFs from the PTF upgrade libraries are to be linkedited provided at least one PTF for such a component was applied (when building the PTF upgrade libraries) with linkediting suppressed (specifying NOLink in APPLY, or not specifying APPLY in SELECT or ACCept). For additional and further detail information refer to MSHP USER'S GUIDE.

Detail Control Statements	Keyword Operands
AFFects	<p>PHAses = phase-name-list EXPANd = size-increment</p> <p>MODUles = module-name-list</p> <p>LIOCS CSect = csect-number</p> <p>EXPANd = size-increment</p> <p>MACRos = macro-name-list</p> <p>SUBLib = sublibrary-qualifier</p>

The AFFects statement identifies which phases, modules, and/or macros are affected by a PTF, or local fix; or which of the replacement modules are for a feature.

Restrictions: One AFFects statement must not refer to more than a total of 100 phases, modules, and macros.

PHAses Identifies that phase(s) as specified in phase-name-list (see below) are affected.

phase-name-list Specifies the affected phase(s).

Restrictions: If the AFFects statement is used in conjunction with CORrect or when archiving a local fix and the fix information itself, list may not be specified, but only the name of the phase to be modified

phase-name is a string of one to eight alphameric characters:
 0 - 9, A - Z, #, \$, and @


MSHP CONTROL STATEMENTS (... Cont'd)

APPLICATION/EXPLANATION (. . . Cont'd)	
EXPand	Identifies that the specified phase of the named module is to be made larger, as specified in size-increment (see below), so that fix code can be added at the end of the module.
size-increment	Specifies the number of bytes by which the module is to be increased. size-increment is a number of one to six digits.
MODules	Identifies these modules as specified in module-name-list.
module-name-list	Specifies the affected module(s). Restrictions: refer to phase-name-list description above. module-name is a string of one to eight alphanumeric characters: 0-9, A-Z, #, \$, and @
LIOCS	Identifies that a LIOCS module is affected by a PTF. Note that only the macro to generate the module is distributed in the PTF, but not the affected module itself.
Csect	Identifies that an alteration applies to the CSECT specified in Csect-number (see below). <u>Default:</u> If not specified, Csect = 001 is assumed; that is, the first CSECT. <u>Restrictions:</u> Csect must only be specified when correcting (CORrect), or when archiving (ARCHive) a local fix.
csect-number	Specifies the CSECT number to which the alteration applies. (The ESID number of SD) csect-number has one to three hexadecimal digits. If less than three digits are specified, the number is padded with leading zeros. <u>Restrictions:</u> csect-number must only be specified as shown under Csect.
EXPand	Identifies that the specified CSECT of the named module is to be made larger, as specified in size-increment (see below), so that fix code can be added at the end of the CSECT. Restrictions: EXPand must only be specified when archiving a local fix.
size-increment	Specifies the number of bytes by which the CSECT is to be increased. size-increment is a number of one to six digits.
MACros	Identifies these macros (members of the source statement library) as specified in macro-name-list (see below) are affected.
macro-name-list	Specifies the affected macro(s). Restrictions: Refer to phase-name-list description above macro-name is string of one to eight alphanumeric characters: 0-9, A-Z, #, \$, @ the first characters must be alphabetic: A-Z, #, \$, or @.
SUBlib	Identifies that a specific sublibrary of the source statement library contains the affected macro(s). Default: If not specified, sublibrary E is assumed.
sublibrary-qualifier	Specifies the sublibrary of the affected macro. sublibrary-qualifier is one alphabetic character: A-Z.
<u>Note:</u>	All sublibrary qualifiers are handled as edited members, except the A qualifiers.
Detail Control Statement	Keyword Operands
ALter _____ address _____ old-text _____ : _____ new-text _____ ;	
APPLICATION/EXPLANATION The ALter statement identifies the modification that are to be made to a phase (core image library member) or module (relocatable library member). Modification includes verification for core image library members, and optionally for relocatable library members.	

MSHP CONTROL STATEMENTS (.... Cont'd)

address	Specifies the address where the new-text is to begin to replace the old-text. address is a string of one to six hexadecimal digits.
old-text	Specifies the text that is to be replaced. The text in the phase or module at the specified address is verified to be identical with the old text; replacement by new text takes only place if identical. Restrictions: old-text must be specified if modifying a phase; it may be specified when modifying a module. Old text can be of any of the three formats described in the MSHP USER,s GUIDE under the description for the ALter Detail Control Statement.
new-text	Specifies the text that is to replace the text at the specified address. new-text can consists of any of the three formats as described for old-text in the MSHP USER's GUIDE.

Detail Control Statement	Keyword Operands
--------------------------	------------------



APPLICATION/EXPLANATION

The DEFine statement creates label/extent definitions for libraries or history files in the user label area of the partition in which MSHP is executed. Further, it determines the library allocation for MSHP functions such as INSTall, RESTore, and Dtape, which involve restoring libraries from tape to disk. DEFine Labelarea is used to specify how many FBA blocks are to be allocated for the System Label Area when installing a system.

The following describes the keyword operands of the DEFine statement.

- CLib** Identifies that the label definition and/or allocation has to be made for a core image library. A label definition is made only if PRIVate is specified as well; in this case, the file name used is: IJSYSCL.
- RLib** Identifies that the label definition and/or allocation has to be made for a relocatable library. A label definition is made only if PRIVate is specified as well; in this case, the file name used is: IJSYSRL.
- SLib** Identifies that the label definition and/or allocation has to be made for a source statement library. A label definition is made only if PRIVate is specified as well; in this case, the file name used is: IJSYSLL.
- PLib** Identifies that a procedure library is to be restored and that its allocations are as specified in EXTent (see below).

Restrictions: DEFine PLib may be specified only in relation to function control statement
 - INSTall

MSHP CONTROL STATEMENTS (... Cont'd)

APPLICATION/EXPLANATION (. . . Cont'd)	
SYStem	<p>Identifies that the library is to be restored as system library.</p> <p>Restrictions: DEFine SYStem may be specified only in relation to function control statements:</p> <ul style="list-style-type: none"> • INSTall • RESTore Dtape
PRIVate	<p>Identifies that (if applicable) the library is to be restored as private library. Further, a label definition entry is made in the partition label area.</p> <p>Restrictions: PRIVate may not be specified with PLib.</p>
PLACEholder	<p>Identifies that, when restoring, space should be left for an (empty) library.</p> <p>Restrictions: PLACEholder must not be specified with CLib.</p> <p>DEFine PLACEholder may be specified only in relation to the function control statement:</p> <ul style="list-style-type: none"> • INSTall <p>Default for SYStem/PRIVate/PLACEholder. If neither SYStem nor PRIVate, nor PLACEholder is specified, the default taken depends on which function control statement the DEFINE statement is detail control statement to. The default is: SYStem for INSTall PRIVate for UPGrade</p>
EXTent	<p>Identifies that extent information (if a label definition entry is made), and the library allocation (when restoring is involved) is to be derived from the specified values in start-track : tracks (see below).</p>
start-track	<p>For CKD devices, specifies the track number relative to zero, where a private library is to begin; the library must begin on a cylinder boundary, except in the case of a private core image library.</p> <p>For FBA devices, designates the number of the first FBA block of a private library.</p> <p>Restrictions: start-track must be specified for libraries or type PRIVate; it must not be specified for libraries of type SYStem.</p>
tracks	<p>Specifies, for a private library, what the extent is to be in the label definition; and for any type of library (SYStem or PRIVate), how many tracks/blocks are to be allocated when restoring.</p> <p>For CKD devices, the number specified is in number of tracks and may be any integral number of cylinders. If less than one cylinder is specified, the minimum allocated is one cylinder; if an odd number of tracks is specified, an integral number of cylinders is allocated.</p>
DIRectory	<p>Identifies that space, as specified in directory-size (see below), is to be allocated for the library directory.</p>
directory-size	<p>For CKD devices, specifies how many tracks must be allocated for the library directory; for FBA devices, how many FBA blocks.</p>
IDentifier	<p>Identifies that the library identifier given in dataset-name (see below) is to be entered in the VTOC.</p>
Dataset-name	<p>Specifies the library identification that is to be entered in the VTOC.</p> <p>dataset-name is a string, enclosed in quotes, of one to 44 alphanumeric characters.</p> <p>Defaults: If dataset-name is not specified, MSHP takes the following defaults:</p> <ul style="list-style-type: none"> • For CLib PRIVate : 'DOS.SYSCLB.FILE' • For RLib PRIVate : 'DOS.SYSRLB.FILE' • For SLib PRIVate : 'DOS.SYSSLB.FILE' <p>If DEFine SYStem has been specified and dataset-name is omitted, MSHP takes the default: DOS.SYSRES.FILE</p> <p>Restriction: If DEFine SYStem RLib/SLib/PLib and dataset-name has been specified, the dataset-name specification is ignored. If CLib has been specified, the VTOC entry for the CLib is that of the SYSRES file.</p>
History	<p>Identifies that a label definition is to be made for a history file.</p>
AUXiliary	<p>Identifies that the entry in the partition's user label area for the history file is to be made under the file-name: IJSYS02</p>

MSHP CONTROL STATEMENTS (.... Cont'd)

APPLICATION/EXPLANATION (. . . Cont'd)	
SYStem	Identifies that the entry in the partition's user label area for the history file is to be made under the file-name: IJSYSHF
DLIBbuild	Identifies that entries for the file-names IJSYSHF and IJSYS02 are to be made in the partition's user label area. Both files have the same extent and identifier as specified or defaulted in EXTent and IDentifier. Restrictions: DLIBbuild may not be used during INSTALL or UPGrade.
EXTent	Identifies that extent information and the library allocation is to be derived from the specified values in start-track : tracks.
start-track	For CKD devices, specifies with which track relative to zero the extent for the history file is to begin; for FBA devices with which FBA block number.
tracks	Specifies, for the history file, the size of the extent. For CKD devices, the number specified is in number of tracks; for FBA devices, the number means FBA blocks.
SPlit	Identifies that the history file is to be maintained as a split-cylinder file, identifies the value given in split-track as the last track to be allocated to the file. Restrictions: SPlit must not be specified for a history file on FBA devices.
split-track	Specifies which track is the last one in each cylinder to be allocated to the history file defined. (The first cylinder occupied by the file ist the one in which the "start-track" lies, and the last cylinder is determined by the number of tracks specified.) split-track is a decimal integer not exceeding 19.
Unit	Identifies that a history file is to reside on the logical unit (other than SYSREC) as specified in SYSnnn. Restrictions: Specification of Unit does not allow for maintaining the system's parameter history file on a logical unit other than SYSREC.
SYSnnn	Specifies the logical unit on which the defined history file is to reside, and assigns the unit to a physical device (CKD or FBA). SYS is followed immediately by three digits (for nnn) representing the physical device address. Default: If not specified, MSHP takes the following defaults: For a SYStem history file: SYSREC For a AUXiliary history file: SYS002 For a DLIBbuild history file: SYS002
IDentifier	Identifies that the history identifier given in dataset-name is to be entered in the VTOC.
'dataset-name'	Specifies the history file identification that is to be entered in the VTOC. dataset-name is a string, enclosed in quotes, of one to 44 alphanumeric characters. Defaults: If dataset-name is not specified, MSHP takes the following defaults: For History AUXiliary: 'VSE.AUXILIARY.HISTORY.FILE' For History SYStem: 'VSE.SYSTEM.HISTORY.FILE' For History DLIBbuild: 'VSE.DLIB.HISTORY.FILE' Restriction: If you use IBM-supplied standard labels or if your own standard label set contains DLBL and EXTENT for IJSYSHF, do not use DEFINE HISTORY SYSTEM in any MSHP job accessing the system history file.
Labelarea	Identifies that a labelarea is to be allocated when installing a system on a FBA device. Restrictions: DEFine Labelarea may only be specified in conjunction with the function control statement INSTall. Default: If omitted, defaults apply as assumed by the RESTORE utility program.
EXTent	Identifies that the size of the labelarea that will be allocated is to be derived from the value given in blocks (see below).
blocks	Specifies how many FBA blocks are to be allocated for the label area when installing a system.

MSHP CONTROL STATEMENTS (.... Cont'd)

Detail Control Statement	Keyword Operands
DELeTe	<p>The diagram shows the syntax for the DELETE statement: <code>DELeTe From-Line [+rel] : to-line [+rel] ;</code>. Brackets indicate that the <code>+rel</code> options are optional and apply to both the <code>From-Line</code> and <code>to-line</code> fields.</p>
<p>APPLICATION/EXPLANATION</p> <p>The DELETE statement indicates the lines to be deleted from a source statement library member when archiving a local fix.</p> <p>from-line Specifies the line-number, in columns 73 through 78 in the de-edited (E-served) deck, where deletion begins. The from-line is the first line to be deleted. from-line is an integer of one to six digits. Default: If omitted, 'from-line' is assumed to be equal to 'to-line'. This means, that only the line designated by to-line (see below) is deleted.</p> <p>rel Identifies the position of the statement relative to the from-line number, and is an integer of one or two digits. Restriction: rel applies to E. macros only</p> <p>to-line Identifies the last line of the lines to be deleted. to-line is an integer of one to six digits. Restrictions: to-line must numerically be equal to or greater than the value given in from-line.</p> <p>rel Identifies the position of the statement relative to the to-line number, and is an integer of one or two digits. Restriction: rel applies to E. macros only.</p>	
Detail Control Statement	Keyword Operands
INsert	<p>The diagram shows the syntax for the INSERT statement: <code>INsert after-line [+rel] ;</code>. A bracket indicates that the <code>+rel</code> option is optional and applies to the <code>after-line</code> field.</p>
<p>APPLICATION/EXPLANATION</p> <p>The INSERT statement identifies where, in a source statement library member, additions are to be made when archiving a local fix or when initiating a local or APAR fix by means of the CORrect Statement.</p> <p>after-line Specifies the line number in the macro in columns 73 through 78, after which the source input (following the INsert statement up to the next/\$) is to be inserted. after-line is an integer of one to six digits.</p> <p>rel Specifies the position of the source input relative to the after-line number, and is an integer of one or two digits Restriction: rel applies only to E. macros</p>	
Detail Control Statement	Keyword Operands
PTF	<p>The diagram shows the syntax for the PTF statement: <code>PTF ptf-number [REVokable] [DLIBbuild] [NOLINK] [COMment = 'comment'] ;</code>. Brackets indicate that the <code>REVokable</code>, <code>DLIBbuild</code>, <code>NOLINK</code>, and <code>COMment = 'comment'</code> options are optional and apply to the <code>ptf-number</code> field.</p>
<p>APPLICATION/EXPLANATION</p> <p>The PTF statement indicates (to SElect) which PTFs are to be selected from the cumulative PTF file. One PTF statement is required for each PTF that is to be selected; they need not to be in any specific sequence.</p>	

MSHP CONTROL STATEMENTS (.... Cont'd)

APPLICATION/EXPLANATION (. . . Cont'd)	
ptf-number	Identifies the PTF that is to be selected from the cumulative PTF file. ptf-number is a string of 6 or 7 characters, the first one or two are alphabetic, the remaining five are digits. For example: N12345 (Nnnnnn is used for "old" format PTFs) UD12345 (UDnnnnn is used for "new" format PTFs)
IRRevokable	Specifies that, when applying the selected PTF, no backout PTF is to be generated. That is, the PTF cannot be revoked. Restrictions: See Hierarchy of Irrevokable/Revokable, below.
REVOkable	Specifies that, when applying the selected PTF, a backout PTF is to be generated. That is, the PTF can be revoked. Restrictions: See "Hierarchy of Irrevokable/Revokable", below. REVOkable cannot be specified with the DLIBbuild option specified.
NODLIBbuild	If explicitly specified, suppresses DLIBbuild specification in the SElect or APply statement for the selected PTF.
DLIBbuild	If specified, has the same effect as if specified in the APply statement or the selected PTF. It overrides any defaulted or explicitly specified NODLIBbuild in the APply or SElect statement. For the function of DLIBbuild in APply, see the APPLY statement. Restrictions: DLIBbuild and REVOkable are mutually exclusive options.
NOLINK	If specified, has the same effect as if specified in the APPLY statement of the selected PTF; even if in the SElect statement no indication is given that Linkedit is to be suppressed (the option APply being coded). For the functions of NOLINK, see NOLINK in the APPLY statement.
COMment	Identifies that the comment as specified in comment (see below) is to be inserted in the history file.
'comment'	Specifies that a comment relating to the selected PTF has to be inserted in the history file when the PTF is applied. comment is a string, enclosed in quotes, of one to 57 characters (not counting the quotes).
Hierarchy of Irrevokable/Revokable	
Revokability for a PTF may be specified in the SElect statement, the APply statement and in the PTF statement. The following hierarchy holds: An explicit specification of IRRevokable or REVOkable in the PTF statement overrides any other revokability specification (explicit or defaulted). If IRRevokable/REVOkable is not explicitly specified in the PTF statement, then an explicit specification in the SElect statement becomes the controlling one. If IRRevokable/REVOkable is not explicitly specified in the PTF or in the SElect statement, then the revokability in the APply statement (explicit or defaulted) becomes effective. Release 34 format PTFs are always IRRevokable, unless REVOkable is specified in the PTF or the SElect statement.	
Detail Control Function	Keyword Operands
REJect ——— component ——— PTFs = ptf-number-list ———	
APPLICATION/EXPLANATION	
The REJect statement indicates which PTFs are explicitly to be excluded if upgrading a system. Restrictions: The total number of PTFs that are to be rejected per UPGRADE (and specified in one or more REJECT statements) together with the total number of components that are to be excepted must not exceed 113.	
component	Specifies the component, for which PTFs (specified in PTFs = ptf-number-list, see below) are to be rejected. component is a string of 11 characters according to the example: 5745-SCJCL.

MSHP CONTROL STATEMENTS (.... Cont'd)

APPLICATION/EXPLANATION (. . . Cont'd)	
PTFs	Identifies that PTFs as specified in ptf-number (see below) are to be excluded from application.
ptf-number-list	Specifies the numbers of the PTFs to be excluded. ptf-number is a string of 6 or 7 characters, the first one or two are alphabetic, the remaining five are digits. For example: N12345 UD12345
Detail Control Statement	Keyword Operands
<pre>REPlace ----- from-line ----- +rel ----- : ----- to-Line ----- +rel ----- ;</pre>	
APPLICATION/EXPLANATION	
The REPlace Statement defines where replacement of lines in a source statement library member must begin and end.	
from-line	Specifies in the macro, by the line-number in columns 73 through 78, the first line to be deleted and to be replaced. from-line is an integer of one to six digits. If less than six digits are coded, leading zeros are supplied.
rel	Specifies the position of the line relative to the from-line number, and is an integer of one or two digits. Applies only to E.macros.
to-line	Specifies the line-number contained in columns 73 through 78 of the macro to be modified. Beginning with from-line up to and including to-line, all lines in the macro are to be deleted. It is an integer of one to six digits. If less than six digits are coded, leading zeros are supplied.
rel	Specifies the position of the line relative to the to-line number, and is an integer of one or two digits. Applies only to E.macros.
Detail Control Statement	Keyword Operands
<pre>VERify ----- verify-line ----- +rel ----- ;</pre>	
APPLICATION/EXPLANATION	
The VERify statement designates where, in a source statement library member, a verification is to be made for a local or APAR fix correction. Applies to E.macros only.	
verify-line	Specifies the (statement) number, in columns 73 through 78 in the de-edited (E-served) deck, that contains the character(s) to be verified, or specifies the line (statement) number which is to be referenced for the 'rel' specification below. verify-line is an integer of one to six digits. If fewer than six digits are coded, leading zeros are supplied.
rel	Specifies the position of the line that contains the character(s) to be verified in relation to the reference statement number specified for verify-line above. rel is an integer of one or two digits. Restrictions: rel applies only to E.books.

INDEX

A

ACCEPT (MSHP) V-66
 ACTION statement II-23
 ADD command II-01
 ADD statement (ESERV) II-35
 Address converting virtual to real IV-88
 AFFECTS (MSHP) V-81
 ALLOC command II-09
 ALLOCR command II-09
 ALTER command II-09
 ALTER (MSHP) V-82
 Anchor Table (ANCHTAB) IV-95
 Apply a single PTF V-53
 Apply cumulative PTF's V-54
 Apply corequisite PTF's V-54
 Apply, record and remove local
 and APAR Fixes V-57
 Apply PTF's of DOS/VS R34 format V-60
 APS Option Table IV-94
 ARCHIVE statement (MSHP) V-67
 ASCII/EBCDIC translation table IV-73
 ASPL macro III-31
 ASSGN command + statement II-09
 ASSGN macro III-31
 ATTACH macro III-31
 Attention routine commands II-06
 Automatic condense, librarian II-26

B

BACKUP (MSHP) V-68
 Base Part Installation (MSHP) V-45
 BATCH command II-10
 BKEND function, librarian II-25

C

CALL macro III-31
 Cancel codes and messages IV-53
 CANCEL command II-10
 CANCEL macro III-31
 CATALOG function, librarian II-25
 CAW I-17
 CBTAB IV-40
 CCB (Command control block) IV-07
 CCB macro III-29
 CCW (channel command word) I-17
 CCWTCB (translation control block) IV-83
 CDLOAD macro III-31
 CDMOD macro III-23
 Channel address word I-17
 Channel commands I-19
 Channel command word I-17
 Channel control table IV-39
 Channel logout, limited I-18
 Channel queue table IV-38
 Channel status word I-17
 CHAP macro III-31
 CHECK macro III-29
 CHKPT macro III-31
 CLOSE command + statement II-11
 CLOSE macro III-29
 CNTRL macro III-29
 Code translation table I-08
 COL statement (ESERV) II-35
 Command control block IV-07
 Communication region:
 partition (COMREG) IV-17
 system (SYSCOM) IV-13
 Component Installation (MSHP) V-40
 COMREG IV-17
 COMRG macro III-31
 Condense function, librarian II-25
 Condense automatic II-26

Condition codes I-06
 Console buffering table IV-40
 Control registers allocation I-13
 Control registers assignment of fields I-13
 Control and workblocks for
 channel program fixing IV-42
 Conversion hex to decimal I-23
 Conversion virtual to real address IV-88
 COPY (MSHP) V-69
 COPY blocks, overview IV-84
 COPY blocks, CCB, layout IV-85
 COPY blocks, CCW, layout IV-86
 COPY blocks, MAIN replica IV-87
 COPY blocks, add. replica IV-87
 COPY blocks, Didal IV-87
 COPY blocks, Didal entry IV-87
 COPY functions, librarian II-28
 COPY functions, CIL II-28
 COPY functions, RL II-29
 COP functions, SL II-29
 COPY functions, PL II-30
 COPY functions, definition of .. II-30
 COPY functions, definition and creation II-31
 COPY functions, merge II-32
 COPY functions, merge directions II-34
 Corequisite PTF application V-54
 CORGZ program, functions II-28
 CORRECT statement (MSHP) V-69
 CORRECT stmt. requirements V-57
 Correct the invalidation of a
 recorded fix V-59
 Correction to CIL V-57
 Correction to RL V-58
 Correction to E. macros V-58
 Correction to A. macros V-59
 CPCLOSE macro III-31
 CREATE statement (MSHP) V-70
 Cross partition ECB (XECB) table IV-47
 CRT constant table IV-96
 CSERV program, functions II-26
 CSW (channel status word) I-17

D

DASD standard labels, format 1 III-09
 DASD standard labels, format 2 III-13
 DASD standard labels, format 3 III-17
 DASD standard labels, format 4 III-18
 DASD standard labels, volume III-07
 Data management and system-
 control macros III-23
 DATE statement II-11
 Declarative macros III-23
 DEF command II-02
 DEFINE statement (MSHP) V-83
 Define the Lock (DTL) IV-27
 DEL command II-02
 DEL statement (ESERV) II-35
 Delete functions, librarian II-25
 DELETE statement (MSHP) V-86
 Density data IV-46
 DEQ macro III-31
 DETACH macro III-31
 Device type macros II-42
 DFR macro III-23
 DIB (Disk Information Block) IV-48
 DIDAL block and entry IV-87
 DIMOD macro III-23
 Directory entry, layout of IV-92
 DISEN macro III-29
 Disk Information Block. IV-48
 Diskette standard labels, HDR1 III-22

INDEX (. . . . Cont'd) D (. . . . Cont'd)

Diskette standard labels, volume III-21
 DLA command II-02
 DLBL statement II-11
 DLF command II-03
 D /NT macro III-23
 DOSVSDMP and Stand-Alone Dump V-23
 DOSVSDMP creating SA Dump program V-23
 DOSVSDMP example for job control V-23
 DOSVSDMP executing SA Dump program V-23
 DOSVSDMP printing SA Dump output V-25
 DOSVSDMP Hard Wait Codes V-26
 DPD command II-03
 DPDTAB (page data set table) IV-79
 DRMOD macro III-23
 DSERV program, functions II-26
 DSPLY command II-12
 DSPLY macro III-29
 DSPLY statement (ESERV) II-35
 DSPCH statement (ESERV) II-35
 DTF table, type codes III-119
 DTFCD macro III-23
 DTFCD reader III-41
 DTFCD punch III-44
 DTFCD combined reader/punch III-46
 DTFCN III-49
 DTFCN macro III-24
 DTFCP, disk=yes III-113
 DTFCP, disk=no III-116
 DTFCP, disk=parameter omitted III-118
 DTFDA III-72
 DTFDA extension III-77
 DTFDA macro III-24
 DTFDI III-111
 DTFDI macro III-24
 DTFDR III-50
 DTFDR macro III-24
 DTFDU III-103
 DTFDU macro III-25
 DTFIS, add III-83
 DTFIS, addrtr III-96
 DTFIS, load III-79
 DTFIS, retrve random III-89
 DTFIS, rtvse sequential III-93
 DTFIS, macro III-25
 DTFMR III-53
 DTFMR macro III-25
 DTFMT, data files III-56
 DTFMT, work files III-64
 DTFMT, macro III-26
 DTFOR III-51
 DTFOR macro III-26
 DTFPH, macro III-26
 DTFPH, DAM-files III-108
 DTFPH, diskette III-109
 DTFPH, magnetic tape III-105
 DTFPH, sequential disk III-106
 DTFPR III-47
 DTFPR macro III-26
 DTFPT macro III-27
 DTFSD, data files III-65
 DTFSD, work files III-70
 DTFSD, macro III-26
 DTL (define the Lock) IV-27
 DTL macro III-31
 DUMOD macro III-27
 DUMP command III-12
 DUMP statement (MSHP) V-70
 DUMP macro III-31
 DVCDN command II-12
 DVCUP

E

EBCDIC/ASCII translation table IV-73
 ECB (event, control block) IV-47
 END card, format II-45
 END command II-12
 END statement (ESERV) II-35
 ENDFL macro III-29
 ENQ macro III-31
 ENTER command II-12
 ENTRY statement II-23
 EOJ macro III-31
 ERBLOC IV-52
 EREP V-04
 EREP, function V-04
 EREP, JCL V-05
 EREP, Logical units V-05
 EREP, Keywords V-06
 EREP, examples V-09
 EREP, abbreviations V-10
 ERET macro III-29
 ERPIB IV-51
 Error bytes in low real storage V-20
 Error recovery block (ERBLOC) IV-52
 Error recovery proc. info. block IV-51
 Error queue entry IV-52
 ESD card, format II-44
 ESERV program II-35
 ESERV control statements II-35
 ESERV example II-36
 ESETL macro III-29
 Event control block (ECB) IV-47
 EXCP macro III-29
 EXEC command + statement II-12
 EXIT macro III-31
 EXTENT statement II-13
 Extents for MSHP History File V-30
 EXTRACT macro III-31

F

FCEPGOUT macro III-31
 Feature Installation (MSHP) V-47
 FEOV (D) macro III-29
 FETCH macro III-32
 FHB, layout IV-43
 Fix List Block (FLB) IV-44
 Fix List Header Block (FHB) IV-43
 Fix Request Block (FRB) IV-44
 File Labels, standard dasd III-09
 File Labels, standard tape III-03
 FLB (Fix List Block) IV-44
 FOPT macro, supervisor II-38
 FRB (Fix Request Block) IV-44
 FREE command II-13
 FREE macro III-32
 FREEVIS macro III-32

G

GENCATALS statement (ESERV) II-35
 GENDTL macro III-32
 GENEND statement (ESERV) II-35
 General Instructions I-01
 GENIORB macro III-29
 GENL macro III-32
 GET macro III-29
 GETIME macro III-32
 GETVIS macro III-32

INDEX (. . . Cont'd)

H

Hard and Softwait Codes V-18
 Hard Wait Codes DOSVDMP V-26
 HDR1 Label, diskette III-22
 Hexadecimal + decimal conversion I-23
 History File (MSHP) V-30
 HOLD command II-13

I

ID command + statement II-13
 IGNORE command II-13
 IJBPU macro III-32
 IFCEREP1 V-04
 IFCOFFLD V-04
 Imperative macros III-29
 INCLUDE statement II-23
 Input/Output Request Block IV-10
 INCORPORATE statement (MSHP) V-70
 INSERT statement (MSHP) V-86
 INSTALL statement (MSHP) V-71
 Instruction code, assembler I-05
 Instruction code, extended mnemonic I-04
 Instruction code, formats I-12
 Instruction code, general I-01
 Instruction code, decimal I-02
 Instruction code, control I-02
 Instruction code, I/O I-03
 Instruction code, floating point I-03
 Internal Resource Table (RETAB) W-66
 Interruption code, external I-19
 Interruption code, I/O I-19
 Interruption code, machine check I-18
 Interruption code, program I-19
 Interruption code, supervisor call I-19
 Interval timer request entry in TCB IV-80
 IOTAB macro, supervisor II-40, IV-01
 I/O table interrelationship IV-33
 IORB (I/O Request Block) IV-10
 IORB macro III-29
 IPL control statements II-01
 ISMOD macro III-27
 ITREQ IV-80

J

JDUMP macro III-32
 JIB (Job Info Block) IV-37
 Job Accounting Interface Common Table IV-71
 Job Accounting Interface Partition Table IV-72
 JOBCOM macro III-32
 Job Control Statements summary II-08
 Job Control Overview II-06
 Job Information Block (JIB) IV-37
 JOB statement II-13

K

L

Labels, standard dsdd III-07
 Labels, standard diskette III-21
 Labels, standard tape III-01
 LBRET macro III-29
 LFCB command II-13
 LFCB macro III-32
 LIBDEF command + statement II-13
 LIBDROP command + statement II-14
 LIBLIST command + statement II-14
 LLB (Locate List Block) IV-45
 LPB (Line Pointer Block) IV-45
 Librarian, copy function II-28
 Librarian, maintenance function II-25
 Librarian, service function II-26

Line Mode Table IV-41
 Line Pointer Block IV-45
 Linkage Editor control statements II-23
 LIOCS module name versus options:
 CDMOD III-35
 DIMOD III-36
 DRMOD III-36 **DU MOD III-36**
 ISMOD III-40
 MRMOD III-37
 MTMOD III-37
 ORMOD III-38
 PRMOD III-38
 PTMOD III-40

LIST statement (MSHP) V-72
 LISTIO command + statement II-14
 LITE macro III-29
 LOAD macro III-32
 Locate List Block IV-45
 LOCK macro III-32
 LOCKTAB entry IV-27
 LOG command II-14
 Logical Transient Key (LTK) IV-25
 Logical Transient Owner ID (LTID) IV-25
 Logical unit assignment with MSHP V-64
 Logical Unit Block (LUB) IV-34
 LOOKUP statement (MSHP) V-72
 LSERV program II-37
 LTID (Logical trans. owner ID) IV-25
 LTK (Logical transient key) IV-25
 LUB (Logical unit block) IV-34
 LUCB command II-14
 LVTOC program II-37

M

Machine instructions I-01
 Macros, declarative III-23
 Macros, imperative III-29
 Macros, system control III-31
 Main Replica Block IV-87
 Main Storage assignment, perm. I-14
 MAINT program, functions II-25
 MAP command II-15
 MAPBDY macro III-32
 MAPPSID macro III-32
 MERGE, function II-32
 MERGE, operation, direction of transfer II-34
 MICRDTF address + pointers IV-50
 MODDTL macro III-33
 MODE command II-15
 Modules, names III-35
 MRMOD macro III-28
 MSG command II-15
 MSHP-Maintain System History Program V-27
 MSHP processing overview V-29
 MTC command + statement II-15
 MTMOD macro III-28
 MVCOM macro III-33

N

NEWVOL command II-15
 NOLOG command II-15
 Notational Conventions (MSHP) V-62
 NOTE macro III-29
 Number symbols (explanation of) V-30

O

OLTEP, requirements V-01
 OLTEP, options V-92
 OLTEP, examples V-03
 OPEN (R) macro III-29
 OPTION statement II-15

INDEX (. . . Cont'd) O (. . . Cont'd)

- ORMOD macro III-28
 OVEND command + statement II-17
 OWNER Element IV-27
- P**
- Page data set format IV-89
 Page data set table (DPDTAB) IV-79
 Page frame table entry (PFTE) IV-81
 PAGEIN macro III-33
 Page out queue entry IV-80
 PAGETAB IV-82
 Partition communication region IV-17
 Partition control block (PCB) IV-29
 Partition control blocks interrelationship IV-28
 Partition identification key (PIK) IV-35
 Partition identifier string (PIDSTR) IV-66
 Partition selection string (PSS) IV-66
 PAUSE command + statement II-17
 PCB IV-29
 PCB address table (PCBATAB) IV-66
 PDZAP, system requirements V-21
 PDZAP, executing of V-21
 PDUMP macro III-33
 Permanent main storage assignm. I-14
 PERSONALIZE statement (MSHP) V-74
 PERSONALIZE the system history V-35
 PFIX macro III-33
 PFREE macro III-33
 PHASE statement II-23
 Physical unit block (PUB) IV-55
 PIB (program info block) IV-30
 PIB2TAB IV-31
 PIDSTR (partition id string) IV-66
 PIK (partition id key) IV-35
 POINTN(S)(W) macro III-30
 POST macro III-33
 PRMOD macro III-28
 Program information block (PIB) IV-30
 PIB-Extension IV-31
 Program Status Word (PSW) I-16
 PRTOV macro II-17
 PTRY command II-17
 PSERV program, functions II-27
 PSS (partition selection string) IV-66
 PSW I-16
 PTF statement (MSHP) V-86
 PTMOD macro III-28
 PUB (Physical unit block) IV-55
 PUB ownership table IV-56
 PUB2 entry addressing IV-57
 PUB2 entry formats dasd IV-58
 PUB2 entry formats tape IV-58
 PUB2 entry formats ur + unsupported IV-58
 PUB2 entry formats 3540 diskette IV-60
 PUB2 entry formats 3800 IV-61
 PUB2 entry formats 3886 OCR IV-60
 PUB2 entry formats 3890/3895 IV-60
 PUT (R) macro III-30
- Q**
- R**
- RAS Linkage area IV-26
 RCB (resource control block) IV-47
 RCB macro III-33
 RC command II-17
 RDLIN macro III-30
 READ macro III-30
 REALAD macro III-33
 Reallocation function, librarian II-26
 Recorder File Table (RF) IV-62
 Record Local APAR Fixes V-57
 REJECT statement (MSHP) V-87
 Relationship fetch/load contr. blocks IV-36
 Relationship control + workblocks IV-42
 Release 34 component installation V-53
 RELEASE macro III-33
 RELPAG macro III-33
 RELSE macro III-30
 Remove local APAR fixes (MSHP) V-57
 REMOVE statement (MSHP) V-75
 RENAME functions, librarian II-25
 REP card, format II-45
 REP statement (ESERV) II-36
 REPLACE statement (MSHP) V-88
 REPLICA block IV-90
 REPLID command II-17
 REQID IV-25
 RESCEN macro III-30
 RESERVE command II-17
 RESET command + statement II-17
 RESIDENCE statement (MSHP) V-75
 Resource control Block (RCB) IV-47
 Resource table internal (RETAB) IV-66
 RESTORE statement (MSHP) V-76
 Restore System Standalone (MSHP) V-36
 RETAB IV-66
 RETRACE statement (MSHP) V-77
 RETURN macro III-33
 REVOKE statement (MSHP) V-77
 RF table IV-62
 RHG (replica header block) IV-90
 RID (routine identifier) IV-93
 RLD card, format II-45
 ROD command II-18
 Routine Identifier IV-93
 RPS, DTF/module relationship III-120
 RPS, DTF/extension layout III-121
 RSERV program, functions II-26
 RST statement (ESERV) II-36
 RSTRT statement II-18
 RUNMODE macro III-33
- S**
- Save areas IV-32
 SAVE macro III-33
 SDAID program requirements V-11
 SDAID program restrictions V-11
 SDAID how to execute from oper.cons. V-11
 SDAID commands V-12
 SDAID path diagram for AREA cmd. V-13
 SDAID path diagram for TRACE cmd. V-14
 SDAID path diagram for OUTDEV cmd. V-16
 SECTVAL macro III-30
 Segment and page table IV-78
 Select function control statement V-78
 Sense bytes I-24
 SEOV macro III-30
 Service functions librarian, display II-26
 Service functions librarian, punch II-27
 Service functions librarian, dspch II-27
 SET IPL command II-04
 JCL command II-18
 SETDEF macro III-30
 SETDF command II-18
 SETFL macro III-30
 SETIME macro III-33
 SETL macro III-30
 SETMOD command II-18
 SETPFA macro III-33
 SETPRT command II-19
 SETT macro III-33
 SIZE command II-19
 Share virtual area (SVA) IV-91

INDEX (. . . Cont'd) S (. . . Cont'd)

SMCB (storage managm.contr.block) IV-12
 Soft and Hardwait Codes V-18
 SSERV program, functions II-27
 Standalone Dump V-23
 Standalone system install. procedure V-36
 START command II-19
 STDOPT command + statement II-19
 STOP command II-21
 Storage assignment, permanent I-14
 Storage Management Control Block IV-12
 Storage protection key IV-35
 Storage requirements of MSHP V-29
 STXIT macro III-33
 SUBSID macro III-33
 Supervisor Call Codes IV-03
 Supervisor macros II-38
 Supervisor storage allocation IV-01
 SUPVR macro, supervisor II-38
 SVA command II-04
 SVA (shared virtual area) IV-91
 SYS command II-05
 SYSCOM (syst. comm. region) IV-13
 System control macros III-31

T

Tape standard labels III-01
 file (ASCII) III-05
 file (EBCDIC) III-03
 volume (ASCII) III-02
 volume (EBCDIC) III-01
 Task Control Block (TCB) IV-65
 Task Identifier (TID) IV-35
 Task Identifier String (TIDSTR) IV-67
 Task Information Block (TIB) IV-64
 Task Selection ~~CL~~Block Interrelationship IV-68
 Task Selection String (TSS) IV-66
 Task Status Flags IV-69
 Task Timer Table (TTTAB) IV-80
 TCB (Task Control Block) IV-65
 TECB macro III-33
 TEST macro III-33
 TIB (Task Info Block) IV-64
 TIB address table (TIBATAB) IV-67
 TID (Task ID) IV-35
 TIDSTR (Task ID String) IV-67
 TLBL statement II-21
 TPBAL command II-21
 TPIN macro III-33
 TPOUT macro III-33
 Tracing of 4331 Comm. Adapter V-17
 Track Hold Table IV-40
 Translation Control Block (CCWTCB) IV-83
 Translation Control + copy blocks IV-84
 TRUNC macro III-30
 TSS (Task Selection String) IV-66
 TTIMER macro III-33
 TTTAB IV-80
 TXT card, format II-44

U

UCS command II-22
 UNBATCH command II-22
 UNDO statement (MSHP) V-79
 UNLOCK command II-22
 UNLOCK macro III-34
 UPDATE, feature libraries (MSHP) V-48
 UPDATE, source statement library II-26
 UPGRADE, statement (MSHP) V-79
 UPSI Statement II-22

V

VER Statement (ESERV) II-35
 VERIFY statement (MSHP) V-88
 VIRTAD macro III-34
 Virtual to real address, conversion IV-88
 VOLUME command II-22
 VOLUME labels, standard dasd III-07
 VOLUME labels, standard diskette III-21
 VOLUME labels, standard tape III-01
 VTAM address vector table IV-94

W

WAIT(F) macro III-30
 WAITM macro III-34
 Workfiles, for CORRECT + UNDO (MSHP) V-57
 WRITE macro III-30

X

XECB table IV-47
 XECBTAB macro III-34
 XPOST macro III-34
 XWAIT macro III-34

Y

Z

ZONE statement II-22
 /+ statement II-22
 /* statement II-22
 /& statement II-22
 * statement II-22

THIS PAGE HAS BEEN ADDED FOR YOUR OWN NOTES

THIS PAGE HAS BEEN ADDED FOR YOUR OWN NOTES

THIS PAGE HAS BEEN ADDED FOR YOUR OWN NOTES

THIS PAGE HAS BEEN ADDED FOR YOUR OWN NOTES

THIS PAGE HAS BEEN ADDED FOR YOUR OWN NOTES

THIS PAGE HAS BEEN ADDED FOR YOUR OWN NOTES

LY339101-0

VSE/Advanced Functions Handbook (File No. S370/4300-40) Printed in U.S.A. LY339101-0



International Business Machines Corporation
Data Processing Division
1133 Westchester Avenue, White Plains, N.Y. 10604

IBM World Trade Americas/Far East Corporation
Town of Mount Pleasant, Route 9, North Tarrytown, N.Y., U.S.A. 10591

IBM World Trade Europe/Middle East/Africa Corporation
360 Hamilton Avenue, White Plains, N.Y., U.S.A. 10601

This sheet is for comments and suggestions about this manual. We would appreciate *your* views, favorable or unfavorable, in order to aid us in improving *this* publication. This form will be sent directly to the author's department. Please include your name and address if you wish a reply. Contact your IBM branch office for answers to technical questions about the system or when requesting additional publications. Thank you.

Your comments* and suggestions:

* We would especially appreciate your comments on any of the following topics:

Clarity of the text	Accuracy	Index	Illustrations	Appearance	Paper
Organization of the text	Cross-references	Tables	Examples	Printing	Binding



BUSINESS REPLY MAIL

FIRST CLASS

PERMIT NO. 40

ARMONK, N.Y.

POSTAGE WILL BE PAID BY ADDRESSEE:

International Business Machines Corporation
Department 812 BP
1133 Westchester Avenue
White Plains, New York 10604

NO POSTAGE
NECESSARY
IF MAILED
IN THE
UNITED STATES

