ROVE EXTENSIONS

is branch contains a program that you can Jex to extend the ROVE mode in
MAS to include some additional options. The SUPERCOPY and OUTLINE output
programs were written and submitted by Thomas Almy. THANK YOU, Tom.

You can edit the AUX ROVE and AUXCMD Jex leafs to add your own extensions
also. See the AUX ROVE HELP leafs for more info on all the added options in
the program of this branch.

AUX ROVE - Jexing this adds Auxiliary options to ROVE's U command

```
LANG SYS
NEWLINE ".... Loading AUX ROVE..." STOUT

'PAGET : NEWPAGE TOGPRINT CRLFOUT TRUEWF .

'SUPERCOPY       KJEX           ; Jex in Tom Almy's Super Copy program
"OUTLINE OUT"    KJEX           ; Jex in Tom Almy's Outline Output program
'NEWVIEW         KJEX           ; Jex in Tom Almy's New VIEW program
'KEYFIND         KJEX           ; Jex in Tom Almy's partial key search

'NLT : NEWLINE 4 SPSOUT .

'AUXMENU :
  NLT "? - Show this option list" STOUT
  NLT "V - View the current Title neighborhood" STOUT
  NLT "F - Find Partial Key" STOUT
  NLT "K - Print Keys in Branch Below" STOUT
  NLT "T - Print Titles in Branch Below" STOUT
  NLT "E - Print FormFeed (Eject)" STOUT
  NLT "O - Output Outline Formatted" STOUT
  NLT "C - Copy Branch or Topic" STOUT
  NLT "P - Protect current stem as Read Only" STOUT
  NLT "D - Delete leaf of current stem" STOUT
  NLT "S - Set Page size, Line skip, or Indent" STOUT
  NLT "U - Utiltiy Jobs Menu" STOUT
  NLT "R - Return to ROVE" STOUT .

'AUXOPS : NEWLINE "==== AUXILIARY OPTIONS FOR ROVE ====" STOUT
  AUXMENU NEWLINE EXECSTAT 768 WAND WO0=
     IFSO NLT "MORE HELP (N)?" STOUT NOYES
        IFSO "AUX ROVE HELP 1" KSHOW
           NEWLINE "==== Type any key to continue " STOUT YESNO
           "AUX ROVE HELP 2" KSHOW
        .IFSO
     .IFSO .

'INKEY : WCIN DUPW WCOUT WCCVTUC .

'SETCMD : "(P - Page size, L - Line skip, I - Indent):" STOUT
  INKEY
  WOCASES
  'P ASCII WOCASE "AGE SIZE: " STOUT WOIN TO PGSIZE        .WOCASE
  'L ASCII WOCASE "INE SKIP: " STOUT WOIN TO SKIP          .WOCASE
  'I ASCII WOCASE "NDENT SIZE: " STOUT WOIN TO INDSIZE     .WOCASE
           OTHERS BEEPOUT NEWLINE
  .WOCASES .

'CCMD : "(B - Branch, T - Topic):" STOUT
  INKEY
  WOCASES
  'B ASCII WOCASE "RANCH" STOUT BRANCH-COPY .WOCASE
  'T ASCII WOCASE "OPIC" STOUT TOPIC-COPY   .WOCASE
           OTHERS BEEPOUT NEWLINE
  .WOCASES .

'UTMENU : "UTILITY JOBS" KFIND IFSO MENU .IFSO .

  'XCMD KJEX
```


AUXCMD - Auxiliary ROVE command

```
'AUXCMD : NEWLINE
  LOOP 13 WCOUT 20 SPSOUT 13 WCOUT 'AUX: STOUT INKEY
```